

AWS DataSync – Copy Data from an EC2 SMB Share to Amazon S3

To Begin with the Lab

Summary of the Lab

In this lab, **AWS DataSync** was demonstrated in a fully cloud-based setup by using an **Amazon EC2** instance as a simulated on-premises SMB server. The EC2 instance was launched, configured as a shared storage server, and given files to transfer. A DataSync agent was then created using the **Amazon EC2** option, activated, and connected to the shared folder through SMB. After that, a DataSync task was created to copy data from the SMB share to an **Amazon S3** bucket, with the IAM role generated automatically. The transfer was started and verified by checking the task history and confirming that the files appeared in the S3 bucket.

Understanding AWS DataSync for Cloud File Transfers

AWS DataSync is an online data transfer service that automates and speeds up moving data between storage systems such as **Amazon S3**, **Amazon EFS**, **Amazon FSx**, and SMB or NFS file servers. It exists so you do not have to copy files manually when moving data between storage locations. In this lab, the source was an SMB share running on an **Amazon EC2** instance, and the destination was **Amazon S3**. The benefit is secure, fast, and repeatable file movement with very little manual work.

Example:

A Windows **EC2** server named Storage Server stores 11 files in a shared folder named data. The team wants to move those files to a bucket named cloud storage 02 without using manual upload and download steps. DataSync reads the SMB share and copies the files into S3, then the same files appear in the bucket after the transfer completes.

Lab Steps

Step 1 – Create the storage server EC2 instance

- Sign in to the **AWS Management Console**.
- Open **Amazon EC2**.

Resources

You are using the following Amazon EC2 resources in the United States (N. Virginia) Region:

Instances (running)	1	Auto Scaling Groups	0	Capacity Reservations	0
Dedicated Hosts	0	Elastic IPs	2	Instances	2
Key pairs	31	Load balancers	0	Placement groups	0
Security groups	39	Snapshots	0	Volumes	2

Launch instance

To get started, launch an Amazon EC2 instance, which is a virtual server in the cloud.

[Launch instance](#) [Migrate a server](#)

Note: Your instances will launch in the United States (N. Virginia) Region

Instance alarms

0 in alarm 0 OK 0 insufficient data

[View in CloudWatch](#)

Scheduled events

United States (N. Virginia)

Service health

[AWS Health Dashboard](#)

Zones

Zone name	Zone ID
us-east-1a	use1-az4
us-east-1b	use1-az6
us-east-1c	use1-az1
us-east-1d	use1-az2
us-east-1e	use1-az3
us-east-1f	use1-az5
us-east-1-atl-2a	use1-atl2-az1

[Enable additional Zones](#)

EC2 cost

Date range: Past 6 months Region: Global

Total cost

Regions

[Analyze your costs in Cost Explorer](#)

Account attributes

Default VPC [vpc-099792461c7d0a616](#)

Settings

Data protection and security

Allowed AMIs

Zones

EC2 Serial Console

Default credit specification

Managed resources

EC2 console preferences

Explore AWS

- Launch a new instance named **Storage Server**.
- Use a **Windows Server 2019** AMI for the shared storage server.

Launch an instance

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

Name and tags

Name: [Add additional tags](#)

Application and OS Images (Amazon Machine Image)

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Search our full catalog including 1000s of application and OS images

Recents My AMIs Quick Start

Amazon Linux macOS Ubuntu **Windows** Red Hat SUSE Linux Debian

Amazon Machine Image (AMI)

Microsoft Windows Server 2019 Base [Free tier eligible](#)

Virtualization: hvm ENA enabled: true Root device type: ebs

Description

Microsoft Windows 2019 Datacenter edition, [English]

Summary

Number of instances: 1

Software Image (AMI): Microsoft Windows Server 2019 ...read more

Virtual server type (instance type): t3.small


Firewall (security group): New security group

Storage (volumes): 1 volume(s) - 30 GiB


Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

[Cancel](#) [Launch instance](#) [Preview code](#)

- Select **t3.small** for the instance type for lab purpose.
- Keep the security group open for all traffic during the lab.



- Create and add **Allow All Traffic** rule as well.



- Launch the instance and wait for it to become available.

Step 2 – Configure the Windows shared folder

- Connect to the EC2 instance through RDP.
- Download the remote desktop file and open it.
- Click on get password and paste your .pem file.

EC2 > Instances > i-04153be8577c5862a > Connect to instance

Instance ID: i-04153be8577c5862a (Storage Server)

VPC ID: vpc-099792461c7d0a616

Security groups: sg-0e0e25756447c708a (launch-wizard-20)

IAM role: -

SSM Session Manager **RDP client** EC2 serial console

Instance ID: i-04153be8577c5862a (Storage Server)

Connection Type: **Connect using RDP client**

You can connect to your Windows instance using a remote desktop client of your choice, and by downloading and running the RDP shortcut file below:

Download remote desktop file

When prompted, connect to your instance using the following username and password:

Public DNS: ec2-54-145-62-1.compute-1.amazonaws.com

Username: Administrator

Password: **Get password**

If you've joined your instance to a directory, you can use your directory credentials to connect to your instance.

Cancel

- Click on Decrypt Password and paste it.

EC2 > Instances > i-04153be8577c5862a > Get Windows password

Get Windows password info

Use your private key to retrieve and decrypt the initial Windows administrator password for this instance.

Instance ID: i-04153be8577c5862a (Storage Server)

Key pair associated with this instance: June-2026-us

Private key: Either upload your private key file or copy and paste its contents into the field below.


Upload private key file

June-2026-us.pem (1.68 KB)


Private key contents: -----BEGIN RSA PRIVATE KEY-----

Cancel **Decrypt password**


- Paste the password in the panel to connect to the Server.
- Log in as the administrator user.




- Change the administrator password, for that Open Server Manager → Tools and Open Computer Management.




- Now Go to **Local Users and Groups** → **Users** → Right-click on **Administrator** → Click on **Set Password**.




- Click **Proceed** and enter your new password and click **OK**.




- Now open **C: Drive** and create a shared folder named **data**.




- Open the folder **Properties** by Right-clicking on it and go to **sharing** tab → **Advanced Sharing** and click on **Share this Folder**.



- Click on **Permissions** and give everyone **full control permissions** and click **Apply** and **OK**.




- Add a few test files into the shared folder.




Step 3 – Create and activate the DataSync agent


- Open **AWS DataSync**.
- Choose the option for transferring data between **on-premises storage** and **AWS**.




- Choose Source location as **Server Message Block (SMB)** and Destination as **Amazon S3**.
- Choose it as **Basic** Task Mode.
- Select **Amazon EC2** as the hypervisor type.
- Now click on **Learn More**.



- Use the AWS official AMI details for the DataSync agent.



- Now configure AWS on your local system as we did in earlier lab by running “aws configure” and then run the AMI command from the official site.



- Now copy this AMI ID and keep it somewhere safe as we are going to make our DataSync Agent with this AMI ID.
- Now visit the site and copy the following command and replace the required values.

The screenshot shows the AWS DataSync User Guide page for deploying an Amazon EC2 agent. The main content area includes a tip about avoiding charges for transferring across Availability Zones and a list of steps to follow. The first step is to copy the following URL:

```
https://console.aws.amazon.com/ec2/v2/home?region=agent-region#LaunchInst
```

The URL contains two placeholders highlighted in red:

- agent-region*: Replace with the Region where you want to deploy your agent.
- ami-id*: Replace with the DataSync AMI ID that you obtained.

The subsequent steps are:

- Paste the URL into a browser.
- The Amazon EC2 instance launch page in the AWS Management Console displays.
- For **Instance type**, choose one of the recommended Amazon EC2 instances for DataSync.
- For **Key pair**, choose an existing key pair, or create a new one.
- For **Network settings**, choose **Edit** and then do the following:

- And paste the modified URL to the browser and press enter.

The screenshot shows a web browser with the AWS Management Console URL in the address bar. The URL is `https://console.aws.amazon.com/ec2/v2/home?region=us-east-1#LaunchInstanceWizard:ami=ami-06643caf2bf83e9a`. The browser also shows a large digital clock displaying 1:28 and the text "Never give up!".

- Enter the name: DataSync-Agent.

Launch an instance Info

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

Name and tags Info

Name: DataSync-Agent

Application and OS Images (Amazon Machine Image) Info

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Search our full catalog including 1000s of application and OS images

AMI from catalog Recents My AMIs Quick Start

Name: aws-datasync-2.0.1784035868.1-x86_64-gp2 Verified provider

Description: aws-datasync-2.0.1784035868.1-x86_64-gp2

Image ID: ami-06643caf2bfb83e9a

Username: root (Check with the AMI provider.)

Published: 2026-07-14T14:21:17.000Z Architecture: x86_64 Virtualization: hvm Root device type: ebs ENA Enabled: Yes

Summary

Number of instances: 1

Software Image (AMI)
aws-datasync-2.0.1784035868.1...[read more](#)
ami-06643caf2bfb83e9a

Virtual server type (instance type)
m7i-flex.large

Firewall (security group)
New security group

Storage (volumes)
1 volume(s) - 80 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

[Cancel](#) [Launch instance](#) [Preview code](#)

- For the agent, we must provide minimum of 8GB RAM so we must change the instance and then configure it with key pair.

Instance type Info | [Get advice](#)

Instance type: m7i-flex.large Free tier eligible

On-Demand Windows base pricing: 0.18316 USD per Hour On-Demand Ubuntu Pro base pricing: 0.09926 USD per Hour
On-Demand RHEL base pricing: 0.12456 USD per Hour On-Demand SUSE base pricing: 0.15206 USD per Hour
On-Demand Linux base pricing: 0.09576 USD per Hour

[Additional costs apply for AMIs with pre-installed software](#)

Key pair (login) Info

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - required: June-2026-us [Create new key pair](#)

Network settings Info

VPC - required: vpc-099792461c7d0a616 (default) [Create new VPC](#)

Subnet: No preference [Create new subnet](#)

Availability Zone: No preference [Enable additional zones](#)

Summary

Number of instances: 1

Software Image (AMI)
aws-datasync-2.0.1784035868.1...[read more](#)
ami-06643caf2bfb83e9a

Virtual server type (instance type)
m7i-flex.large

Firewall (security group)
New security group

Storage (volumes)
1 volume(s) - 80 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

[Cancel](#) [Launch instance](#) [Preview code](#)

- Now configure the Network settings and allow **All Traffic** from **Anywhere**.
- Launch the agent instance.

Launch an instance

This security group will be added to all network interfaces. The name can't be edited after the security group is created. Max length is 255 characters. Valid characters: a-z, A-Z, 0-9, spaces, and _-./@.#[]+=&()!\$*

Description - required [Info](#)

launch-wizard-22 created 2026-07-16T08:00:21.077Z

Inbound Security Group Rules

▼ Security group rule 1 (TCP, 22, 0.0.0.0/0)

Type [Info](#) Protocol [Info](#) Port range [Info](#)

ssh TCP 22

Source type [Info](#) Source [Info](#) Description - optional [Info](#)

Anywhere 0.0.0.0/0 e.g. SSH for admin desktop

▼ Security group rule 2 (All, All, 0.0.0.0/0)

Type [Info](#) Protocol [Info](#) Port range [Info](#)

All traffic All All

Source type [Info](#) Source [Info](#) Description - optional [Info](#)

Anywhere 0.0.0.0/0 e.g. SSH for admin desktop

Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from known IP addresses only.

Add security group rule

Summary

Number of instances [Info](#)

1

Software Image (AMI)

aws-datasync-2.0.1784035868.1...[read more](#)

ami-06645ca72bf85e9a

Virtual server type (instance type)

m7i-flex.large

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 80 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

Cancel Launch instance [Preview code](#)

- Activate the agent by entering its Public IPv4 address in DataSync and press **Get Key**.

Create agent

types view

Select the hypervisor platform for deploying your agent.

Amazon EC2

Create an EC2 instance using the AMIs provided in our User Guide. [Learn more](#)

Service endpoint

Endpoint type

Choose the service endpoint that this agent will connect to. [Learn more](#)

Public service endpoint in US East (N. Virginia)

Activation key

Activation securely associates the agent that you deployed with your AWS account. [Learn more](#)

Choose a method for obtaining your agent's activation key. [Learn more](#)

☒ Automatically get the activation key from your agent
Your browser will connect to your agent over HTTP to get a unique activation key.

☐ Manually enter your agent's activation key
Choose this option if you already have an activation key and need to enter it manually.

Agent address

When your DataSync agent has been deployed, enter its domain name or IP address. When you click **Get key**, your browser will connect to this address to get a unique activation key.

http://18.206.189.34

Make sure this address is accessible from your browser.

Cancel **Get key**

- The IP Address can be found by clicking on the Instance we have created.

The screenshot shows the AWS Management Console for the 'Instances' page. In the left-hand navigation pane, 'EC2' is selected. The main content area displays a list of instances. The 'DataSync-Agent' instance (ID: i-062a697a11ffcd5aa) is selected. Below the list, the 'Details' tab for this instance is open. A red box highlights the 'Public IPv4 address copied' status and the public IP address 18.206.189.36. Other details visible include the instance state (Running), instance type (m7i-flex.large), and various DNS and IP address information.


- The agent will be activated, Give name to your agent and click **Create Agent**.

The screenshot shows the 'Create agent' page in the AWS Management Console. The 'Activation key' section displays a success message: 'Successfully retrieved activation key from agent'. Below this, the 'Agent name' field is highlighted with a red box and contains the text 'Ag1'. At the bottom right, the 'Create agent' button is also highlighted with a red box. The page includes sections for 'Agent name - optional' and 'Tags - optional'.

- Create the agent and wait until it becomes active.


Step 4 – Create the S3 destination bucket

- Open **Amazon S3**.
- Create a new bucket named **amazon-datasync-ec2**.
- Confirm that the bucket is empty before the transfer.



Step 5 – Create the DataSync task

- Return to AWS DataSync.
- Click on **Create task**.



- Create a new location for the source.
- Select **SMB** as the source type.
- Enter the **Public IP address** of the shared Storage Server.

Instances (1/4) Info

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IPv4 ...	Elastic
Build-Machine	i-03a0fa64c50198-99	Stopped	t3.micro	–	us-east-1b	–	–	–
server	i-00c40480f621ed74d	Stopped	t3.micro	–	us-east-1b	–	–	–
DataSync-Agent	i-062a697a11ffcd5aa	Running	m7i-flex.large	3/3 checks passed	us-east-1b	ec2-18-206-189-36.co...	18.206.189.36	–
Storage Server	i-04153be8577c5862a	Running	t3.small	3/3 checks passed	us-east-1a	ec2-100-24-36-100.co...	100.24.36.100	–

i-04153be8577c5862a (Storage Server)

Details | Status and alarms | Monitoring | Security | Networking | Storage | Tags

Instance summary Info

Instance ID: i-04153be8577c5862a

IPv6 address: –

Hostname type: IP name: ip-172-31-29-112.ec2.internal

Answer private resource DNS name: –

Public IPv4 address: 100.24.36.100 | [open address](#)

Instance state: Running

Private IP DNS name (IPv4 only): ip-172-31-29-112.ec2.internal

Instance type: t3.small

Private IPv4 addresses: 172.31.29.112

Public DNS: ec2-100-24-36-100.compute-1.amazonaws.com | [open address](#)

Elastic IP addresses: –

- Enter the SMB share name **/data**.

DataSync > Tasks > Create task

Step 3: Configure settings

Choose the location that you want to transfer data from

☒ Create a new location ☐ Choose an existing location

Configuration

Location type: Server Message Block (SMB)

Region: US East (N. Virginia) us-east-1
Transfers to or from SMB must stay in the current Region.

Agents
The agents you choose should have access to your SMB server.
Choose one or more agents: Ag1 (agent-0952570533df0d033a) Public - US East (N. Virginia) Basic mode

SMB server
Domain name or IP address of the SMB server.
172.31.29.112

Share name
Mount path exported by the SMB server or a subdirectory of that path, delimited with forward slashes (for example, /my-folder/sub-folder).
/data

Additional settings

- Choose **NTLM** as Authentication Type.
- Use **administrator** as the username.
- Enter the Windows password for the shared server we have configured earlier.

Authentication Info

Authentication type
DataSync authenticates with the SMB server using this method.

☒ NTLM ☐ Kerberos

ⓘ DataSync authenticates using a user name and a password that you provide. [Learn more about choosing a user name](#) that ensures sufficient permissions to files, folders and metadata.

User
User who has permission to access the SMB server.

administrator

Access configuration

☒ Specify a password ☐ Use a Secrets Manager secret

Password
Password of the user who has permission to access the SMB server.

KMS Key Arn (optional)
Enter an optional KMS Key ARN to encrypt your password.

Domain - optional
The name of the Windows domain that the SMB server belongs to.

- Select **Amazon S3** as the destination.
- Choose the bucket **amazon-datasync-ec2**.
- Keep the storage class as standard.
- Let DataSync auto-generate the IAM role by clicking on **Autogenerate** button.

Configuration

Location type
Amazon S3

Transfers from SMB can go to Amazon EFS, Amazon FSx, or Amazon S3.

Region
US East (N. Virginia) us-east-1
Transfers to or from SMB must stay in the current Region.

S3 URI
s3://amazon-datasync-ec2

S3 storage class
Choose a storage class you want your objects to be transferred into.

Standard

IAM role
Used to access your S3 bucket. [Learn more](#)

Choose a role with access to your S3 bucket

☒ Autogenerate

Tags - optional
A tag is a label that you assign to an AWS resource. Each tag consists of a key and an optional value.
No tags associated with the resource.

[Add new tag](#)

- Enter the name for the Task.
- Choose the Mode to **Basic**.
- Choose **Everything** for the Contents to Scan option.

Configure settings

Task mode Info
Your task options and performance might vary depending on the task mode you choose. Task mode can't be changed once you create this task. [See pricing details.](#)

☐ Enhanced
Transfer virtually unlimited numbers of objects with advanced metrics, more detailed logs, and higher performance than Basic mode. Currently available for transfers between S3 buckets, between S3 and other clouds when not using an agent, or between NFS or SMB servers and S3 using an Enhanced mode agent.

☒ **Basic**
Transfer objects within quotas on the number of files and objects in a dataset. Lower performance than Enhanced mode for most workloads. Requires an agent when copying to or from on-premises or other clouds.

Name - optional
Agent-EC2

Source data options Info
Contents to scan
Specify the data in your source location that you want to transfer to your destination.
Everything

Excludes - optional Info
Specify the files, objects, and folders that you don't want to transfer.
/folder-to-exclude or *.temp-file Add pattern

Transfer options

- Set Transfer mode to **Transfer all data**.
- Leave rest settings as default.

Transfer options

Transfer mode
Determines whether DataSync transfers only the data and metadata that differ between the source and the destination.
Transfer all data

Verification
Specify how and when DataSync checks the integrity of your data. DataSync always performs data integrity checks during a transfer.
Verify only transferred data

Bandwidth limit
Allocate the maximum network bandwidth to be utilized by this task.
☒ Use available

File and object handling

☒ Keep deleted files
Keep or delete data in your destination that isn't in your source. You can't deselect this option if you set Transfer mode to Transfer all data. [Learn more](#)

☒ Overwrite files
Modify or preserve your destination data when your source data (including metadata) changes. You can't deselect this option if you set Transfer mode to Transfer all data. [Learn more](#)

Additional settings

Schedule
Specify when you want this task to run.
Frequency
Not scheduled

- Create the task.

Step 6 – Start the transfer

- Open the DataSync task we have created.
- Start the task manually with **Start** → **Start with defaults**.

Agent-EC2

Overview

Task status: Available

Latest execution: -

Task mode: Basic

Task ARN: arn:aws:datasync:us-east-1:123456789012:task/task-0e972324246709dbf

Creation time: Jul 16, 2026, 3:38:03 PM GMT+5:30

Locations | Options | Schedule | Tags | Monitoring | Task executions

Source location

Location ID: loc-066873a3b3cea38d7

Region: US East (N. Virginia)

Type: Server Message Block (SMB)

Path: /data/

Creation Time: Jul 16, 2026, 3:38:02 PM GMT+5:30

Server: 172.31.29.112

Agents: agent-0952570533dfcd033a

SMB version: Automatic

Authentication type: NTLM

User: administrator

Secret: aws-datasyncloc-066873a3b3cea38d7-TgMYrC

Destination location

Location ID: loc-0ee01bbb72a4cb25c

Region: US East (N. Virginia)

Type: Amazon S3

Path: /

Creation Time: Jul 16, 2026, 3:38:03 PM GMT+5:30

S3 bucket: amazon-datasync-ec2

S3 storage class: Standard

S3 bucket IAM role: AWSDataSyncS3BucketAccess-amazon-datasync-ec2-d3649

- Wait for the transfer to finish.

Step 7 – Verify the transfer

- Open the task execution history.

Agent-EC2

Overview

Task status: Available

Latest execution: Jul 16, 2026, 3:52:15 PM GMT+5:30

Task mode: Basic

Creation time: Jul 16, 2026, 3:43:07 PM GMT+5:30

Task ARN: arn:aws:datasync:us-east-1:123456789012:task/task-071169190a392a4c0

Locations | Options | Schedule | Tags | Monitoring | **Task executions**

Task executions (2)

A task execution is an individual run of a DataSync task and contains information about the execution results.

Find task executions

Execution ID	Start time	Duration	Status	Data throughput	File throughput	Mode
exec-0d5ebcd86f763624	Jul 16, 2026, 3:52:15 PM GMT+5:30	2 seconds	Success	0 B/s	8.26 file/s	Basic
exec-076fb7505ed1812e1	Jul 16, 2026, 3:43:37 PM GMT+5:30	0 seconds	Error	0 B/s	0 file/s	Basic

- Confirm that the run completed successfully.

DataSync

Task executions
Tasks
Locations
Agents

exec-Od5ebbcd86f763624

[View logs in CloudWatch](#) [Edit](#) [Stop](#)

Overview

Execution status
Success

Start time
Jul 16, 2026, 3:52:15 PM GMT+5:30

Task ID
task-071169190a392a4c0

Duration
2 seconds

End time
Jul 16, 2026, 3:54:32 PM GMT+5:30

Task mode
Basic

Task execution ARN
arn:aws:datasync:us-east-1:123456789012:task/task-071169190a392a4c0/execution/exec-Od5ebbcd86f763624

Performance

Transferred
9 files

Skipped
0 files

Remaining
0 files

Verified
9 files

Data transferred
0 B

Data throughput
0 B/s

File throughput
8.26 file/s

Percent compressed
-

[Investigate with AI - new](#) 2026-07-16T10:22:15 > 2026-07-16T10:24:32 UTC timezone [Explore related](#)

Processing rate (file/s)
No data available. Try adjusting the dashboard time range.

Data throughput (MiB/s)
No data available. Try adjusting the dashboard time range.

Network throughput (Gbps)
No data available. Try adjusting the dashboard time range.

- Check the file count in the transfer summary.
- Open the S3 bucket.
- Refresh the bucket contents.
- Confirm that all files now appear in **Amazon S3**.

Amazon S3

amazon-datasync-ec2

[Objects](#) [Metadata](#) [Properties](#) [Permissions](#) [Metrics](#) [Management](#) [File systems - new](#) [Access Points](#)

Objects (9)

Objects are the fundamental entities stored in Amazon S3. You can use [Amazon S3 Inventory](#) to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. [Learn more](#)

☐	Name	Type	Last modified	Size	Storage class
☐	aws-datasync-metadata	aws-datasync-metadata	July 16, 2026, 15:54:16 (UTC+05:30)	0 B	Standard
☐	New Bitmap Image - Copy (2).bmp	bmp	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Bitmap Image - Copy (3).bmp	bmp	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Bitmap Image - Copy.bmp	bmp	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Bitmap Image.bmp	bmp	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Text Document - Copy (2).txt	txt	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Text Document - Copy (3).txt	txt	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard
☐	New Text Document - Copy.txt	txt	July 16, 2026, 15:54:15 (UTC+05:30)	0 B	Standard

Verification

- Verified that the Windows **EC2** storage server was created successfully.
- Verified that the shared folder data was created and populated with test files.
- Verified that the **AWS DataSync** agent was created and activated.
- Verified that the SMB source location pointed to the correct server and share.
- Verified that the destination bucket cloud storage 02 was created successfully.
- Verified that the DataSync task completed successfully.

- Verified that the files appeared in **Amazon S3** after the transfer.