

TVWebHook 1.0.68

TradingView Webhook Handler for CCXT / Phemex — Full Instruction Manual

1. Overview

TVWebHook 1.0.68 is a Flask-based webhook server that receives TradingView alerts and executes trades on Phemex using the CCXT library. It is designed to run on multiple computers with different API keys and sub-accounts.

Key features:

- Auto-sizing based on a percentage of free account balance
- Trade cooldown system (bars × timeframe in minutes)
- Multi-symbol watchlist with automatic learning of new symbols
- Startup visibility of positions and open orders
- Source website detection + auto-learning of new domains
- PC Name + SubAccount identity labeling on every log line
- Take Profit, Stop Loss, and Trailing Stop support
- Webhook can override symbol and lotsize (SymLotOverride)
- Friendly errors for size-too-small and wrong margin currency

2. Requirements

- Python 3.9 or higher (or use the portable .exe)
 - Packages: flask, ccxt, python-dotenv, colorama, waitress
 - A Phemex account with API Key and Secret
 - An environment file containing the API credentials
- ```
pip install flask ccxt python-dotenv colorama waitress
```

## 3. Configuration (configFile.json)

All settings are stored in **configFile.json**. If the file does not exist, the bot creates one using built-in defaults. See the Config Reference PDF for every key.

## 4. How to Run the Bot

1. Place API keys in the env file (example APIGoesHere.env):

```
PHEMEX_API_KEY=your_key_here
PHEMEX_SECRET=your_secret_here
```

2. Edit configFile.json (especially PC\_NAME, SUBACCOUNT\_NAME, SANDBOX\_MODE).

3. Start:

```
python TVWebHook_68_Portable.py
or TVWebHook_68_Portable.exe
```

On startup the bot loads config and keys, shows free balance, prints positions/orders for WATCH\_SYMBOLS, then listens on port 5000.

## 5. TradingView Alert Format

```
buy BTC/USDT:USDT
sell BTC/USD:BTC

{
 "message": "buy BTC/USDT:USDT",
```

```
"lotsize": 0.01
}
```

## 6. Webhook Override Priority

Controlled by **SymLotOverride** (see SymLotOverride Manual). Side follows BUY\_SELL\_MODE. TP/SL/trailing/cooldown always come from config.

## 7. Feature Details

**Auto-Sizing** — AUTO\_SIZE\_PERCENT of free balance (USDT for linear, base coin for inverse). Raised to exchange minimum.

**Trade Cooldown** — After a trade, new webhooks are blocked for COOLDOWN\_BARS × COOLDOWN\_TIMEFRAME\_MINUTES.

**Trailing Stop** — Optional percent or fixed distance; independent of TP/SL.

**Watch Symbols** — Startup snapshot for each entry; new webhook symbols are auto-saved.

**Identity** — Every log line: [PC\_NAME | SUBACCOUNT\_NAME].

## 8. Useful Endpoints

GET / — health check

GET /version — JSON of key settings

POST / — TradingView webhook

## 9. Multi-PC Setup

Each PC needs its own configFile.json (unique PC\_NAME / SUBACCOUNT\_NAME), its own .env with that account's keys, and the same .exe/.py. Match USE\_HEDGE\_MODE to the exchange account mode.