

TVWebHook 1.0.68

Webhook Override Manual — SymLotOverride

What SymLotOverride Does

The config key **SymLotOverride** controls whether a TradingView webhook is allowed to change the **symbol** and the **lotsize** used for the trade.

Everything else (side mode, TP/SL, trailing stop, cooldown, price improvement, etc.) still comes from config unless you later expand overrides.

Config setting

```
"SymLotOverride": true    // true  = webhook may set symbol + lotsize
                        // false = lock symbol + lotsize to config
```

When SymLotOverride = true

- Symbol: uses the symbol from the webhook message if present.
- Lotsize: uses the webhook lotsize if present and > 0.
- If lotsize is missing/empty → falls back to Auto-Sizing or MIN_LOT_SIZE.
- Exchange is re-initialized for that symbol (watchlist auto-learn runs).

When SymLotOverride = false

- Symbol is locked to the SYMBOL value in configFile.json.
- Lotsize from the webhook is ignored.
- Sizing uses Auto-Sizing (if on) or MIN_LOT_SIZE.
- The webhook still fires and still opens a trade — only symbol/lotsize are locked.

Message format and fallback

Each line of the webhook message is treated as a command:

```
buy BTC/USDT:USDT    → side = buy,  symbol = BTC/USDT:USDT
sell ETH/USDT:USDT   → side = sell, symbol = ETH/USDT:USDT
buy                  → side = buy,  symbol = SYMBOL from config (fallback)
```

If the webhook sends only buy or only sell (no symbol), the bot uses the default SYMBOL from config. The trade still runs.

Lotsize priority (when SymLotOverride = true)

1. Webhook lotsize (if present and > 0)
2. Else Auto-Sizing % of free balance (if USE_AUTO_SIZING = true)
3. Else MIN_LOT_SIZE

After that, the bot always raises size to the exchange minimum (and applies a coin-m floor when needed).