9 Move the toolrest in closer to reduce tool overhang. Go back to the spindle gouge to remove the waste from the bottom of the bowl. Check the depth as you go. Remember that you will be working on the bottom curve and the underside later on

10 Use the scraper to finish the inside curve and the base of the bowl. Make sure this tool is sharp to reduce grain tear-out and sanding later. Take light cuts due to tool overhang

11 Start sanding with 120 grade abrasives to remove any tool marks left from the turning tools, then go to 180, 240 and 320. Next, oil the surface with finishing oil and while it's still wet, sand with 400 grade abrasive. I then added more oil and then used 600 grade abrasive, applying more oil as needed. Finish to the top part on the outside also. Buff to a shine

12 Place a piece of scrap timber in the chuck and turn to fit the opening of the bowl. Add some paper towels in between the bowl and scrap timber to protect the inside of the finished bowl. Start to refine the outside curve and foot. If in doubt about the wall thickness stop the lathe and check with callipers. Refit to the lathe and continue

'Make sure this tool is sharp to reduce grain tear-out'

13 To finish the foot, sand as in step 11 on the outside and the foot of the bowl. Once this is complete, stop the lathe and remove, then with a small chisel remove the small pip and sand as before

14 Now to the plate. This is a faceplate grain turning project meaning the grain runs at 90° to the axis of the bed bars. Drill a suitable sized with a deep enough hole in the piece to enable it to be held in your chuck jaws, then take a cut across what will be the base of the saucer. Once you have come past the corners you should have bevel contact all the time

15 Mark the spigot diameter on the base, for my chuck this is 48mm, then use the parting tool to cut this about 4mm deep. This will act as the foot on the finished item. Always keep your fingers at your side of the toolrest

16 Use the bowl gouge to start shaping the underside, a flowing curve with no flat spots is what you are aiming for. Have the flutes facing the direction of cut. Don't push the gouge against the bowl, just let it rub lightly, this will help when you reach the corners when you have an intermittent cut

9

10

11

12

13

14

15


16

WT_288_87_91_PHILIP_GREENWOODbdJRmbPGSD.indd 90 30/11/2015 12:40