3

4

5

6

7

8


9

10

3 Mount the workpiece on the scroll chuck and tighten the chuck. Ensure that the workpiece does not foul the bed bars, and set the tool rest to the front, as close as is safe to do so. If you have a remote control pod for your lathe, set it in front of the tool rest. If you do not have this facility, ensure you are able to cut the power to the lathe quickly and safely, should the need arise. It is useful to rotate the workpiece and mark with a pen where the longest point passes the tool rest as a reference for cutting

4 Clean up the face surface: you can use a pull cut using the wing of a long ground bowl gouge, taking light and controlled cuts. Ensure you have bevel support for the tool. Work fluidly towards the outer marker you made on the tool rest. Remember that at four points in every rotation there will be voids where the tool is not in contact with the wood: take great care while turning these areas

5 Alternatively, if you are confident, you can make a push cut from the outer marker towards the centre

6 Once the surface is clean and true, begin to cut the wings away until you have a complete raised circular central boss. This area is where you create the decorative features, in contrast with the surrounding flat wings

7 At the outer edge of the central boss cut a bead 25mm wide using a 10mm parting and beading tool. Use only the corner tip of the tool and take light cuts

8 Next define and cut rings of different widths across the workpiece, leaving a small central boss that can be domed. Here you can see that I have used a texturing tool on one of the rings. You can add texture or designs as you wish on each of the defined bands

9 With the lathe stationary and the headstock locked, use a sanding arbor on a drill and abrade the flat surfaces to your preferred level of finish

10 Next, use a wood ageing product to cause an ebonising effect on the outer ring. You could also use a vinegar and wire wool mixture to create a similar effect. To add further texture use a cone-shaped burr in a drill. The cone allows for holes of differing diameters to be made

WT_291_33_36_TRYPTICH_AC_bdMBvsACSD.indd 35 02/03/2016 09:40