

rubrapack Manual

Building and signing MSI and MSIX packages - and how the formats work

Version 0.1.0

<https://github.com/rubidus-api/rubrapack>
<https://rubidus-api.github.io/rubrapack/>

The English edition is the original.
MIT License.

Contents

1	.rpk sources and the rubrapack command	2
1.1	Example	2
1.2	The TOML subset	2
1.3	Tables	2
1.4	Command line	10
2	Package formats for implementers	15
2.1	How to read the facts	15
2.2	Conventions	16
2.3	The pipeline, in one picture	16
3	Compound File Binary (CFB)	17
3.1	Sectors	17
3.2	Header (first 512 bytes) [spec]	17
3.3	FAT, DIFAT, mini FAT [spec]	18
3.4	Directory [spec]	18
3.5	A simple, deterministic writer	18
3.6	Reading safely	19
4	The MSI database inside the compound file	20
4.1	Streams	20
4.2	The string pool: _StringPool and _StringData	20
4.3	System tables	21
4.4	Table streams	22
4.5	IDT archive files (what MsiDatabaseExport writes)	22
4.6	Reading safely	22
5	Summary information	23
5.1	Layout [spec] [observed]	23
5.2	Properties an installer package sets	23
5.3	The code page trap - keep summary strings ASCII [observed]	23
6	The smallest package that installs, repairs, upgrades and uninstalls	25
6.1	Tables and columns	25
6.2	Property	25
6.3	Directory	25
6.4	Components, features, files	26
6.5	Empty folders	26
6.6	Media and the cabinet	26
6.7	Major upgrade and downgrade refusal	26
6.8	Running an installed program to register and unregister	26
6.9	Registry values	27
6.10	Shortcuts	27
6.11	Removing files and duplicating them	28
6.12	Environment variables	28
6.13	INI files	28
6.14	Searches and launch conditions	28
6.15	Services, fonts, permissions	28
6.16	Cabinets, administrative images, advertisement	29
6.17	Per-user and dual packages	29
6.18	Files in use	29
6.19	Sequences	29
6.20	Dialogs	30

6.21	What this recipe does not cover yet	31
7	Program files: machine type and version	32
7.1	Finding the headers [spec]	32
7.2	The version resource [spec]	32
7.3	What goes into the package [observed]	32
7.4	Reading safely	32
8	Cabinets, MSZIP and deflate	33
8.1	Cabinet layout [spec: MS-CAB]	33
8.2	MSZIP [spec: MS-MCI]	33
8.3	A deflate encoder in brief [spec: RFC 1951]	33
9	Deterministic identities and reproducible packages	35
9.1	Name-based GUIDs (UUID version 8) [spec: RFC 9562]	35
9.2	Keys	35
9.3	Reproducible packages	35
10	Authenticode signatures	36
10.1	Where the signature lives in a PE file	36
10.2	The PE digest	36
10.3	The CMS SignedData	36
10.4	MSI packages	37
10.5	Timestamps	37
10.6	ECDSA	38
10.7	What Windows reports	38
11	Checking your output against Windows	39
11.1	The database opens and decodes	39
11.2	The package installs	39
11.3	Checks before writing	40
11.4	Things that look fine but are not	41
12	MSIX packages	42
12.1	The ZIP archive	42
12.2	The block map (AppxBlockMap.xml)	42
12.3	[Content_Types].xml	43
12.4	The manifest (AppxManifest.xml)	43
12.5	The virtual registry (Registry.dat, User.dat)	43
12.6	The virtual file system (VFS\...)	43
12.7	Extensions	44
12.8	Bundles (.msixbundle)	45
12.9	Signatures (AppxSignature.p7x)	46
12.10	Installing an unsigned package	47
13	Registry hive files (REGF)	48
13.1	Layout	48
13.2	The base block	48
13.3	Keys (nk)	48
13.4	Subkey lists (lh, ri)	48
13.5	Values (vk) and value lists	49
13.6	The security cell (sk)	49
13.7	Reproducible hives	49

Part I

User manual

1 .rpk sources and the rubrapack command

An .rpk file describes a package. It is a strict subset of [TOML 1.0](#): every .rpk file is valid TOML, but rubrapack refuses TOML features outside the subset instead of ignoring them.

1.1 Example

```
[define]
VERSION = "1.4.0"

[package]
name = "Example App"
manufacturer = "Example"
version = "${VERSION}"
arch = "x64" # x64, arm64 or x86 - no default
upgrade-code = "{0B9A6C1E-3D2F-4A5B-8C7D-6E5F4A3B2C1D}" # generate your own once, keep it forever
language = "en-US" # or "ko-KR"

[dir.INSTALLDIR]
path = "ProgramFiles/Example App"

[dir.Docs]
path = "INSTALLDIR/docs"

[file.MainExe]
dir = "INSTALLDIR"
source = "dist/app.txt"

[file.Guide]
dir = "Docs"
source = "dist/guide.txt"
name = "User guide.txt"
```

```
rubrapack build example.rpk -o example.msi -D VERSION=1.4.1
rubrapack inspect example.msi File
```

1.2 The TOML subset

Accepted: tables [kind] and [kind.ID], bare keys (A-Z a-z 0-9 _ -), basic strings "..." with TOML escapes, literal strings '...' (no escapes - use them for backslashes and quotes: 'SOFTWARE\Example'), decimal and 0x integers, true/false, one-type arrays, # comments. UTF-8 with or without a BOM, or UTF-16LE with a BOM; LF or CRLF.

Refused with an error: multi-line strings, inline tables, arrays of tables, dotted and quoted keys, table names with more than two parts, floats, dates, _ in numbers, octal/binary numbers, empty or mixed arrays, keys before the first table. Table and key order never matters.

1.3 Tables

Table	Keys (required in bold)
[package]	name , manufacturer , version (a.b.c or a.b.c.d), arch , upgrade-code , upgrade-code-x64 / -arm64 / -x86, product-code, summary-name (ASCII), language, scope (machine, user, dual), ui (none, basic, minimal, installdir, features), license (.txt, .md, .rtf), reboot (suppress/allow), downgrade-mes-

Table	Keys (required in bold)
	sage, compress (none, mszip, mszip:0..mszip:9; default mszip:6), cab (embed or external), cab-max-size (MiB), refuse-upgrade-below, refuse-upgrade-message
[define]	variables: NAME = "value"
[feature.ID]	title , description, level (1-32767), hidden, parent
[dir.ID]	path = Base/relative/path, feature
[file.ID]	dir , source , name, vital (default true), any-arch, feature, component-guid
[files.ID]	dir , glob , vital, any-arch, feature
[folder.ID]	dir , name , keep, feature
[arp]	no-modify, no-repair, help (URL), about (URL) - how the product shows in Installed apps
[property.ID]	value , secure, hidden - an upper-case public property
[action.ID]	run (file:ID of an .exe in this package), do , undo , check
[registry.ID]	root (HKLM, HKCU, HKCR, HKMU), key , name, value, type, remove, keep, view, with, feature
[remove.ID]	dir , name (* and ?; omitted = the folder itself), on (install, uninstall, both), feature
[ini.ID]	dir , file , section , key , value, mode (set, add, remove), feature
[require.ID]	condition , message
[search.ID]	property , kind (registry: root, key, name, view; file: path, file, min-version; dir: path; component: component-guid)
[service.ID]	file (file:ID of an .exe), name , display-name, description, start (auto, demand, disabled), account (LocalSystem, LocalService, NetworkService), args, start-on-install
[assoc.ID]	extension (.ext, lower case), prog-id , target (file:ID of an .exe), description, icon (file:ID), args (default "%1")
[protocol.ID]	name (the scheme, lower case), target (file:ID of an .exe), description, args (default "%1")
[font.ID]	file (file:ID of a file in a dir with path = "Fonts"), title
[permission.ID]	target (dir:ID, file:ID, registry:ID), sddl
[env.ID]	name , value , mode (set, append, prepend), keep, feature
[copy.ID]	source (file:ID), dir , name (default: the source's name)
[ui]	install-dir (a dir ID; default INSTALLDIR), banner (.bmp)
[ui-text.ID]	text - replaces one built-in dialog text
[dialog.ID]	after (a built-in page or another [dialog.*]), title, description
[dialog-control.ID]	dialog , type (text, checkbox, edit, radio, combo), x , y , width , height , text, property, values, labels
[shortcut.ID]	dir (a dir ID, or Programs, Desktop, StartMenu, Startup), name , target (file:ID), args, description, working-dir (a dir ID)
[msix]	identity-name , publisher , publisher-display-name, min-version - see MSIX packages
[msix-app.ID]	executable (a [file.*] ID), display-name, description, logo-150, logo-44, store-logo
[msix-extension.ID]	kind (alias: alias ; startup-task: task-id, display-name, enabled), app (an [msix-app.*] ID; default the first) - MSIX only

Base in a dir path is another dir ID or one of: ProgramFiles (64-bit for x64/arm64, 32-bit for x86), ProgramFiles32, CommonFiles, AppData, LocalAppData, CommonAppData, StartMenu, Programs, Desktop, Startup, Windows, System, Fonts, Temp. A path may also be a known folder alone (path = "Fonts") for files that go into that folder itself.

IDs are [A-Za-z_][A-Za-z0-9_]* (at most 72 characters, 38 for features) and must differ across dirs, files and features.

MSIX packages

The same source builds an MSIX package when the output ends in .msix: one desktop application that runs with full trust, for one architecture. Two more tables say what only MSIX needs:

```
[msix]
identity-name = "Example.App"           # 3-50 characters: A-Z a-z 0-9 . -
publisher = "C=KR, O=Example, CN=Example" # the signing certificate's subject, last part first
```

```

publisher-display-name = "Example"           # default: [package] manufacturer
min-version = "10.0.17763.0"                 # the oldest Windows it installs on (this is the default)

[msix-app.Main]
executable = "MainExe"                       # the [file.*] that starts the app
display-name = "Example App"                 # default: [package] name
description = "An example"                   # default: the display name
logo-150 = "assets/Square150x150.png"        # PNG, 150x150
logo-44 = "assets/Square44x44.png"           # PNG, 44x44
store-logo = "assets/StoreLogo.png"          # PNG, 50x50

```

- The version is [package] version with four parts (1.2.3 becomes 1.2.3.0), the architecture [package] arch, the language [package] language.
- The package's own folder is that of the first [msix-app.*]'s executable - the dir anchored in a known location, such as ProgramFiles/Example App. Files in other known locations go into the package's virtual file system, where the app sees them at their usual place: Program Files (VFS\ProgramFilesX64, or X86 for an x86 package and for ProgramFiles32), CommonFiles, System, Windows and CommonAppData (ProgramData). There is none for the user's AppData or LocalAppData, nor for Temp: files there are an error (RP1609). A font in Fonts goes in through its [font.*]; the Start menu, Programs and Desktop folders take shortcuts ([shortcut.*]), and Startup a startup task ([msix-extension.*]).
- Several [msix-app.*] tables make several entries of one package (at most 100); the first one gives the package its logo.
- [registry.*] values go into the package's virtual registry, which the app sees merged into the real one while the machine's registry stays untouched: HKLM (and HKMU) under Software into Registry.dat (with view = "32" in the 32-bit view), HKCU under Software into User.dat. What an MSIX cannot hold is an error (RP1612): HKCR (file types and protocols are [assoc.*] and [protocol.*]), keys outside Software, remove and keep, and values with a part Windows Installer fills in at install time ([INSTALLDIR], [#File], ...; the escapes [[] and \[] are fine).
- Give the three logos or none: without them the package gets plain one-colour logos. A logo must have the exact size (RP1608).
- What an MSIX cannot do is an error, not something left out quietly (RP1605): custom actions, services, environment variables, INI files, permissions, launch conditions and searches, files removed or copied at install, empty folders. Add msi-only = true to such a table (or to a [file.*]/[files.*]) and the MSI keeps it while the MSIX is built without it. Features, properties, dialogs and [arp] concern the Windows Installer only and are not used for an MSIX.
- --unsigned-test adds the attribute Windows needs to install an unsigned package for testing (Add-AppxPackage -AllowUnsigned, as administrator when it contains a program); such a package is not for distribution and its identity differs from the signed one. --key signs the package (or the bundle and its packages) instead; see sign below.
- Files are compressed (--msix-compress store turns it off); pictures, archives and other already compressed files are stored. An MSIX holds no time: the same source gives the same bytes on Linux and Windows.
- An output ending in .msixbundle is a bundle: the source built once for each architecture of --arch (a list, --arch x64,x86,arm64; without it the source's own), each package named <identity-name>_<version>_<arch>.msix inside. Windows installs the package for its own architecture from it (an x64 machine takes x64 before x86). \$(ARCH) gives each build its own programs: source = "bin/\$(ARCH)/app.exe". The bundle's version is the packages' version.

Registering with an installed program: [action.ID]

```

[action.Tip]
run = "file:MainExe"           # an .exe this package installs

```

```
do = "--register"      # run after the files are installed, and again on repair
undo = "--unregister"  # run on removal, before the files are removed
```

rubrapack turns the pair into deferred, elevated actions with their rollback twins, so removal and upgrade are all-or-nothing: if anything fails later (or do/undo itself exits non-zero), the files come back and the other command restores the registration. Both commands must be safe to run twice and must finish without asking anything - they run without a window, and nothing waits for a user. check names an optional command that exits 0 when the registration is in place.

Registry values: [registry.ID]

```
[registry.InstallDir]
root = "HKLM"
key = 'SOFTWARE\Example'      # literal strings keep the backslashes
name = "InstallDir"          # omit it for the key's default value
value = "[INSTALLDIR]"        # an MSI formatted string: [PROPERTY], [#FileID], [\[] for "[
```

type is string (default), expand, dword (an integer, 0 to 0xFFFFFFFF), qword (an integer, or "0x" and up to 16 hex digits), binary (hex digits) or multi (an array of strings). Windows Installer cannot write REG_QWORD itself; rubrapack adds its small helper DLL to the package for it, which also restores the previous value if the installation fails. Each value is its own component, removed at uninstall (keep = true leaves it); with = "file:ID" puts it in that file's component instead. In a 64-bit package values go to the 64-bit registry view; view = "32" writes to the 32-bit view. remove = true (without value) deletes the named value - or the whole key when name is omitted - during installation.

Shortcuts: [shortcut.ID]

```
[dir.Menu]
path = "Programs/Example"      # Start menu > Example

[shortcut.Settings]
dir = "Menu"
name = "Example settings"      # ".lnk" is added
target = "file:MainExe"
args = "--settings \"[INSTALLDIR]\""
```

A shortcut belongs to its target file (and its feature); folders created for it are removed at uninstall. In a per-machine package Programs and Desktop are the all-users Start menu and the Public Desktop.

In an MSIX a shortcut starts an application (its target must be an [msix-app.*] executable): one in Programs or StartMenu is that application's own Start menu entry (no args); one on the Desktop is written into the manifest and needs min-version = "10.0.19645.0" or later (RP1614). Other folders, working-dir and [...] in args are errors there (RP1613); for Startup use a startup task.

File types and links: [assoc.ID], [protocol.ID]

```
[assoc.Doc]
extension = ".exdoc"
prog-id = "Example.Document"    # tables sharing it describe one kind of document
description = "Example document"
target = "file:MainExe"
args = "--open \"%1\""          # the default is "%1"

[protocol.Link]
name = "example"                # example:... opens the program
target = "file:MainExe"
```

In an MSI they are registry values under HKEY_CLASSES_ROOT, in the program's component: the extension's default value is the prog-id, the prog-id has the description, DefaultIcon (icon, or the program's first icon) and shell\open\command; a scheme gets URL Protocol. HKEY_CLASSES_ROOT follows the installation: per machine they land in HKLM\Software\Classes, per user in HKCU\Software\Classes, and removal takes them away. A type that only this program claims opens in it directly; where the user has chosen another program, Windows keeps that choice.

In an MSIX they go into the manifest of the application whose executable is the target (a file type association, a protocol), and args must be plain text. icon is not used there: the application's logo stands for the file type.

MSIX only: [msix-extension.ID]

```
[msix-extension.Cli]
kind = "alias"
alias = "example.exe"           # typed in a console, it starts the application

[msix-extension.Boot]
kind = "startup-task"          # starts with Windows once the application has run once
display-name = "Example"       # the name in Task Manager; task-id defaults to the table ID
enabled = true
```

An MSI build leaves these out. Fonts ([font.*]) in an MSIX are shared with other applications (uap4:SharedFonts) from the package's Fonts folder; title is not used there.

Removing and copying: [remove.ID], [copy.ID]

[remove.ID] deletes files matching name in dir - for example *.log an older version left, at on = "install", or files the program writes at run time, at on = "uninstall". Without name it removes the folder itself when it is empty. A failed installation puts removed files back. [copy.ID] installs a second copy of a file of this package into another folder; it goes and comes with its source. Folders that existed before the installation are never removed.

Environment variables: [env.ID]

A system (machine-wide) variable. mode = "set" (default) replaces it, append/prepend add ;value to the end or value; to the front of what is there. Uninstall undoes exactly that: a set variable is deleted, an appended part is taken out and the rest kept. keep = true leaves it.

INI files: [ini.ID]

mode = "set" (default) writes key=value in [section] of the file, add appends the value to a comma-separated list (a becomes a,b), remove deletes the key during installation. Uninstall takes out what set and add wrote. remove runs before files are installed, so it is for INI files an older version left behind.

Searching and requiring: [search.ID], [require.ID]

A search runs before anything else and puts what it found into a public property (empty when nothing is found): a registry value's data, the full path of a file (path = a known folder and a relative path, like System or ProgramFiles/Example; min-version for program files), a folder, or the key file of another product's component. A requirement stops a first installation with its message when its condition is false (repair and removal are never blocked); conditions use Windows Installer's syntax (VersionNT >= 603, FOUND_TOOL, NOT OLDSETTING) and may test search results.

```
[search.Tool]
property = "FOUND_TOOL"
kind = "file"
path = "System"
file = "tool.exe"
```

```
[require.Tool]
condition = "FOUND_TOOL"
message = "[ProductName] needs tool.exe."
```

Services, fonts and permissions

[service.ID] installs a service run by an .exe of the package: it is stopped before its files change and at uninstall, deleted at uninstall, and started after installation with start-on-install = true. [font.ID] registers a font file that the package installs into the Fonts folder; without title Windows reads the name from the TrueType/OpenType file. [permission.ID] sets an SDDL security descriptor on a folder the package creates, one of its files, or a registry value it writes (this raises the package to Windows Installer 5.0).

Per-user and dual packages: scope

scope = "machine" (default) installs for everyone and needs administrator rights. scope = "user" installs for the current user without elevation: ProgramFiles becomes %LOCALAPPDATA%\Programs, Programs and Desktop are the user's, registry values go to HKCU (or HKMU), environment variables are the user's, and do/undo actions run as the user; asking for a per-machine installation is refused. scope = "dual" installs per user by default and per machine from an elevated prompt with msixec /i x.msi ALLUSERS=1 MSIINSTALLPERUSER=""; its registry values use HKMU, which is HKLM or HKCU as installed. Services, fonts, permissions and the machine folders (Windows, System, Fonts, CommonAppData) need scope = "machine".

Cabinets

Files are compressed into one cabinet embedded in the package. cab-max-size = N starts a new cabinet after N MiB of files; cab = "external" writes the cabinets next to the package as <name>.cab (or <name>-1.cab, <name>-2.cab, ...), which must travel with it. rubrapack never overwrites an existing cabinet and writes the package last. Every package also carries the administrative (msixec /a, an uncompressed network image) and advertisement (msixec /jm) sequences.

Only these fields are MSI formatted strings: registry value (and multi items), shortcut args, environment value, INI value, requirement message, service args. Everywhere else rubrapack writes the text exactly as given.

Installed apps entry and properties

[arp] sets how the product appears in Settings > Installed apps (no-modify, no-repair, help, about). [property.NAME] adds a public property; secure = true lets it reach the elevated part of the installation, hidden = true keeps its value out of logs. Names the installer or rubrapack set themselves (ARP*, MSI*, RP_*, ALLUSERS, REBOOT, ...) are refused.

Installing without a window

Every package rubrapack builds installs, repairs, upgrades and uninstalls from the command line with no user interface:

```
msixec /i example.msi /qn /l*v install.log
msixec /x {ProductCode} /qn
```

Exit code 0 is success, 3010 success with a restart needed (rubrapack never restarts the machine itself), anything else a failure after which the machine is as before.

Dialogs: ui

ui in [package] picks one of the built-in dialog sets. Without it (none) the package shows only Windows Installer's own progress bar.

ui	Installing	Already installed
basic	progress, then finished (or error)	progress, finished
minimal	welcome, the license if there is one, progress, finished	repair or remove
installdir	welcome, license, install folder (with a folder browser), ready, progress, finished	repair or remove
features	as installdir, plus a feature tree and the disk space it needs	repair or remove

Every set also has the cancel question, the error dialog, the files-in-use list and the out-of-disk-space warning. The dialogs only collect values that all have defaults, so /qn still installs without a window.

```
[package]
ui = "installdir"
license = "LICENSE.txt"          # the Install/Next button stays disabled until it is accepted
language = "ko-KR"              # the built-in texts are Korean for ko-KR, English otherwise

[ui]
install-dir = "APPDIR"          # the dir the user may change (default INSTALLDIR)
banner = "banner.bmp"          # the strip at the top; about 493 x 58 pixels

[ui-text.WelcomeText]
text = "This will install [ProductName]. Close other programs first."
```

A .txt or .md license is shown as plain text (Korean, emoji and any other characters are kept); an .rtf license is used as it is. Without banner the strip is plain white. [ui-text.ID] replaces one text; the texts are MSI formatted strings, so [ProductName] is replaced and a literal [is written \[. The IDs are: Back, Next, Cancel, Install, Finish, OK, Yes, No, Retry, Ignore, Abort, Exit, Browse, WelcomeTitle, WelcomeText, LicenseTitle, LicenseText, LicenseAccept, DirTitle, DirText, DirLabel, BrowseTitle, BrowseText, BrowseLookIn, BrowseFolder, BrowseUp, BrowseNew, CustomizeTitle, CustomizeText, Reset, DiskCost, DiskCostTitle, DiskCostText, ReadyTitle, ReadyText, ProgressTitle, ProgressText, ProgressStatus, ExitTitle, ExitText, UserExitTitle, UserExitText, FatalTitle, FatalText, CancelText, FilesInUseTitle, FilesInUseText, OutOfDiskTitle, OutOfDiskText, MaintTitle, MaintText, Repair, RepairText, Remove, RemoveText. In button texts & marks the access key (&Next is Alt+N).

Your own dialog pages: [dialog.ID], [dialog-control.ID]

With minimal, installdir or features you can add pages to the built-in flow. A page gets the same banner and Back / Next / Cancel buttons as the others; you place the controls in its body.

```
[dialog.Options]
title = "Options"                # the banner heading; [ProductName] when omitted
description = "Choose how to install."
after = "RpInstallDirDlg"        # shown right after this page

[dialog-control.ModeLabel]
dialog = "Options"
type = "text"
x = 20
y = 55
width = 330
height = 12
text = "Installation &mode:"

[dialog-control.Mode]
dialog = "Options"
type = "radio"
x = 20
y = 70
width = 200
height = 42                     # at least 12 per value
property = "APP_MODE"
values = ["typical", "portable", "server"]
```

```
labels = ["&Typical", "&Portable", "&Server"]

[property.APP_MODE]
value = "typical"                # the default, also for a silent installation
```

- after is a page of the chosen set - RpWelcomeDlg, RpLicenseDlg (with a license), RpInstallDirDlg (installdir, features), RpCustomizeDlg (features) - or another of your pages. Several pages after the same page follow in ID order. In minimal the last page's button is Install; in the other sets the ready page always comes last.
- Coordinates are dialog units on a 370 x 270 page; controls go in the body, between y = 45 and y = 234. The Tab key moves through the controls from top to bottom, then left to right.
- text shows a label (& marks an access key; on a text control it moves to the next control). checkbox sets its property to 1 when ticked and removes it when clear. edit lets the user type the property's value. radio and combo choose one of values (1 to 32 strings of at most 64 bytes), shown as labels (default: the values themselves), in the order written.
- A radio or combo needs a [property.*] whose value is one of its values: the dialogs only collect values, and a silent installation (/qn) uses the defaults. Any property can also be set on the command line: `msiexec /i example.msi /qn APP_MODE=server`.
- The properties are public names of your own (upper case), one control each, and reach the elevated part of the installation, so [registry.*], [ini.*], [env.*], conditions and the rest can use them as [APP_MODE].
- Page IDs starting with Rp and the control IDs of the frame (Banner, Title, Description, BannerLine, BottomLine, Back, Next, Cancel) are reserved; a page holds up to 64 controls.

Architectures and upgrade families

arch is the source's own architecture and upgrade-code its upgrade family. To build the same source for another architecture (--arch), give that architecture its own family with upgrade-code-x86, upgrade-code-arm64 or upgrade-code-x64; without it the build is refused. Windows Installer's upgrade detection cannot tell architectures apart, so sharing one code would make installing one architecture remove the other. An MSIX has no upgrade code, so .msix and .msixbundle builds do not need these.

Versions that must be removed first

refuse-upgrade-below = "1.0.0" refuses to upgrade an installed version below 1.0.0 and tells the user to remove it first; the message (refuse-upgrade-message, or a default one) always ends with the command that does it: `msiexec /x {ProductCode} /qn MSIRESTARTMANAGERCONTROL=Disable`. Use it when older versions were built by another tool without MSIRESTARTMANAGERCONTROL=Disable: removing such a version inside an upgrade would try to close every program that has its files loaded (see formats/msi-package.md, "Files in use").

Wildcards: [files.ID]

glob is a source path with * (any characters within one folder), ? (one character) and ** (any number of folders). Matches are sorted by name, so the result never depends on the file system. Folders below the first wildcard are recreated under dir: `glob = "dist/layouts/**/*.jmt"` installs `dist/layouts/de/x.jmt` as `<dir>/de/x.jmt`. No match, a symbolic link, or the output file itself among the matches is an error.

Empty folders: [folder.ID]

Creates the folder name inside dir even when no file goes there. With `keep = true` the folder stays after uninstall (for data the program writes).

Features

Without any [feature.*] table everything goes into one hidden feature. As soon as one feature is declared, every file needs one: its own feature key, or the feature of its dir. A feature with a level above 1 is not installed by default.

Variables

\$(NAME) inside a string value is replaced once, from -D NAME=value on the command line first, then [define]. The result is not read again (a value containing \$(X) stays literal). \$\$ is a literal \$. An undefined name is an error. \$(ARCH) is built in, unless -D or [define] defines it: the architecture being built (x64, arm64 or x86) - so one source can name each architecture's program, as source = "bin/\$(ARCH)/app.exe".

Program files

Files that are Portable Executables (.exe, .dll, ...) are checked: their machine type must match arch (an x86 helper in an x64 package needs any-arch = true), and their version resource becomes the file's version in the package, which is how Windows Installer decides whether to replace an installed file.

Paths

Source paths are relative to the .rpk file and use /. Absolute paths, \, symbolic links and missing files are errors. Target names may use any Unicode text except what Windows forbids (< > : " / \ | ? *, control characters, trailing dot or space, device names such as CON), and two names in one folder may not differ only by letter case. Windows Installer stores a name together with its 8.3 short name in 255 UTF-16 units, so a long name may use only what the short name leaves: 242 units for name.ext with a three-letter extension, 246 for a name without one (NTFS would accept 255). A longer name is refused with RP1514.

1.4 Command line

```
rubrapack build <src.rpk> -o <out.msi|out.msix|out.msixbundle> [-D NAME=VALUE]...
    [--arch x64|arm64|x86] [--arch <list> (.msixbundle)]
    [--compress none|mszip|mszip:N] [--nfc] [--reproducible]
    [<key>] [--cert <chain.pem>]
    [--timestamp <URL>] [--tsa-trust <certificates>] [--tls-trust <certificates>] [--system-roots]
    [--proxy <URL>]] [--allow-unsigned-cabs]]
    [--unsigned-test] [--msix-compress deflate|store]      (.msix, .msixbundle)
rubrapack inspect <file.msi> [table | --summary | --files | --streams]
rubrapack inspect <file.msix|file.msixbundle> [--files | --manifest]
rubrapack inspect <file.cab>
rubrapack new [msi] <name>
rubrapack guid [--from <text>]
rubrapack lint <src.rpk> [-D NAME=VALUE]... [--arch x64|arm64|x86] [--nfc] [--strict]
rubrapack lint <file.msi|file.msix|file.msixbundle> [--strict]
rubrapack extract <file.msi|file.msix|file.msixbundle|file.cab> -d <new dir> [--limit-entries N] [--limit-bytes N]
rubrapack sign <file.exe|.dll|.msi|.msix|.msixbundle> <key> [--cert <chain.pem>]
    [--timestamp <URL>] [--tsa-trust <certificates>] [--tls-trust <certificates>] [--system-roots]
    [--proxy <URL>]] [--allow-unsigned-cabs] [-o <out>]
rubrapack keys list [--pkcs11 <module>] [--token-label <label>] [--pin-env VAR | --pin-file FILE]]
rubrapack verify <file.exe|.dll|.msi|.msix|.msixbundle> [--trust <certificates>]... [--system-roots] [--tsa-trust
<certificates>]...
rubrapack version | help [command]

<key> is one of:
  --key <key.pfx|.pem> [--pass-env VAR | --pass-file FILE]          a key file
  --pkcs11 <module> --key-label <label> [--token-label <label>]
    [--pin-env VAR | --pin-file FILE]                                a key in a PKCS#11 token
  --key-store <SHA-1 thumbprint> [--machine-store]                 a key in the Windows store
```

- Command-line options override the source.

- `--reproducible` derives the package code from the content: the same source gives the same bytes, on Linux and on Windows, from any folder, with the options in any order. Without it the package code is random, as Windows Installer expects for different package files. An MSI holds no time at all (no creation or save dates in its summary; cabinet entries are dated 1980-01-01), so `SOURCE_DATE_EPOCH` does not change it; nor does it hold the source's path or the name of the machine or user that built it. Every source file is read once, and those bytes are hashed, versioned and packed; a file that changes while the package is being built stops the build (RP1515).
- `--nfc` puts the names the package gives to folders, files and shortcuts in Unicode NFC (composed). A file from macOS often has a decomposed name - a Hangul syllable such as U+D55C as the three jamo U+1112 U+1161 U+11AB - and Windows installs names exactly as they are, so the same word can become two different files. The source files keep their names; texts and registry values stay as written. `lint` warns (RP2105) about any text that is not in NFC, and a name that becomes the same as another one is refused (RP1511). The normalization is rubrapack's own, from Unicode 17.0 data.
- `inspect <file.msi> <table>` prints the table in Windows Installer's IDT format. `--files` prints one tab-separated line per file: installed path, size, File key, component, version, language, MD5 (from `MsiFileHash`; empty when the package has none). `--streams` lists the streams and their sizes. `inspect <file.cab>` lists the files in a cabinet. `inspect <file.msix>` shows the identity, the executable and the files (after checking every block's hash); `--files` lists path, size and whether each file is compressed, `--manifest` prints `AppxManifest.xml`. For a bundle, the identity and the packages (each opened and checked as a package), and its `AppxBundleManifest.xml`; `extract` writes the packages out.
- `new <name>` writes `<name>.rpk`, a source that builds as soon as the program's files are in `dist/`, with a fresh upgrade-code. It never replaces an existing file.
- `guid` prints a random GUID (version 4). `guid --from <text>` prints the GUID rubrapack derives from a text, the same way on every machine: SHA-256 over the 32-bit little-endian length of `guid` and those 4 bytes, the 32-bit little-endian number 1, and the 32-bit little-endian length of the text and its UTF-8 bytes; the first 16 bytes of the hash, with the version nibble set to 8 and the variant bits to 10 (RFC 9562 UUIDv8), written as {XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX} in upper case. For example `guid --from hello` gives {B52FE8EF-B68D-84B5-91AF-E6E01BEC2773}.
- Diagnostics look like `example.rpk:12:3: error[RP1201]: unknown key 'nmae' in [package] (did you mean 'name'?)`.
- Before writing, `build` checks the finished tables (RP20xx diagnostics, exit code 5); these checks guard rubrapack itself, so a source that passes the RP1xxx checks should never meet them.
- `lint <src.rpk>` runs every check `build` runs and writes nothing. `lint <file.msi>` checks a package made by any tool with the same table rules: what stops an installation is an error (exit code 5) - a value that does not fit its column, a missing referenced row, a duplicate key, a broken dialog tab order (RP2101), a dialog's first/default/cancel control that is not there (RP2102), a files-in-use dialog without a `ListBox` table (RP2103), an error dialog without `ErrorText/ErrorIcon` (RP2104) - and everything else is a warning. `--strict` makes warnings fail too. A package in another code page than 65001 gets a note (RP2100): its text cannot be checked as UTF-8. The last line on stdout counts errors and warnings. `lint <file.msix>` checks the package the way Windows reads it - the ZIP, the block map, every block's hash - and that the manifest has an identity and names files that are in the package (RP2201, RP2202). For a bundle: its manifest's block map, and for each package where the manifest says it lies, its size, its identity and the package itself; one package per architecture.
- `extract` unpacks a package the way it installs: folders by their long names under the Directory tree (a standard folder such as `ProgramFiles64Folder` keeps its name), files from the embedded or external cabinets, or from the source folders next to an uncompressed package. Every file is checked against its size and `MsiFileHash`. The target must be new or empty, and nothing is written until the whole package has passed: names with `..`, `/`, `\`, `:`, a drive, a reserved device name (`CON`, `COM1`, ...), a trailing dot or space, or two paths that differ only in case are refused. The defaults allow

100,000 entries and 16 GiB. A .cab unpacks by the names inside it. An .msix unpacks its files (not the ZIP's own [Content_Types].xml and AppxBlockMap.xml) after every block has matched its hash.

- `sign` adds an Authenticode signature (SHA-256; RSA, or ECDSA P-256/P-384) to a PE file, an MSI package, an MSIX package or a bundle (whose packages are signed first), in place or to `-o`; `build --key` signs the package as it is built (the same code), and a signed `--reproducible` build still gives the same bytes every time (the signature holds no time) - unless it is timestamped: a timestamp carries the server's time and serial number, so it differs on every run, and only the package inside the signature stays the same. An MSI whose cabinets lie outside it is refused: its signature would not cover them - use embedded cabinets, or `--allow-unsigned-cabs` to sign the .msi alone with a warning. The key file is a PKCS#12 file (.pfx/.p12: AES with PBKDF2-HMAC-SHA256, SHA-256 MAC - what current Windows and OpenSSL export) or a PKCS#8 PEM/DER key, plain or encrypted with PBES2; `--cert` adds certificates the key file does not hold. The certificate must be for code signing, must not be a CA and must be valid now. The password comes from an environment variable or a file, never from the command line. A file that is signed already is refused. An MSIX's [msix] publisher must be the certificate's subject as Windows writes it - its parts from last to first, as O=Example Ltd, CN=Example - or signing stops and prints the subject to use; `--unsigned-test` and a key do not go together.
- A key that must not leave its hardware - required for publicly trusted code-signing certificates since 2023 - stays there: rubrapack computes the hashes, the CMS structure and the timestamp request itself and asks only for the one signature. `--pkcs11 <module>` loads the token's PKCS#11 library (the only library rubrapack ever loads, and only this one you name), logs in with the PIN from `--pin-env` or `--pin-file` (never the command line), and uses the private key labelled `--key-label` with the certificate stored under the same ID on the token (`--cert` supplies it, or the rest of the chain, when the token has none); with several tokens present, `--token-label` picks one. On Windows, `--key-store <thumbprint>` uses a certificate in the current user's personal store (`--machine-store`: the local machine's) whose private key is reachable through NCrypt - a smart card, a token or TPM through its key storage provider, or a software key - and takes the chain Windows builds for it. RSA and ECDSA keys both work. Every signature is checked with the certificate before it is written.
- `keys list` shows the keys that can sign: with `--pkcs11`, each private key on the token(s) with its label, ID and certificate; on Windows without it, the certificates with a private key in the personal stores, with their thumbprints. For each it prints the MSIX publisher that certificate signs for and when it expires; nothing secret.
- `--timestamp <URL>` asks an RFC 3161 time-stamping server to countersign the signature, so that it stays valid after the certificate expires; without it `sign` and `build --key` warn that it will not. There is no default server and nothing goes over the network unless you name one. Public servers include <http://timestamp.digicert.com>, <http://timestamp.sectigo.com> and <http://time.certum.pl>; http is fine, because the answer is itself signed and checked (the nonce, the hash of the signature, the server's signature and its time-stamping certificate). `--tsa-trust` also requires the server's certificate path to end in one of the given certificates. For an https server rubrapack speaks TLS 1.3 itself (AES-GCM, x25519 or P-256, RSA-PSS or ECDSA server keys; not TLS 1.2) and checks the server's certificate - its path to a root given with `--tls-trust` or found in the operating system's store with `--system-roots`, its dates, that it names the server (subjectAltName; no wildcard across dots) and that it is for TLS servers; nothing turns these checks off. The three trusts stay apart: `--tls-trust` and `--system-roots` say whom to believe about the connection, `--tsa-trust` whom to believe about the time; neither is used for the other. On Linux `--system-roots` reads \$SSL_CERT_FILE or the distribution's CA bundle; on Windows the ROOT store, which Windows fills with some roots only when something first needs them, so a root may be missing there until then. `--proxy http://host:port` sends the request through a proxy (an https server through CONNECT, so the proxy sees only the server's name); without it `https_proxy` or `HTTPS_PROXY` (for an https server) or `http_proxy` (for http);

the upper-case HTTP_PROXY is not read, since a CGI environment can set it from a request header) are used unless no_proxy or NO_PROXY - names, each also covering the names under it, or * - lists the server. A proxy that asks for a password is not supported (a clear error), nor an https:// proxy. When the timestamp fails - no answer, a refusal, a bad answer, a time outside the signing certificate's validity - nothing is signed and nothing is written (exit code 6); the signature never quietly goes out without it. The limits: 10 s to connect, 60 s in all, a 4 MiB answer, 3 redirects, 2 retries after a network error or a 5xx answer.

- verify prints what it checked - structure, digest, signature, the path to a certificate given with --trust, revocation (never looked up: not-checked) and timestamp - and succeeds only when all of them hold and the path ends in a trusted certificate. Without --trust it does not call anything trusted (exit code 4); --system-roots adds the operating system's roots to --trust for the signer's path (not for the timestamp's). It says nothing about Windows' own reputation checks. The timestamp line is not-present, <time>, TSA not-checked (give --tsa-trust), <time>, TSA trusted, <time>, TSA untrusted, invalid or unsupported (the older Authenticode timestamp that Set-AuthenticodeSignature -TimestampServer writes, which rubrapack does not check); the last three fail. Only a timestamp whose server is trusted through --tsa-trust - --trust does not count for it - moves the time at which the signer's certificate must have been valid from now to the stamped time. (For tests, the environment variable RUBRAPACK_TEST_NOW - seconds since 1970 - replaces "now" in verify's checks, so that an expired certificate can be checked without changing a clock; it widens nothing that a clock set to that time would not.)
- Exit codes: 0 success, 1 error in the source, 2 usage, 3 input/output, 4 signing, 5 lint, 6 network.

Part II

File format manual

2 Package formats for implementers

These pages describe what a program has to write to produce a Windows Installer package (.msi) and an MSIX package or bundle that Windows accepts, and how to sign them. They are written from public specifications and from experiments against Windows itself, so that you can build your own tool from them without reading rubrapack's code - or check rubrapack's code against them.

Page	Covers
Compound File Binary (CFB)	Compound File Binary: the container every .msi is
The MSI database inside the compound file	Streams, string pool, system tables, table encoding, IDT export
Summary information	The summary information stream and its code page trap
The smallest package that installs, repairs, upgrades and uninstalls	The tables that install, upgrade, repair and uninstall: files, registry, shortcuts, services, fonts, dialogs, per-user packages, sequences
Program files: machine type and version	Program files: machine type and version resource
Cabinets, MSZIP and deflate	Cabinet files, MSZIP blocks, the deflate encoder
Deterministic identities and reproducible packages	Deterministic GUIDs and keys, reproducible builds
Authenticode signatures	Authenticode signatures for PE files and MSI packages: the digests, the CMS structure Windows accepts, ECDSA, RFC 3161 timestamps
Checking your output against Windows	How to check your output with Windows' own components
MSIX packages	MSIX: the ZIP layout, block map, manifest, virtual registry and file system, extensions, bundles, signatures
Registry hive files (REGF)	Registry hive files (REGF), as MSIX Registry.dat and User.dat hold them

2.1 How to read the facts

Every statement is tagged with where it comes from:

- **[spec]** - a public specification: [MS-CFB], [MS-OLEPS], [MS-CAB], [MS-MCI], RFC 1951, RFC 1321, RFC 3161, RFC 5652, RFC 9562, the PKWARE ZIP APPNOTE, ECMA-376 Part 2 (OPC), the Authenticode PE specification, or the Windows Installer and MSIX references on Microsoft Learn.
- **[observed]** - measured on Windows 11: the MSI pages on 25H2 (build 26200) with Windows Installer 5.0.10011, by creating databases through `msi.dll` and reading them back byte for byte, and by installing packages; the MSIX, registry hive and signature pages on build 26100, against Windows' own packaging API, Offline Registry Library and signer, and by installing and running packages. Observations are facts about those builds; where Microsoft does not document a format (the MSI table encoding, the registry hive, the MSIX signature's record of hashes are not published), observation is the only source.

No text or code here comes from other MSI, MSIX, cabinet or registry implementations.

2.2 Conventions

- All integers are little-endian unless stated otherwise.
- u16, u32, u64 are unsigned; i16, i32 signed two's complement.
- Offsets are in bytes from the start of the structure named.
- Hex byte strings are written in file order: D0 CF 11 E0.

2.3 The pipeline, in one picture

```
source description --> tables (rows of strings/integers/streams)
                    --> MSI database encoding (string pool + one stream per table)
                    --> files packed into a cabinet (stored or MSZIP) --> one more stream
                    --> summary information stream
                    --> all streams written into one compound file = the .msi
```

An MSIX package is simpler: the payload files (each deflated in independent 64 KiB parts), AppxManifest.xml, AppxBlockMap.xml (a hash per part) and [Content_Types].xml in one ZIP64 archive, with Registry.dat/User.dat hives for registry values; a bundle stores packages side by side; a signature adds AppxSignature.p7x (MSIX packages, Registry hive files (REGF)).

Each arrow is a page above. None of it needs Windows to produce: rubrapack builds the same bytes on Linux and on Windows.

3 Compound File Binary (CFB)

An `.msi` file is a Compound File Binary file ("structured storage"): a small file system of named streams inside one file. The format is specified in [MS-CFB]; this page is the part an MSI writer needs, plus what Windows' own writer does.

3.1 Sectors

- The file is a sequence of fixed-size sectors. **Version 3** uses 512-byte sectors (sector shift 9), **version 4** uses 4096-byte sectors (shift 12). [spec]
- The header is at offset 0. Sector number N starts at file offset $(N + 1) * \text{sector_size}$ in both versions; in version 4 the header therefore occupies a whole 4096-byte sector whose bytes after the header are zero. [spec]
- `msi.dll` writes **version 4** for every new database, whatever its size (20 KB to 10 MB were tried), with minor version `0x003E`. Either version is accepted when installing; rubrapack writes version 4 by default and can write version 3. [observed]

Special sector numbers in chains and tables: [spec]

Value	Meaning
FFFFFFFA	largest regular sector number
FFFFFFFC	DIFAT sector (in the FAT)
FFFFFFFD	FAT sector (in the FAT)
FFFFFFFE	end of chain
FFFFFFF	free sector / no stream

3.2 Header (first 512 bytes) [spec]

Offset	Size	Field	Value written
0	8	signature	D0 CF 11 E0 A1 B1 1A E1
8	16	CLSID	zero
24	2	minor version	003E
26	2	major version	3 or 4
28	2	byte order	FFFE (bytes FE FF)
30	2	sector shift	9 or 12
32	2	mini sector shift	6 (64-byte mini sectors)
34	6	reserved	zero
40	4	number of directory sectors	0 in version 3; the count in version 4
44	4	number of FAT sectors	
48	4	first directory sector	
52	4	transaction signature	0
56	4	mini stream cutoff	4096
60	4	first mini FAT sector	FFFFFFFE if none
64	4	number of mini FAT sectors	
68	4	first DIFAT sector	FFFFFFFE if none
72	4	number of DIFAT sectors	
76	436	first 109 FAT sector numbers (DIFAT)	unused entries FFFFFFFF

3.3 FAT, DIFAT, mini FAT [spec]

- The **FAT** is an array of u32, one entry per sector, giving the next sector of the chain the sector belongs to. FAT sectors themselves are marked FFFFFFFD.
- The FAT's own sector numbers are listed in the **DIFAT**: the first 109 in the header, the rest in DIFAT sectors, each holding $\text{sector_size} / 4 - 1$ numbers and, in its last u32, the next DIFAT sector (FFFFFFFE at the end). DIFAT sectors are marked FFFFFFFC in the FAT.
- With 4096-byte sectors, 109 FAT sectors already cover about 457 MB, so real MSI files in version 4 have no DIFAT sectors. With 512-byte sectors DIFAT starts at about 7 MB.
- Streams smaller than the **cutoff (4096 bytes)** live in the **mini stream**, in 64-byte mini sectors chained through the **mini FAT** (same layout as the FAT). The mini stream is itself stored as the root directory entry's own regular stream.

The FAT must cover its own sectors and the DIFAT's; a writer computes the counts by iterating until they stop changing.

3.4 Directory [spec]

The directory is a chain of sectors holding 128-byte entries. Entry 0 is the root.

Offset	Size	Field
0	64	name, UTF-16LE, NUL-terminated (at most 31 characters + NUL)
64	2	name length in bytes, including the NUL
66	1	type: 0 unused, 1 storage, 2 stream, 5 root
67	1	colour: 0 red, 1 black
68	4	left sibling (FFFFFFF = none)
72	4	right sibling
76	4	child (storages and root only)
80	16	CLSID
96	4	state bits
100	8	creation time
108	8	modification time
116	4	starting sector (regular or mini, by size)
120	8	stream size (in version 3 only the low 32 bits count)

- The root entry is named Root Entry; its starting sector and size describe the mini stream.
- The root entry of an MSI carries the CLSID {000C1084-0000-0000-C000-000000000046}, stored as bytes 84 10 0C 00 00 00 00 00 C0 00 00 00 00 00 00 46. [spec] [observed]
- Unused entries are all zero except the three link fields, which are FFFFFFFF. [spec]
- The children of a storage form a **red-black tree** ordered first by name length, then by comparing the upper-cased UTF-16 names. [MS-CFB] allows the simplest valid tree: every node black, the tree a plain balanced binary search tree. rubrapack builds that - a balanced tree over the sorted names, all nodes black - and `msi.dll` opens it. [spec] [observed]
- Times may be zero. Writing zero times (and no other clock input) is what makes a CFB writer deterministic. [spec]

3.5 A simple, deterministic writer

rubrapack lays the file out in this order, all runs contiguous:

```
header | FAT sectors | DIFAT sectors | directory | mini FAT | mini stream | large streams in order
```

1. Sort stream sizes into "mini" (< 4096) and "regular".
2. Mini streams are packed back to back in 64-byte units; the mini stream length is the sum.
3. Count directory, mini FAT and mini stream sectors, then FAT and DIFAT sectors (iterate).

4. Fill FAT chains for each contiguous run, write the directory tree, mini FAT, FAT, DIFAT, header.

3.6 Reading safely

A reader must refuse, rather than follow: chains that loop (a chain never reaching FFFFFFFE within the number of sectors in the file), sector numbers beyond the file, a chain shorter than the stream size needs, directory links out of range, sibling trees that visit a node twice, and counts beyond sane limits. None of this costs much, and a crafted .msi otherwise hangs or crashes the reader.

4 The MSI database inside the compound file

Microsoft documents the *meaning* of the Windows Installer tables (Microsoft Learn, "Database Tables"), but not how a database is laid out in the compound file. Everything on this page about the layout was established by creating databases through `msi.dll`, reading the streams back byte for byte, and checking that databases written from these rules open, export and install. [observed] unless marked otherwise.

4.1 Streams

Every table is one stream directly under the root storage. There are no sub-storages in an ordinary package.

Stream names

A table named `T` is stored under the name `U+4840` followed by `T` **packed** two characters per UTF-16 unit:

1. Map each character of this 64-character alphabet to 0..63: 0-9 -> 0..9, A-Z -> 10..35, a-z -> 36..61, . -> 62, _ -> 63.
2. Two alphabet characters in a row become one unit $0x3800 + \text{first} + (\text{second} \ll 6)$.
3. A single alphabet character (the last one, or one followed by a character outside the alphabet) becomes $0x4800 + \text{value}$.
4. Any other character is written as itself.

The packed name (with the `U+4840` prefix for tables) must fit the 31-unit CFB name limit, which allows table names of up to 60 alphabet characters. Unpacking reverses the steps.

Example: `_Columns` -> `U+4840 U+3B3F U+43F2 U+4438 U+45B1`.

Other streams:

Stream	Name
a Binary/Icon cell (OBJECT column)	<code><Table>.<key></code> packed the same way without the <code>U+4840</code> prefix, e.g. <code>Binary.Logo</code> (compound keys joined with <code>.</code>)
an embedded cabinet	the name after <code>#</code> in <code>Media.Cabinet</code> (e.g. <code>cab1.cab</code>), packed, no prefix
summary information	<code>\x05SummaryInformation</code> - not packed (see Summary information)

4.2 The string pool: `_StringPool` and `_StringData`

All strings of all tables live once in a shared pool; table cells hold string ids.

`_StringPool`:

```

u32  header      low 31 bits: the database code page; bit 31: string references are 3 bytes
then per string id 1, 2, 3, ... (id 0 is "no string" and is not stored):
u16  length      byte length in _StringData
u16  refs        bits 0-14: reference count; bit 15: set exactly when the string has a byte >= 0x80

```

- **Long strings** (64 KiB of bytes or more): the entry is `length = 0`, `refs` as above (non-zero), followed by an extra `u32` with the full byte length. The pair still describes one id. Seen: a 70002-byte string used once -> `0000 8001 00011172`.
- An entry with `length = 0` and `refs = 0` is a free id.

- **Reference count** = the number of cells that hold the string, plus, per table, 1 for its `_Tables` row and, per column, 1 for the table name in `_Columns` and 1 for the column name. (Checked by recounting every database `msi.dll` produced.)
- `_StringData` is all the strings' bytes concatenated in id order, in the database code page. Lengths are **bytes**, not characters.
- **An empty string is never stored**: writing "" into a cell stores null.
- With more than 65535 distinct strings the header's bit 31 is set and every string reference in every table becomes 3 bytes (low 16 bits, then the high byte).

Code page

The database code page is the pool header's low bits: 0 when never set, otherwise what was set through the `_ForceCodepage` import. **65001 (UTF-8) works for every table** on current Windows: Korean, Japanese and supplementary-plane (e.g. U+20000, U+1F600) file and folder names, registry keys and values, shortcut names and the product name all install with exactly the right UTF-16 text, and dialogs display them - also under a system locale whose ANSI code page cannot hold Korean (en-US, 1252), so no separate Unicode setup program is needed. A UTF-16 code page (1200) is not possible here: the pool holds single-byte-unit strings. [observed] Windows Installer does not normalize names: a folder named with decomposed Hangul (U+1100 U+1161) is installed with exactly those code units, next to - not instead of - one named U+AC00. [observed]

4.3 System tables

Table	Columns	Key
<code>_Tables</code>	Name (string)	Name
<code>_Columns</code>	Table (string), Number (i2, 1-based), Name (string), Type (i2)	Table, Number

`_Tables` does not list itself or `_Columns`. A table with no rows has no stream at all, only its `_Tables` and `_Columns` rows. `_Validation`, when present, is an ordinary table.

Column type bits (`_Columns.Type`)

Bits	Meaning
0x00FF	width: maximum string length (0 = unlimited), or 2 / 4 for integers
0x0100	valid
0x0200	localizable
0x0400	non-binary (set for text, clear for OBJECT)
0x0800	string (set for text and OBJECT)
0x1000	nullable
0x2000	part of the primary key

Values `msi.dll` uses for common SQL column types:

SQL	Type
CHAR(72) NOT NULL (key)	0x2D48
CHAR(72) (nullable)	0x1D48
CHAR(255) NOT NULL LOCALIZABLE	0x0FFF
LONGCHAR NOT NULL LOCALIZABLE	0x0F00
SHORT NOT NULL	0x0502
SHORT (nullable)	0x1502
SHORT NOT NULL (key)	0x2502
LONG NOT NULL	0x0104
OBJECT NOT NULL	0x0900

Integer columns do not have the non-binary bit.

4.4 Table streams

- A table stream is **column-major**: every row's cell of column 1, then every row's cell of column 2, and so on. The row count is the stream size divided by the row width.
- Cell widths: string reference 2 bytes (3 with long references), 16-bit integer 2 bytes, 32-bit integer 4 bytes, OBJECT 2 bytes.
- Integers are stored with the sign bit flipped: $\text{stored} = \text{value} \wedge 0x8000$ (16-bit) or $\text{value} \wedge 0x80000000$ (32-bit). **Stored 0 means null**. Consequently -32768 and -2147483648 cannot be stored.
- An OBJECT cell stores 1 when a stream exists, 0 for null.
- **Rows are sorted by the primary-key cells' stored numbers** - string ids, flipped integers - key columns in order. Windows Installer relies on this order.

A writer that assigns string ids in byte order of the strings gets rows sorted by string value for free, which is also the order an IDT export uses.

4.5 IDT archive files (what MsiDatabaseExport writes)

Useful as a reference output: a reader that exports byte-identical IDT files decodes the database the way Windows does.

```
line 1: column names separated by TAB
line 2: column types: s/S (string), l/L (localizable string), i/I (integer), v/V (binary),
        upper case = nullable, followed by the width (0 = unlimited; 2 or 4 for integers)
line 3: [<code page> TAB] <table name> TAB <key column> [TAB <key column> ...]
rows   : cells separated by TAB, lines end with CR LF
```

- The code page prefix on line 3 appears **only when the table holds a non-ASCII string**.
- Rows are sorted by primary-key **values** (strings by bytes, integers signed) - not by stored order.
- Null prints as an empty field. Binary cells print <key>.ibd; the bytes go to <Table>/<key>.ibd.
- TAB, CR and LF inside values are written as 0x10, 0x11 and 0x19. [spec]
- _ForceCodepage.idt is two empty lines then <code page> TAB _ForceCodepage.
- _SummaryInformation.idt has header lines PropertyId TAB Value, i2 TAB l255, _SummaryInformation TAB PropertyId and one row per property. Dates are printed yyyy/mm/dd hh:mm:ss in the **local time of the machine doing the export**.

4.6 Reading safely

Check that the pool lengths add up to exactly the size of _StringData, that every string reference in a table points to a used id, that table stream sizes are a multiple of the row width, and that _Columns numbers each table's columns 1..n without gaps.

5 Summary information

Every package has a stream `\x05SummaryInformation` (the first character is U+0005; the name is not packed). It is an OLE property set as specified in [MS-OLEPS]; Microsoft Learn ("Summary Information Stream Property Set") says which properties an installer package uses.

5.1 Layout [spec] [observed]

```

u16  byte order      FFFE
u16  version         0 (msi.dll writes 0)
u32  OS field        msi.dll writes 0x00020206
16   CLSID           zero
u32  section count   1
16   FMTID           F29F85E0-4FF9-1068-AB91-08002B27B3D9, stored E0 85 9F F2 F9 4F 68 10 AB 91 08 00 2B 27 B3 D9
u32  section offset  48

```

section:

u32 section size

u32 property count

count x (u32 property id, u32 offset from the section start)

values, each padded to a multiple of 4 bytes:

VT_I2 (2) u32 type, i16 value, 2 bytes padding

VT_I4 (3) u32 type, i32 value

VT_LPSTR (30) u32 type, u32 byte count including the NUL, bytes, NUL, padding

VT_FILETIME (64) u32 type, u64 100-ns intervals since 1601-01-01 UTC

5.2 Properties an installer package sets

Id	Name	Type	Value
2	Title	LPSTR	e.g. Installation Database
3	Subject	LPSTR	product name
4	Author	LPSTR	manufacturer
5	Keywords	LPSTR	e.g. Installer
7	Template	LPSTR	<platform>;<language id>: x64;1033, Arm64;1042, Intel;1033
9	Revision Number	LPSTR	the package code : a GUID, new for every different package file
12, 13	Create / Last Save time	FILETIME	optional
14	Page Count	I4	minimum installer version: 200 for x64 and x86, 500 for Arm64
15	Word Count	I4	bit 1 = files are compressed (in cabinets); 2 for a normal package
18	Creating Application	LPSTR	any

5.3 The code page trap - keep summary strings ASCII [observed]

Property 1 (CodePage, VT_I2) says how the LPSTR bytes are encoded. On Windows 11 25H2:

- **65001**: msi.dll writes the strings correctly as UTF-8, but reads the code page back as the signed value -535, fails to convert every string (the installation log says "Failed to retrieve # 9 summary info property. GetLastError returned 87, the code page is -535") and refuses the package with error 1620.
- **1200 (UTF-16)**: refused the same way (log: "... the code page is 1200"), even with complete UTF-16 strings and byte counts that follow [MS-OLEPS].
- **No code page property and ASCII strings**: installs.

So: leave property 1 out and write every summary string in ASCII. Localized product names belong in the Property table (ProductName), which uses the database code page - and 65001 works there (see The MSI database inside the compound file).

6 The smallest package that installs, repairs, upgrades and uninstalls

Table meanings are documented on Microsoft Learn ("Database Tables", "Standard Actions", "Suggested InstallExecuteSequence"). This page is a tested recipe: a package built exactly like this installs per machine, survives repair, upgrades an older version, refuses a downgrade and uninstalls cleanly on Windows 11. [observed]

6.1 Tables and columns

Types use the notation of The MSI database inside the compound file (s72 = CHAR(72), upper case = nullable, l = localizable, i2/i4 integers). Keys are in bold.

Table	Columns
Property	Property s72, Value l0
Directory	Directory s72, Directory_Parent S72, DefaultDir l255
Component	Component s72, ComponentId S38, Directory_ s72, Attributes i2, Condition S255, KeyPath S72
Feature	Feature s38, Feature_Parent S38, Title L64, Description L255, Display I2, Level i2, Directory_ S72, Attributes i2
FeatureComponents	Feature_ s38, Component_ s72
File	File s72, Component_ s72, FileName l255, FileSize i4, Version S72, Language S20, Attributes I2, Sequence i4
MsiFileHash	File_ s72, Options i2, HashPart1..HashPart4 i4
CreateFolder	Directory_ s72, Component_ s72
Media	DiskId i2, LastSequence i4, DiskPrompt L64, Cabinet S255, VolumeLabel S32, Source S72
Upgrade	UpgradeCode s38, VersionMin S20, VersionMax S20, Language S255, Attributes i4, Remove S255, ActionProperty s72
CustomAction	Action s72, Type i2, Source S72, Target S255
InstallExecuteSequence, InstallUISequence	Action s72, Condition S255, Sequence I2

File.Sequence and Media.LastSequence as 32-bit integers let a package hold more than 32767 files.

6.2 Property

ProductCode, ProductName, ProductVersion (a.b.c, a and b up to 255, c up to 65535; a fourth part is allowed but ignored when versions are compared), Manufacturer, ProductLanguage (1033, 1042, ...), UpgradeCode, ALLUSERS=1 (per machine), REBOOT=ReallySuppress, MSIRESTARTMANAGERCONTROL=Disable (see "Files in use" below), and SecureCustomProperties listing the two upgrade properties below.

6.3 Directory

- TARGETDIR with no parent and DefaultDir = SourceDir.
- Each standard folder used (ProgramFiles64Folder, ProgramFilesFolder, ...) as a child of TARGETDIR with DefaultDir = .. Windows resolves these names itself. For an x64 or Arm64 package use the ...64Folder names, for x86 the plain ones.
- Your folders below them with DefaultDir = SHORT|Long name. The long name may be any Unicode text (with code page 65001). The short name must be a valid 8.3 ASCII name, unique among all

files and folders of the same parent; when the long name already is a valid 8.3 name it can be written alone.

6.4 Components, features, files

- **One component per file**, the file as its key path. ComponentId is a GUID that must stay the same for the same resource at the same place for the life of the product (see Deterministic identities and reproducible packages). Attributes 256 (64-bit) for x64 and Arm64 packages, 0 for x86.
- A feature with Level 1; Display 0 hides it. Map every component in FeatureComponents. A child feature names its parent in Feature_Parent. A feature whose Level is above INSTALLLEVEL (1 unless the package sets it) is not installed by default; MsiConfigureFeature can add it later, and its files then arrive. [observed]
- File.FileName is SHORT|Long like DefaultDir. Attributes 512 marks the file vital. Sequence numbers 1..n are the order of the files inside the cabinet.
- Files without a version resource need an **MsiFileHash** row: the MD5 of the file, read as four little-endian 32-bit integers (stored as signed values). Installed files hash with MsiGetFileHash to exactly these values. Files with a version resource put the version in File.Version instead (and need no hash).

6.5 Empty folders

A folder that must exist without files gets its own Directory row, a component whose Directory_ is that folder and whose KeyPath is null (the folder itself is the key path), a CreateFolder row pointing at both, and a FeatureComponents row. CreateFolders makes it at install time; RemoveFolders removes it at uninstall if it is empty. [observed] With component attribute 16 (permanent) the folder stays after uninstall while everything else is removed. [observed]

6.6 Media and the cabinet

One row: DiskId 1, LastSequence n, Cabinet #cab1.cab - the # means "a stream inside this package named cab1.cab". The cabinet holds the files named by their File keys, in Sequence order (Cabinets, MSZIP and deflate). Summary Word Count 2 says the files are compressed into cabinets.

6.7 Major upgrade and downgrade refusal

Two Upgrade rows with the package's UpgradeCode:

VersionMin	VersionMax	Attributes	ActionProperty	Meaning
this version	-	0x102 (only detect, min inclusive)	NEWER_FOUND	same or newer version installed
-	this version	0x001 (migrate features)	OLDER_FOUND	older version installed: remove it

The Upgrade table matches by UpgradeCode, version and language only - not by architecture. If an x64 and an x86 build share one UpgradeCode, installing one removes the other as "older". Give each architecture its own UpgradeCode when both may be installed side by side (verified: two architectures with separate codes install and uninstall independently). [observed]

An error custom action (type 19, Target = the message; it is a formatted string, so [ProductName] works) conditioned on NEWER_FOUND stops the installation with error 1603 when a same-or-newer version is present. Every version needs a new ProductCode (and every package file a new package code).

6.8 Running an installed program to register and unregister

Some products must register themselves (an input method, a shell extension) through their own program rather than through table rows. The pattern that keeps install, repair, upgrade and removal atomic uses the component action state of that program's component C (\$C = what this installation

does to it, ?C = its state before; 2 absent, 3 local) [spec], with type 18 actions (Source = the program's File key, Target = its arguments), all deferred (0x400) and not impersonated (0x800):

Action	Type	Where	Condition	Runs
...UndoRollback	18+0x100+0x400+0x800+0x40	before RemoveFiles	\$C=2 AND ?C=3	register (rollback of the next row)
...Undo	18+0x400+0x800	after it, before RemoveFiles	\$C=2 AND ?C=3	unregister
...DoRollback	18+0x100+0x400+0x800+0x40	after InstallFiles	\$C>2 AND ?C<>3	unregister
...RedoRollback	same	after it	\$C>2 AND ?C=3	register
...Do	18+0x400+0x800	after both	\$C>2	register

A rollback action must be sequenced *before* the action it undoes: rollback runs the script backwards, and only rollback actions already in the script are run. Rollback actions ignore their exit code (0x40); forward actions do not, so a failing register or unregister fails the installation and rolls it back. Observed on Windows 11: repair runs ...Do again; a failing unregister rolls the removal back and the program (still present) registers again; when an upgrade fails, the new package's ...DoRollback runs, then the old version's files return and the old package's own ...UndoRollback registers the old program again. [observed]

Nothing that writes to the script may stand between InstallInitialize and RemoveExistingProducts: with any deferred or rollback custom action there, every upgrade stops with error 2613 ("RemoveExistingProducts action sequenced incorrectly"). [observed]

6.9 Registry values

Registry (**Registry** s72, Root i2, Key l255, Name L255, Value L0, Component_ s72) is written by WriteRegistryValues (5000) and undone at uninstall; RemoveRegistry (same columns without Value) by RemoveRegistryValues (2600). Root 0 = HKCR, 1 = HKCU, 2 = HKLM. The value's first characters choose its type: #x binary (hex), ## expandable string, # followed by digits a DWORD (up to #4294967295), [~] anywhere a multi-string ([~]a[~]b[~]); a plain string that starts with # is written as ##. A Name of - in RemoveRegistry deletes the whole key. A failed installation restores overwritten values and removed keys. [observed]

A component whose key path is a registry value has attribute 4 and KeyPath = the Registry row. The component's 64-bit attribute (256) chooses the registry view: without it, a 64-bit package writes to the 32-bit view (WOW6432Node). A 32-bit component in a 64-bit package is legal; a 64-bit component in a 32-bit package is not.

REG_QWORD cannot be expressed in the Registry table. rubrapack writes it with a DLL custom action from the Binary table (type 1): an immediate action reads the component action states and the current values and passes two lists as CustomActionData - one to a deferred action that writes or deletes, one to its rollback twin that restores what was there. The DLL's bitness must match the package (the engine loads it into a custom action server of the package's architecture). [observed: x64 and x86]

File types and URL schemes are plain Registry rows under Root 0 (HKCR) in the program's component, not the Extension/Verb/ProgId tables (those bring advertisement and repair on first use): .ext (default) = the ProgId; ProgId (default) = its description, ProgId\DefaultIcon = [#File], 0, ProgId\shell\open\command = "[#File]" "%1"; for a scheme, scheme (default) = URL:<description>, URL Protocol = empty (a Null Value with a Name writes an empty string), and the same DefaultIcon and shell\open\command. Root 0 follows the installation: HKLM\Software\Classes per machine, HKCU\Software\Classes per user. Opening a file of a type only this program claims then starts it directly. [observed]

6.10 Shortcuts

Shortcut (**Shortcut** s72, Directory_ s72, Name l128 SHORT!Long without .lnk, Component_ s72, Target [#FileKey] for a non-advertised shortcut, Arguments (formatted), Description (plain text), Hotkey,

Icon_, IconIndex, ShowCmd, WkDir = a Directory key) is written by CreateShortcuts (4500) and removed by RemoveShortcuts (3200). Put the shortcut in its target file's component. A folder made only for shortcuts is not removed by itself: add a RemoveFile row (FileName null, DirProperty = the folder, InstallMode 2) for it and each parent below the standard folder. With ALLUSERS=1, ProgramMenuFolder and DesktopFolder are the all-users Start menu and the Public Desktop. A failed installation leaves no shortcut or folder; repair recreates a deleted one. [observed]

6.11 Removing files and duplicating them

RemoveFile (**FileKey** s72, Component_ s72, FileName L255 with */? or null for the folder, DirProperty s72, InstallMode i2: 1 install, 2 uninstall, 3 both) runs in RemoveFiles when its component is installed (1) or removed (2). A component with no key path file and a Directory_ works as the carrier. DuplicateFile (**FileKey** s72, Component_ s72 = the source's component, File_ s72, DestName L255 SHORT|Long, DestFolder S72) runs in DuplicateFiles (4210) and RemoveDuplicateFiles. Files removed at install come back when the installation fails; a folder that existed before the installation is left in place at uninstall, even when empty. [observed]

6.12 Environment variables

Environment (**Environment** s72, Name l255, Value L255 formatted, Component_ s72), written by WriteEnvironmentStrings (5200) and RemoveEnvironmentStrings. Name prefixes: * system variable (without it a per-user one), = create or set, - undo when the component is removed. Value [~];x appends ;x, x; [~] prepends. With -, uninstall deletes a set variable and takes only the appended or prepended part out of a variable that existed before; without - nothing is undone. A failed installation restores the previous values. [observed]

6.13 INI files

IniFile (**IniFile** s72, FileName l255 SHORT|Long, DirProperty S72, Section l96, Key l128, Value l255 formatted, Action i2: 0 add line, 1 create line, 3 add tag, Component_ s72) is applied by WriteIniValues (5100) and undone when the component is removed; RemoveIniFile (same columns, Value nullable, Action 2 remove line, 4 remove tag) by RemoveIniValues, which runs before InstallFiles. An add tag appends ,value to a comma list and uninstall removes just that item. Non-ASCII file, section, key and value names work. A failed installation restores the file. [observed]

6.14 Searches and launch conditions

AppSearch (**Property, Signature_**) at 50 in both sequences sets the property from a locator with the same signature: RegLocator (Root, Key, Name, Type 2 = raw value, +16 = 64-bit view), DrLocator (Path may start with a folder property, like [System64Folder]) with a Signature row for a file (FileName, MinVersion), or CompLocator (ComponentId, Type 1 = key file). The property must be public and listed in SecureCustomProperties to reach the server side. LaunchCondition (**Condition**, Description formatted) at 100 in both sequences stops the installation with the description when a condition is false. [observed]

6.15 Services, fonts, permissions

ServiceInstall (Name, DisplayName and Description formatted, ServiceType 0x10, StartType 2/3/4, ErrorControl 1, StartName null or NT AUTHORITY\LocalService, Arguments formatted, Component_ = the exe's component) with InstallServices (5800); ServiceControl Event flags 0x1 start on install, 0x2 stop on install, 0x20 stop on removal, 0x80 delete on removal, Wait 1, with StopServices (1900), DeleteServices (2000), StartServices (5900). Font (File_, FontTitle null = read from the font) with RegisterFonts/UnregisterFonts; the file must be in FontsFolder itself. MsiLockPermissionsEx (**MsiLockPermissionsEx**, LockObject, Table = CreateFolder, File, Registry or ServiceInstall, **SDDLText** (the column name), Condi-

tion) needs Windows Installer 5.0 (summary page count 500); a folder gets it through a CreateFolder row. A failed installation leaves no service or font. [observed]

6.16 Cabinets, administrative images, advertisement

Several cabinets: one Media row each (DiskId 1..n, LastSequence = the last file's sequence in it); embedded ones are streams named in Cabinet with #, external ones are files next to the package named in Cabinet without # (long names work). AdminExecuteSequence (CostInitialize 800, FileCost 900, CostFinalize 1000, InstallValidate 1400, InstallInitialize 1500, InstallAdminPackage 3900, InstallFiles 4000, InstallFinalize 6600) and AdminUISequence make `msiexec /a` write an uncompressed image that installs like the original; AdvtExecuteSequence (CostInitialize, CostFinalize, InstallValidate, InstallInitialize, PublishFeatures 6300, PublishProduct 6400, InstallFinalize) makes `msiexec /jm` advertise the product. [observed]

6.17 Per-user and dual packages

The single-package form: `ALLUSERS=2` with `MSIINSTALLPERUSER=1` installs per user - the engine points `ProgramFilesFolder/ProgramFiles64Folder` at `%LOCALAPPDATA%\Programs` and the menu and desktop folders at the user's - and `ALLUSERS=1 MSIINSTALLPERUSER=""` installs per machine. Summary Word Count bit 8 says no elevation is needed. Registry Root -1 (HKMU) is HKCU per user and HKLM per machine; an Environment name without * is a user variable. Once a per-user product is installed the engine deletes `MSIINSTALLPERUSER`, so a launch condition that tests it must read `Installed OR ...` or the product can no longer be removed; in general, write every launch condition as `Installed OR (...)`. [observed]

6.18 Files in use

When a file to be replaced or removed is held by a running program (a DLL loaded into it):

- With Restart Manager, the default, Windows Installer tries to **shut down every program holding such a file, even in a silent installation** (/qn), and restarts it afterwards; if one does not close, the whole installation fails (1601). [observed]
- With `MSIRESTARTMANAGERCONTROL=Disable` in the Property table, the engine moves the held file aside (`C:\Config.Msi\*.rbf`), puts the new file in place at once and returns 0; the program keeps running on the old copy, programs started afterwards load the new file, and the old copy is deleted at the next restart. [observed]
- A property given on the command line reaches only the package being installed. During an upgrade, the removal of the old version follows **the old package's** Property table - author the property from the first version on. [observed]

6.19 Sequences

`InstallExecuteSequence` (conditions in brackets):

```
FindRelatedProducts 25, <refuse-downgrade action> 30 [NEWER_FOUND], CostInitialize 800,
FileCost 900, CostFinalize 1000, MigrateFeatureStates 1200, InstallValidate 1400,
InstallInitialize 1500, RemoveExistingProducts 1501, ProcessComponents 1600,
UnpublishFeatures 1800, RemoveFiles 3500, RemoveFolders 3600, CreateFolders 3700,
InstallFiles 4000, RegisterUser 6000, RegisterProduct 6100, PublishFeatures 6300,
PublishProduct 6400, InstallFinalize 6600
```

`InstallUISequence`: `FindRelatedProducts 25`, the refuse-downgrade action `30 [NEWER_FOUND]`, `CostInitialize 800`, `FileCost 900`, `CostFinalize 1000`, `MigrateFeatureStates 1200`, `ExecuteAction 1300` (and the dialogs, see Dialogs).

`RemoveExistingProducts` right after `InstallInitialize` puts the removal of the old version inside the new installation's transaction, so a failed upgrade rolls back to the old version. [observed: a deferred

custom action that fails right after InstallFiles makes the upgrade end with 1603, and the old version is registered again with its files byte for byte; a failed first installation leaves no files and no registration.]

6.20 Dialogs

A package with dialogs carries these tables (types as above):

Table	Columns
Dialog	Dialog s72, HCentering i2, VCentering i2, Width i2, Height i2, Attributes I4, Title L128, Control_First s50, Control_Default S50, Control_Cancel S50
Control	Dialog s72, Control s50, Type s20, X i2, Y i2, Width i2, Height i2, Attributes I4, Property S72, Text L0, Control_Next S50, Help L50
ControlEvent	Dialog s72, Control s50, Event s50, Argument s255, Condition S255, Ordering I2
ControlCondition	Dialog s72, Control s50, Action s50, Condition s255
EventMapping	Dialog s72, Control s50, Event s50, Attribute s50
TextStyle	TextStyle s72, FaceName s32, Size i2, Color I4, StyleBits I2
UIText	Key s72, Text L255
Binary	Name s72, Data v0 (a stream)
RadioButton	Property s72, Order i2, Value s64, X i2, Y i2, Width i2, Height i2, Text L0, Help L50
ComboBox	Property s72, Order i2, Value s64, Text L64

What the engine checks when it shows a dialog (each seen as an error dialog carrying the number):

- **Tab order.** Control_Next must form one cycle through every control that has one, starting at Control_First. A chain that leaves a control out, or ends at a control whose Control_Next is empty, stops the installation with 2810 or 2809. Static text takes no part in the cycle. [observed] rubrapack checks every dialog it builds and refuses to write a broken one (RP0010).
- **The error dialog.** The dialog named by the ErrorDialog property needs a Text control named ErrorText and an Icon control named ErrorIcon (2835 otherwise); its Attributes carry the error-dialog bit (0x10000), and push buttons named A, C, I, N, O, R, Y with EndDialog arguments ErrorAbort .. ErrorYes are shown as the message needs. [observed]
- **Brackets in texts.** Text is a formatted string: [Next] is read as a property and shows as nothing. [observed] Quote button names in running text instead.
- **Files in use.** With Restart Manager off, the engine shows the dialog named FilesInUse (buttons ending with Retry, Ignore, Exit) with a ListBox bound to FileInUseProcess. The **ListBox table must exist, even empty**: without it the engine logs 2205 and skips the dialog, and the installation goes on as if Ignore was chosen. In a major upgrade the dialog comes twice (the new files, then the old version's removal). After Ignore the held file is moved aside and the installation ends with 0. [observed]
- **Error icon.** The engine puts its own icon for the message type into ErrorIcon (a warning triangle for a launch condition), whatever the control's Binary holds. [observed]
- **List order.** A ComboBox lists its items alphabetically unless the control has the Sorted attribute (0x10000); with it they follow the Order column. [observed] rubrapack sets it.
- **Elevation.** A per-machine installation started interactively by a non-elevated user asks for consent (UAC) when the execute sequence starts, on the secure desktop. [observed]
- **Code page.** With the database code page 65001, Korean titles, texts and RTF license text show correctly under a Korean and under an English (1252) system locale. observed, see [msi-database.md]

rubrapack's sets: every dialog is 370 x 270 dialog units with a banner strip (a Bitmap control 0,0,370,44 whose picture is Binary.RpBanner), the title in bold ({\RpTitle}, a TextStyle) and a line of description in it, a Line at 44 and at 234, and Back / Next / Cancel at y 243. The InstallUISequence adds the welcome (1230, NOT Installed) or the maintenance dialog (1240, Installed AND NOT RESUME AND NOT Preselected), the progress dialog (1280, modeless, subscribed to ActionText and SetProgress through EventMapping)

and the three exit dialogs at -1 (success), -2 (cancelled) and -3 (fatal). The install folder dialog puts the folder's Directory key in a PathEdit, and its Next runs SetTargetPath before NewDialog, which checks the path. The license text is a ScrollableText control holding RTF: plain text becomes \uN? escapes (characters above U+FFFF as a surrogate pair), one \par per line.

Author pages are ordinary Dialog rows in the same frame; Control_Next runs through their controls in position order and on to Back, Next and Cancel. A radio group is a RadioButtonGroup control whose buttons are RadioButton rows (positions relative to the group); a drop-down list is a ComboBox control with ComboList (0x20000) and Sorted, filled from ComboBox rows. Their properties are added to SecureCustomProperties, so values chosen in the dialogs or given on the command line reach the execute sequence. [observed]

6.21 What this recipe does not cover yet

Custom actions other than the error type, the register pair and the REG_QWORD helper above; and _Validation (needed by validation tools, not by the installer). These pages grow as rubrapack implements them.

7 Program files: machine type and version

A package writer reads two facts from every Portable Executable (.exe, .dll, ...) it packs: the machine type, to refuse a file built for the wrong architecture, and the version resource, because Windows Installer treats versioned and unversioned files differently. Layout from the Microsoft PE/COFF specification and the VS_VERSIONINFO documentation. [spec]

7.1 Finding the headers [spec]

```
offset 0      "MZ"
offset 0x3C   u32  e_lfanew: offset of the PE signature
e_lfanew     "PE\0\0"
+4           COFF header: u16 machine, u16 number of sections, ..., u16 optional header size (at +16)
+24          optional header: u16 magic 0x10B (PE32) or 0x20B (PE32+); the data directories
              start at +96 (PE32) or +112 (PE32+), preceded by their count
then         section table: 40 bytes per section (virtual size +8, virtual address +12,
              raw size +16, raw offset +20)
```

Machine values: 0x8664 x64, 0xAA64 Arm64, 0x014C x86. A file that starts with MZ but has no valid PE\0\0 header is an ordinary data file.

7.2 The version resource [spec]

1. Data directory 2 is the resource table (an RVA and size). Map RVAs to file offsets through the section table.
2. Resource directories are three levels deep: type -> name -> language. Each directory has a 16-byte header (named and ID entry counts at +12 and +14) followed by 8-byte entries (u32 name or ID, u32 offset; the high bit of the offset marks a sub-directory).
3. Type 16 (RT_VERSION), its first name, its first language: the leaf is a data entry (u32 RVA, u32 size).
4. The data is VS_VERSIONINFO: u16 length, u16 value length, u16 type, the UTF-16 key VS_VERSION_INFO with its NUL, padding to 4 bytes, then VS_FIXEDFILEINFO whose first u32 is 0xFEEF04BD. dwFileVersionMS (+8) and dwFileVersionLS (+12) give the version HIWORD(MS).LOWORD(MS).HIWORD(LS).LOWORD(LS).

7.3 What goes into the package [observed]

- Versioned file: File.Version = the four-part version, File.Language = the language MsiGetFileVersion reports, which is the first language of VarFileInfo\Translation (for example 1033, 1042); no MsiFileHash row. Installed files read back with the same version.
- Unversioned file: no version, a MsiFileHash row (The smallest package that installs, repairs, upgrades and uninstalls).
- Machine type: an x64 package takes x64 files, an Arm64 package Arm64 files, an x86 package x86 files. A deliberate exception (a 32-bit helper in a 64-bit package) should be declared, not silently accepted; the component's own bitness does not change.

7.4 Reading safely

Check every offset and size against the file length before using it, map RVAs only through a section that holds the whole range, and stop at the three expected directory levels - crafted files with loops or out-of-range pointers are common.

8 Cabinets, MSZIP and deflate

8.1 Cabinet layout [spec: MS-CAB]

```
CFHEADER (36 bytes when no reserve fields):
  "MSCF", u32 0, u32 cabinet size, u32 0, u32 offset of the first CFFILE, u32 0,
  u8 minor version 3, u8 major version 1, u16 folder count, u16 file count, u16 flags (0),
  u16 set id, u16 cabinet index (0)
CFFOLDER (8 bytes each):
  u32 offset of the folder's first CFDATA, u16 number of CFDATA blocks, u16 compression
  (0 = none, 1 = MSZIP)
CFFILE (per file):
  u32 uncompressed size, u32 offset inside the folder's uncompressed data, u16 folder index,
  u16 date, u16 time, u16 attributes, NUL-terminated name
CFDATA (per block):
  u32 checksum, u16 compressed bytes, u16 uncompressed bytes (at most 32768), data
```

- In an MSI, file names in the cabinet are the File table keys, which are ASCII.
- DOS date (year - 1980) << 9 | month << 5 | day, time hour << 11 | minute << 5 | second / 2. A fixed date (rubrapack writes 1980-01-01 00:00) keeps output deterministic; attributes 0x20.
- One folder holds at most 65535 blocks (about 2 GiB); more data needs more folders or cabinets.

Block checksum [spec]

```
checksum(bytes, seed):
  xor every complete little-endian u32 of the bytes into seed;
  the 1-3 remaining bytes form one more u32 with the FIRST remaining byte in the HIGHEST
  position used (3 left: b0<<16 | b1<<8 | b2; 2 left: b0<<8 | b1; 1 left: b0), xor it in.
block checksum = checksum(the 4 bytes "compressed size, uncompressed size" as stored,
                          checksum(block data, 0))
```

A checksum of 0 means "not computed"; readers accept it.

8.2 MSZIP [spec: MS-MCI]

Each CFDATA block of a folder with compression type 1 holds:

```
"CK" (43 4B), then one complete raw deflate stream (RFC 1951) for this block's
uncompressed bytes (at most 32768), ending with a final block.
```

The decompressor keeps the previous blocks of the same folder as its dictionary, so an encoder *may* refer back into earlier blocks. An encoder that never does (each block compressed on its own) produces valid MSZIP; rubrapack does that, and reads either kind. Windows extracts both.

8.3 A deflate encoder in brief [spec: RFC 1951]

1. **Match finding (LZ77):** hash the next 3 bytes, walk a chain of earlier positions with the same hash within 32 KiB, keep the longest match (3..258 bytes). Longer chain walks give better compression; a "lazy" step that also tries the next position and emits a literal when that match is longer helps noticeably.
2. **Blocks:** group up to a few ten thousand symbols. For each block compute the size of three encodings and write the smallest:

- fixed Huffman codes (literal/length 0-143: 8 bits, 144-255: 9, 256-279: 7, 280-287: 8; distances 5 bits);
 - dynamic Huffman codes: code lengths limited to 15 bits (7 for the code-length alphabet); package-merge gives optimal limited lengths; send HLIT, HDIST, HCLLEN, the code-length code in the order 16 17 18 0 8 7 9 6 10 5 11 4 12 3 13 2 14 1 15, then the run-length coded lengths (16 = repeat previous 3-6, 17 = zeros 3-10, 18 = zeros 11-138);
 - stored (byte-aligned LEN, NLEN, raw bytes; at most 65535 per stored block).
3. Huffman codes are written most significant bit first; everything else least significant bit first.
 4. Always give at least two symbols a code length (pair a lone symbol with a dummy), so every code is complete - some decoders reject incomplete codes.

Check an encoder by inflating its output with an independent implementation (for example the zlib library with raw deflate, window bits -15) and an MSI built with it by installing it and comparing installed files' hashes (Checking your output against Windows).

9 Deterministic identities and reproducible packages

Windows Installer identifies things by GUIDs and keys that must be **stable**: the same component must keep the same `ComponentId` in every version, or repair and upgrade misbehave. Generating them from the content, instead of storing them by hand, keeps them stable and makes builds reproducible. This page describes rubrapack's rules; other rules work too as long as they are stable.

9.1 Name-based GUIDs (UUID version 8) [spec: RFC 9562]

```
digest = SHA-256( u32le(len(tag)) || tag
                  || u32le(1)                (format version)
                  || for each field: u32le(len(field)) || field ) (fields in UTF-8)
uuid   = digest[0..16], then byte 6 = (byte 6 & 0x0F) | 0x80 (version 8)
                  byte 8 = (byte 8 & 0x3F) | 0x80 (variant 10)
text   = "{" + hex(bytes 0-3) "-" hex(4-5) "-" hex(6-7) "-" hex(8-9) "-" hex(10-15) + "}"
          upper case, bytes in order
```

Length prefixes keep ("ab", "c") and ("a", "bc") apart; the tag keeps different kinds of identity apart.

Identity	Tag	Fields
ComponentId	rubrapack.component	upgrade code, scope (machine), component architecture, logical target path (<dir id>/<file name>), key path kind (file), key path name (the File key)
ProductCode	rubrapack.product	upgrade code, architecture, scope, the version's first three parts
package code (reproducible builds)	rubrapack.package	hex SHA-256 of the package built with an all-zero package code

The ProductCode changes with the three-part version - which is what a major upgrade needs - and the ComponentIds do not.

9.2 Keys

Table keys (File, Component, Directory) are identifiers: `[A-Za-z_][A-Za-z0-9_]*`, at most 72 characters. rubrapack uses the author's IDs for files and folders as given and derives the rest:

```
key = prefix + "_" + first 20 lower-case hex digits of SHA-256(logical name)
      prefix C for components (logical name: the File key), D for intermediate folders
      (logical name: "<standard folder>/<part>/<part>..."), F for files from wildcards
```

9.3 Reproducible packages

A package is byte-for-byte reproducible when nothing depends on the clock, the machine or the order of hash tables: fixed CFB directory times (zero), fixed cabinet dates, string ids assigned in byte order of the strings, rows sorted by key, streams in a fixed order, no random GUIDs. The one identity that must differ between package files is the package code; derive it from the content (as above) when reproducibility matters, and use a random one otherwise.

10 Authenticode signatures

What a program has to write so that Windows accepts a signed PE file (.exe, .dll) or MSI package. Facts are tagged as in Package formats for implementers: **[spec]** for Microsoft's "Windows Authenticode Portable Executable Signature Format", the PE/COFF specification and RFC 5652 (CMS); **[observed]** for files signed by Windows' own signer (PowerShell Set-AuthenticodeSignature, which uses mssign32.dll) and checked with Get-AuthenticodeSignature / WinVerifyTrust on Windows 11.

10.1 Where the signature lives in a PE file

- The certificate table: data directory entry 4 (its entry is 8 bytes: file offset, size) of the optional header. The directory starts at optional header + 96 for PE32 (magic 0x10B) and + 112 for PE32+ (magic 0x20B); NumberOfRvaAndSizes must be at least 5. Unlike every other directory entry, its "address" is a **file offset**, not an RVA. [spec]
- At that offset, at the end of the file: WIN_CERTIFICATE { u32 dwLength, u16 wRevision = 0x0200, u16 wCertificateType = 0x0002 (PKCS_SIGNED_DATA), bCertificate[] }, where bCertificate is a DER CMS ContentInfo. dwLength includes the 8-byte header and is rounded up to 8; the extra bytes are zero. The directory entry's size equals dwLength. [spec] [observed]
- Before the table is appended, the file is padded with zeros to a multiple of 8. The padding is hashed (it is "data after the sections", below). [spec]
- The optional header's CheckSum (optional header + 64) is updated. Windows' signer adjusts the existing value rather than recomputing it: for a file whose checksum was not the PE algorithm's value, Windows keeps the difference, a fresh computation does not. CheckSum is outside the digest, so both verify. [observed]

10.2 The PE digest

In this order, with SHA-256: [spec]

1. The headers, from 0 to SizeOfHeaders, without CheckSum (4 bytes) and without the certificate table directory entry (8 bytes).
2. Every section with SizeOfRawData > 0, in increasing PointerToRawData order, SizeOfRawData bytes from PointerToRawData.
3. The data after them: from SizeOfHeaders + sum(SizeOfRawData) to the end of the file minus the certificate table.

Hashing the file linearly with the two holes gives the same result only when the sections follow each other without gaps; the steps above are the definition.

10.3 The CMS SignedData

Windows' signer writes, and accepts: [observed]

```
ContentInfo { signedData (1.2.840.113549.1.7.2), [0] SignedData {
  version 1,
  digestAlgorithms SET { sha256 + NULL },
  encapContentInfo { SPC_INDIRECT_DATA (1.3.6.1.4.1.311.2.1.4),
    [0] SpcIndirectDataContent }          -- the SEQUENCE itself, no OCTET STRING
  certificates [0] { the signer's certificate, then intermediates; no self-signed root },
  signerInfos SET { SignerInfo {
    version 1, IssuerAndSerialNumber of the signer,
```

```
digestAlgorithm sha256 + NULL,
signedAttrs [0] { SpcSpOpusInfo, contentType, SpcStatementType, messageDigest },
signatureAlgorithm rsaEncryption + NULL,
signature (RSA PKCS#1 v1.5) } } }
```

- `SpcIndirectDataContent ::= SEQUENCE { data, messageDigest DigestInfo }`. For a PE file data is `SEQUENCE { SPC_PE_IMAGE_DATA (1.3.6.1.4.1.311.2.1.15), SpcPeImageData }` and Windows writes `SpcPeImageData` as `30 09 03 01 00 A0 04 A2 02 80 00`: no flags, and a file link that is an empty Unicode string. `messageDigest` holds the PE digest. [observed]
- The **messageDigest attribute** is the hash of the `SpcIndirectDataContent` contents **without** its `SEQUENCE` tag and length - not of the whole element, and not of the PE file. [observed]
- The signed attributes are stored with tag `[0] (0xA0)` but the signature is computed over the same bytes with tag `SET (0x31)`, sorted as a DER SET OF. The four attributes Windows writes: `SpcSpOpusInfo (1.3.6.1.4.1.311.2.1.12) = SEQUENCE { [0] { [0] "" }, [1] { [0] "" } }`, `contentType = SPC_INDIRECT_DATA`, `SpcStatementType (1.3.6.1.4.1.311.2.1.11) = SEQUENCE { individual code signing (1.3.6.1.4.1.311.2.1.21) }`, `messageDigest`. No signing time. [observed]
- RSA PKCS#1 v1.5 is deterministic: a program that writes exactly this structure with the same key produces the same bytes as Windows. rubrapack does, except the `Checksum` difference above. [observed]

10.4 MSI packages

Microsoft does not publish how an MSI package is hashed. The rules below were worked out by signing packages with Windows' signer and comparing: rubrapack's signature and Ex streams came out byte-identical to Windows' for the same package and key, and packages whose directory entries were given non-zero state bits, times and CLSIDs told the fields apart. [observed]

- The signature is the stream `\005DigitalSignature` at the root of the compound file: the same CMS `ContentInfo` as for a PE file, with data = `SEQUENCE { SPC_SIPINFO (1.3.6.1.4.1.311.2.1.30), SpcSipInfo }`, where Windows writes `SpcSipInfo` as `SEQUENCE { 2, OCTET STRING <the MSI SIP GUID {000C10F1-0000-0000-C000-000000000046} in its little-endian byte order>, 0, 0, 0, 0, 0 }`.
- Windows also writes `\005MsiDigitalSignatureEx`: 32 bytes, the SHA-256 of a "prehash" of the compound file's directory: The root's own times are not part of it (Windows sets the root's modification time when it saves the signed file).
 - the root entry's CLSID (16 bytes) and state bits (4 bytes, little-endian);
 - then, for every stream at the root except the two signature streams, in the order of their names compared as UTF-16LE bytes: the name (UTF-16LE, no terminating NUL), the stream size as 8 bytes little-endian, and the entry's creation and modification times as stored (8 + 8 bytes). A stream's CLSID and state bits are not part of it.
- The digest in `SpcIndirectDataContent` is the hash of: the 32-byte `MsiDigitalSignatureEx` value (when that stream is written), then every stream's contents in the same name order (again without the two signature streams), then the root CLSID.
- Only streams at the root were observed; a package with storages (embedded transforms, sub-databases) is not covered here, and rubrapack refuses to sign one.
- A signature covers what is inside the .msi only: cabinets outside it (Media table Cabinet values that do not start with #) are not part of the digest.

10.5 Timestamps

A signature without a timestamp stops being valid when the signing certificate expires. With an RFC 3161 timestamp, Windows checks the certificate at the stamped time instead. What `mssign32!SignerTimeStampEx2` with `SIGNER_TIMESTAMP_RFC3161` writes: [observed]

- The request's message imprint is the hash (here SHA-256) of the SignerInfo's signature value: the OCTET STRING's contents, without its tag and length.
- The server's TimeStampToken (a CMS SignedData over a TSTInfo, RFC 3161) goes into the SignerInfo as its unsigned attributes, after the signature: [1] { SEQUENCE { 1.3.6.1.4.1.311.3.3.1, SET { TimeStampToken } } }.
- Nothing else in the signature changes: the signed attributes, the signature and the outer certificates are the same bytes as before; the server's certificates travel inside the token. For an MSI package the \005DigitalSignature stream grows accordingly (from the mini stream to regular sectors, for a token of a few kilobytes); \005MsiDigitalSignatureEx and the digest do not change, since the signature streams are not part of them.
- rubrapack writes exactly this; with the same key and token its PE file is byte-identical to Windows', and so is the MSI signature stream.

Set-AuthenticodeSignature -TimestampServer writes an older form instead: a PKCS#9 counterSignature attribute (1.2.840.113549.1.9.6) and the server's certificates added to the outer certificates. Windows accepts both. [observed]

10.6 ECDSA

An ECDSA P-256 signer works for PE files, MSI packages and MSIX packages alike (Windows 11 26100 calls all three Valid with the root trusted). Windows' signer writes the SignerInfo's signatureAlgorithm as id-ecPublicKey (1.2.840.10045.2.1) with NULL parameters - not ecdsa-with-SHA256 - and the signature value as the DER SEQUENCE { INTEGER r, INTEGER s }. rubrapack writes the same, with deterministic nonces (RFC 6979), and reads either OID. [observed]

10.7 What Windows reports

Get-AuthenticodeSignature distinguishes the cases a signer needs (and names the time-stamping certificate in TimeStamperCertificate when there is a timestamp): Valid (digest, signature and chain to a trusted root), UnknownError with "the certificate chain ... not trusted" (digest and signature are right, the root is not trusted on this machine), HashMismatch (the file changed after signing), NotSigned. So a signature can be checked for correctness before any root is trusted. [observed]

11 Checking your output against Windows

Microsoft does not publish the MSI table encoding, so the reference is Windows itself. These checks need only a Windows machine and the Windows Installer API (`msi.dll`); no SDK tools.

11.1 The database opens and decodes

1. `MsiOpenDatabase` your file read-only - the compound file and string pool are acceptable.
2. `MsiDatabaseExport` every table (and `_ForceCodepage`, `_SummaryInformation`) to IDT files.
3. Compare with what your own reader exports, or with the IDT of a reference database made through `msi.dll` (`MsiOpenDatabase` with create mode, `MsiDatabaseImport` of a `_ForceCodepage.idt` containing 65001, SQL CREATE TABLE/INSERT via views). Byte-identical IDT means your encoding matches.

11.2 The package installs

Drive the installer from a program rather than `msiexec`, so every step is synchronous and returns an error code:

Step	API	Expect
silent UI	<code>MsiSetInternalUI(INSTALLUILEVEL_NONE)</code>	
verbose log	<code>MsiEnableLog</code> (all modes)	read it when anything fails
install	<code>MsiInstallProduct(path, "")</code>	0
names	FindFirstFile on each installed path, compare the entry's own UTF-16 name exactly	equal
content	<code>MsiGetFileHash</code> of each installed file vs your <code>MsiFileHash</code> row	equal
registration	<code>MsiGetProductInfo(ProductCode, InstalledProductName)</code>	your Product-Name
repair	delete one installed file, <code>MsiReinstallProduct(ProductCode, ...)</code>	file back, same name
upgrade	install version N+1 over N	old Product-Code gone, new one installed
downgrade	install version N again	re-fused (1603, the

Step	API	Ex- pect
		log names your re- fus- ing ac- tion)
features	MsiQueryFeatureState; MsiConfigureFeature(..., INSTALLSTATE_LOCAL)	lev- els above INSTALLLEVEL ab- sent un- til turned on
rollback	copy of version N+1 with a deferred custom action that fails after InstallFiles (type 34 + 1024, "[SystemFolder]cmd.exe" /c exit 1) and a new package code, installed over N	1603 (log: er- ror 1722); N still reg- is- tered, its files un- changed
uninstall	MsiConfigureProduct(ProductCode, ..., INSTALLSTATE_ABSENT)	0; fold- ers, keys and reg- is- tra- tion gone

Per-machine installs need an elevated process. Keep test products on their own UpgradeCodes and remove them in the same run.

11.3 Checks before writing

msi.dll accepts many broken databases and only fails at install time, if at all (it does not even enforce column widths). A writer should check its own tables first. rubrapack's build refuses to write a package that breaks any of these (diagnostics RP2001-RP2015):

- every cell has the column's kind; no null in a non-nullable column; strings no longer than the column width, counted in UTF-16 units (a non-BMP character counts two), and valid UTF-8; 16-bit integers within -32767..32767 and 32-bit ones not -2147483648 (those values mean null);

- no duplicate primary keys; references (Component.Directory_, File.Component_, FeatureComponents, CreateFolder, MsiFileHash.File_, Directory_Parent, Feature_Parent) point at existing rows; every sequence action is a standard action, a CustomAction or a Dialog;
- ProductCode, ProductName, ProductVersion, Manufacturer, ProductLanguage are present; GUIDs are upper case in braces, component GUIDs are unique, ProductCode differs from UpgradeCode;
- each File.Sequence is unique and covered by a Media.LastSequence;
- standard actions keep their order (costing before InstallValidate, file actions between InstallInitialize and InstallFinalize);
- the 64-bit component attribute (256) matches the summary Template platform (x64/Arm64 vs Intel);
- a file key path is a file of the same component;
- each Upgrade.ActionProperty is upper case (public) and listed in SecureCustomProperties - otherwise a per-machine install does not pass it to the server side.

11.4 Things that look fine but are not

- An msi.dll-made database is not a complete specification: msi.dll stores 65001 summary strings correctly and still cannot read them back (Summary information).
- MsiDatabaseExport prints summary dates in local time; compare dates in UTC.
- A successful MsiOpenDatabase says nothing about row order or reference counts - only installation does. Test with an install, not just an open.

12 MSIX packages

What a program has to write so that Windows reads, installs and runs an MSIX package. Facts are tagged as in Package formats for implementers: **[spec]** for Microsoft Learn (package manifest and block map schemas) and ECMA-376 Part 2 (Open Packaging Conventions); **[observed]** for packages written by Windows' own packaging API (IAppxFactory/IAppxPackageWriter in AppxPackaging.dll, part of Windows) and for rubrapack's packages read back through IAppxPackageReader and installed with Add-AppxPackage on Windows 11. rubrapack writes what is described here.

12.1 The ZIP archive

- The payload files first, then AppxManifest.xml, AppxBlockMap.xml and [Content_Types].xml, in that order. [observed]
- Every entry is ZIP64, whatever its size: the local header has version needed 4.5, flag 0x0008 (data descriptor), CRC and sizes 0 and no extra field; the data is followed by a ZIP64 data descriptor (PK\7\8, CRC-32, compressed and plain size as 8 bytes each). The central directory entry has made-by and needed 4.5 (MS-DOS), sizes and offset 0xFFFFFFFF and a ZIP64 extra field (0x0001, 24 bytes: plain size, compressed size, local header offset). The archive ends with a ZIP64 end record (size 44), its locator, and an end record whose counts and offsets are all 0xFFFF / 0xFFFFFFFF. [observed]
- Methods: stored (0) and deflate (8). AppxManifest.xml, AppxBlockMap.xml and [Content_Types].xml are deflated even when the payload is stored. [observed]
- Entry names are OPC part names: / between folders and every byte outside A-Z a-z 0-9 - . _ ~ percent-encoded, UTF-8 bytes included - data\<U+C790> %%(1).txt (a Hangul syllable, a space, %, # and parentheses) is stored as data/%EC%9E%90%20%25%23%28%29.txt - and the UTF-8 name flag is not set. [Content_Types].xml keeps its brackets. [observed]
- The dates in the headers are not read; Windows writes the time of writing, rubrapack 1980-01-01 00:00 so that a package does not change from one build to the next. [observed]

12.2 The block map (AppxBlockMap.xml)

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<BlockMap xmlns="http://schemas.microsoft.com/appx/2010/blockmap"
  xmlns:b4="http://schemas.microsoft.com/appx/2021/blockmap" IgnorableNamespaces="b4"
  HashMethod="http://www.w3.org/2001/04/xmlesc#sha256">
  <File Name="data\text.txt" Size="218890" LfhSize="43">
    <Block Hash="(base64 SHA-256 of 65536 plain bytes)" Size="(compressed bytes of this block)" />
    ...
    <b4:FileHash Hash="(base64 SHA-256 of the whole file)" />
  </File>
  ...
</BlockMap>
```

- One File per payload file and one for AppxManifest.xml; the block map and [Content_Types].xml are not listed. Name is the path as written, with \, not percent-encoded; Size is the plain size; LfhSize the local header's size (30 + the ZIP name's length). An empty file has no Block. [spec] [observed]
- One Block per 65536 bytes of plain data; Hash is the base64 SHA-256 of that plain block. [spec]
- A deflated file is one independent raw deflate part per block: each part decodes with a fresh decoder (nothing refers back into an earlier block) and ends with an empty stored block (00 00

FF FF), and after the last part comes an empty final block (03 00). The block's Size counts the bytes of its part, so the compressed size of the file is the sum of the Sizes plus 2 (an empty file: 2 bytes, no block). Stored files have no Size on their blocks. Incompressible data is deflated as well (into stored blocks). [observed]

- b4:FileHash appears only for files of more than one block. [observed]
- Windows' reader checks every block's hash as the file is read, and refuses a package whose file differs from its block map, both when reading and when installing. [observed]

12.3 [Content_Types].xml

One line: a Default per file extension in order of first use (lower case), xml as application/vnd.ms-appx.manifest+xml, and Override PartName="/AppxBlockMap.xml" as application/vnd.ms-appx.blockmap+xml. rubrapack adds an Override for each file without an extension, and one for /AppxManifest.xml when a payload .xml file took the xml default. [observed]

12.4 The manifest (AppxManifest.xml)

The smallest desktop application that Windows installs and starts (namespaces foundation/windows10, uap/windows10, restrictedcapabilities): [spec] [observed]

- Identity: Name (3-50 characters of A-Z a-z 0-9 . -), Publisher (the signing certificate's subject), Version (four parts, each at most 65535), ProcessorArchitecture (x64, arm64, x86).
- Properties: DisplayName, PublisherDisplayName, Logo (a PNG in the package).
- Dependencies/TargetDeviceFamily Name="Windows.Desktop" with MinVersion and MaxVersionTested.
- Resources/Resource Language.
- Application Id Executable EntryPoint="Windows.FullTrustApplication" with uap:VisualElements (DisplayName, Description, BackgroundColor, Square150x150Logo, Square44x44Logo), and the restricted capability runFullTrust.
- Paths in the manifest use \ and name files of the package.

12.5 The virtual registry (Registry.dat, User.dat)

Registry hives at the package root (the REGF format: Registry hive files (REGF)). Measured with a packaged app on Windows 11 (26100): [observed]

- Registry.dat: its REGISTRY\MACHINE\SOFTWARE key stands for HKLM\Software (the hive's root itself does not); REGISTRY\MACHINE\SOFTWARE\WOW6432Node\... is what the app sees in the 32-bit view. Microsoft's description ("registry.dat serves as the logical equivalent of HKLM\Software") is about what the app sees, not about the hive's layout.
- User.dat: its root stands for HKCU (Software\... beneath it is HKCU\Software\...).
- The app reads the package's keys merged into the real registry; nothing is written to the machine's registry, and nothing is left after removal.
- Windows' packaging tools write these hives with the Offline Registry Library (its mark "OfRg" is in the base block).

12.6 The virtual file system (VFS\...)

Files under VFS\<folder> appear to the app at the real location; the real folder does not change. Measured: ProgramFilesX64 (%ProgramFiles%), SystemX64 (System32), Common AppData (%ProgramData%) - and none for AppData or Local AppData, as Microsoft Learn says. The other names rubrapack uses (ProgramFilesX86, ProgramFilesCommonX64/X86, SystemX86, Windows) are those Microsoft Learn lists. [spec] [observed]

12.7 Extensions

What rubrapack writes into an application's <Extensions> (after uap:VisualElements), and only this: a source feature with no row here is an error, and one whose Windows build is above the package's MinVersion asks for min-version to be raised. [spec] Microsoft Learn, "Integrate your desktop app with Windows using packaging extensions" and the element pages. The last column is what was checked by installing a package on Windows 11 (26100). [observed]

Source	Element (category)	Namespace	Min build	Capability	Checked on Windows 11
[assoc]	uap:Extension windows.fileTypeAssociation > uap3:FileTypeAssociation (Name, Parameters) > uap:DisplayName, uap:SupportedFileTypes > uap:FileType	uap, uap3	14393	runFullTrust	opening a .rpx/.rpy file starts the program with the file
[protocol]	uap3:Extension windows.protocol > uap3:Protocol (Name, Parameters)	uap3	14393	runFullTrust	starting a scheme: URI starts the program with it
[msix-extension] alias	uap3:Extension windows.appExecutionAlias (Executable, EntryPoint) > uap3:AppExecutionAlias > desktop:ExecutionAlias (Alias)	uap3, desktop	14393	runFullTrust	the alias appears in %LOCALAPPDATA%\Microsoft\Windows and starts the program
[msix-extension] startup task	desktop:Extension windows.startupTask (Executable, EntryPoint) > desktop:StartupTask (TaskId, Enabled, DisplayName)	desktop	14393	runFullTrust	registered after the first start
[shortcut] Desktop	desktop7:Extension windows.shortcut > desktop7:Shortcut (File	desktop7	19645	runFullTrust	the short-

Source	Element (category)	Namespace	Min build	Capability	Checked on Windows 11
	\$(Desktop)\<name>.lnk, Icon, Arguments, Description)				cut is on the user's desktop and starts the program
[shortcut] Programs, StartMenu	none: the application's own Start entry	-	-	-	the Start menu lists the application
[font]	uap4:Extension windows.sharedFonts > uap4:SharedFonts > uap4:Font (File Fonts\<name>), in the first application	uap4	15063	-	other programs see the font while the package is installed, and not after

- The namespaces are declared on Package, and made ignorable, only when used, so a package without extensions keeps the manifest described above.
- Parameters, Arguments: literal text (MSI's [...] is refused); Windows puts the file or URI where %1 is.
- FileTypeAssociation Name: the prog-id in lower case; [assoc] tables that share a prog-id become one association with several FileTypes.
- Everything goes into the application whose executable the source names as target; a target that is not an application's executable is an error.

12.8 Bundles (.msixbundle)

A ZIP archive laid out like a package (ZIP64 entries with data descriptors), as Windows' bundle writer (IAppxBundleWriter) makes it: [observed]

- The packages first, stored (method 0) under their file names, in the order they were added; then AppxMetadata/AppxBundleManifest.xml, AppxBlockMap.xml and [Content_Types].xml, deflated.
- The block map lists the bundle manifest only (AppxMetadata\AppxBundleManifest.xml); the packages carry their own block maps.
- [Content_Types].xml: Default msix = application/vnd.ms-appx, Default xml = application/vnd.ms-appx.bundlemanifest+xml, and an Override for /AppxBlockMap.xml.
- The bundle manifest, CRLF line ends, tab indents, no line end after the last tag:

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<Bundle xmlns="http://schemas.microsoft.com/appx/2013/bundle" SchemaVersion="5.0" xmlns:b4="http://schemas.
microsoft.com/appx/2018/bundle" xmlns:b5="http://schemas.microsoft.com/appx/2019/bundle" IgnorableNamespaces="b4
b5">
  <Identity Name="Example.App" Publisher="CN=Example" Version="1.0.0.0"/>
  <Packages>
    <Package Type="application" Version="1.0.0.0" Architecture="x64" FileName="Example.App_1.0.0.0_x64.msix"
Offset="66" Size="61340">
      <Resources>
        <Resource Language="en-US"/>
      </Resources>
      <b4:Dependencies>
        <b4:TargetDeviceFamily Name="Windows.Desktop" MinVersion="10.0.17763.0" MaxVersionTested="10.0.26100.0"/>
      </b4:Dependencies>
    </Package>
  </Packages>
</Bundle>
```

- Offset is where the package's bytes start in the bundle (after its local header), Size their length. Resources and Dependencies repeat the package manifest's Resource and TargetDeviceFamily elements.
- The bundle's Version is the writer's argument (a 64-bit number, 16 bits per part); rubrapack gives the packages' version. Every package must have the bundle's Name and Publisher, one version, and an architecture of its own.
- rubrapack's bundle of the same packages has the same entries at the same offsets and the same manifest, block map and content types, byte for byte; only the ZIP dates differ (1980 in rubrapack's). Windows installs from it the package for its own architecture: x64 on an x64 machine even when x86 and arm64 are there, x86 from a bundle of x86 alone. [observed]

12.9 Signatures (AppxSignature.p7x)

Worked out against Windows' signer (mssign32!SignerSignEx2 with APPX_SIP_CLIENT_DATA; the PowerShell cmdlet cannot sign a package) and checked by installing rubrapack's signed packages. [observed]

- Publisher in the manifest must be the signing certificate's subject written the way Windows displays it: the RDNs from last to first, A=value joined by , - a certificate made with /CN=Example/0=Example Ltd needs 0=Example Ltd, CN=Example. Otherwise signing fails with 0x8007000B.
- Signing rewrites the archive the way the signer does: the payload's local records, the manifest and the block map stay as they were; [Content_Types].xml gets <Override PartName="/AppxSignature.p7x" ContentType="application/vnd.ms-appx.signature"/>; the signature is added last, deflated, with its sizes in the local header (version needed 2.0, no data descriptor); the central directory is written the ZIP32 way (no ZIP64 extra fields) where sizes and offsets allow, and the end record's disk numbers are 0.
- AppxSignature.p7x is PKCX followed by a CMS SignedData as in Authenticode signatures, with these differences: data is SEQUENCE { SpcSipInfo (1.3.6.1.4.1.311.2.1.30), SEQUENCE { INTEGER 0x01010000, OCTET STRING <SIP GUID>, INTEGER 0, INTEGER 0, INTEGER 0, INTEGER 0, INTEGER 0 } } with the package SIP GUID bytes 4B DF C5 0A 07 CE E2 4D B7 6E 23 C8 39 A0 9F D1 or the bundle SIP GUID bytes B3 58 5F 0F DE AA 9A 4B A4 34 95 74 2D 92 EC EB; the signed attributes are contentType and messageDigest only.

- The DigestInfo's digest is not one hash but APPX followed by records of a 4-byte tag and a SHA-256:
 - AXPC: the archive from its start to the signature entry's local header;
 - AXCD: the central directory without the signature entry, then the ZIP64 end record, its locator and the end record, all as if the signature entry did not exist (the central directory starting where the signature's local header is). Windows reads the signature entry's place from its ZIP32 fields: a signature entry described the ZIP64 way (0xFFFFFFFF there) is a HashMismatch - so is the package whose central directory is rewritten that way after signing;
 - AXCT: [Content_Types].xml (the plain bytes); AXBM: AppxBLOCKMap.xml;
 - AXCI: AppxMetadata/CodeIntegrity.cat, only when the package has one.
- Windows' signer also adds AppxMetadata/CodeIntegrity.cat - a catalog of the package's program files, signed by the same key - when the package holds any. It is optional: a package signed without it installs and runs. rubrapack does not write one; it checks AXCI when it is there.
- A bundle: every package inside is signed first (each with its own AppxSignature.p7x), then the bundle is written around them and signed with the bundle SIP GUID, without AXCI.
- An unsigned package that needs -AllowUnsigned and the publisher OID (below) is not signed: signing refuses a publisher with that OID.

12.10 Installing an unsigned package

- Publisher must end in 0ID.2.25.311729368913984317654407730594956997722=1; then Add-AppxPackage - AllowUnsigned installs it on Windows 11. [spec]
- A package with an executable needs an elevated process (otherwise 0x80073D2B: an unsigned package cannot hold an executable activation). Developer mode is not needed. [observed]
- Add-AppxPackage from a network logon (an SSH session) fails at "PLM initialization" with 0x80070005; it works in an interactive session. [observed]
- A package with file types leaves, after removal, an empty OpenWithProgids key under HKCU\Software\Classes\.<ext> - Windows' own doing, not the package's. [observed]

13 Registry hive files (REGF)

The file format of Registry.dat and User.dat in an MSIX package. Microsoft does not publish it; every fact here is **[observed]**: hives written by Windows' Offline Registry Library (offreg.dll, 10.0.26100, the writer Windows' packaging tools use - its mark is in the base block) for chosen key/value sets, and rubrapack's hives for the same sets read back on Windows with OROpenHive and RegLoadAppKey into exactly the keys and values Windows enumerates in its own. Only what a freshly written hive needs is described: no transaction logs, no volatile keys, no free-cell reuse.

13.1 Layout

- A 4096-byte base block, then hive bins. Offsets in cells ("cell offsets") count from the end of the base block (file offset - 4096); "none" is 0xFFFFFFFF.
- A bin: hbin, u32 its own cell offset, u32 its size (4096 or a multiple), 8 bytes zero, u64 time (0), u32 spare (0); 32 bytes in all. Cells follow; a cell that does not fit in the current bin starts a new bin sized to hold it; the rest of a bin is one free cell.
- A cell: i32 size (negative while in use, a multiple of 8, the size field included), then its content. A cell never crosses its bin's end.

13.2 The base block

Offset	Field	Value
0	signature	regf
4, 8	sequence numbers	1, 1 (unequal = not closed cleanly; readers refuse or replay a log)
12	u64 time	0 is accepted
20, 24	version	1, 5
28, 32	type, format	0, 1
36	root key cell offset	
40	size of all bins	
44	clustering	1
0xB0	offreg's mark	0fRg, then u32 1
508	checksum	XOR of the 127 dwords before it; 0 is written as 1, 0xFFFFFFFF as 0xFFFFFFFFE

Everything else is zero.

13.3 Keys (nk)

nk, u16 flags, u64 time, u32 access bits (0), u32 parent (none for the root), u32 subkey count, u32 volatile subkey count (0), u32 subkey list, u32 volatile list (none), u32 value count, u32 value list, u32 security cell, u32 class (none), u32 longest subkey name, u32 longest class (0), u32 longest value name, u32 largest value data, u32 work var (0), u16 name length, u16 class length (0), then the name.

- Flags: 0x20 when the name is stored as Latin-1 ("compressed": every UTF-16 unit below 256), else the name is UTF-16LE. The root key of an offreg hive is named ROOT and has flags 0x20 only.
- The longest names are counted in UTF-16 bytes, whatever the stored form.
- Names compare without case: each UTF-16 unit mapped by Unicode simple upper case.

13.4 Subkey lists (lh, ri)

- lh, u16 count, then per subkey: u32 key cell, u32 hash. Sorted by upper-cased name.

- Hash: $h = 0$; for each UTF-16 unit of the name, $h = h * 37 + \text{upper}(\text{unit})$ (32-bit wrap).
- More than 507 subkeys: an ri (u16 count, u32 per lh list) of lh lists of up to 507.

13.5 Values (vk) and value lists

- A value list is a plain cell of u32 value cell offsets, in the order the values were set.
- vk , u16 name length, u32 data size, u32 data offset, u32 type, u16 flags, u16 spare, then the name. Flag 1 = Latin-1 name; the unnamed default value has an empty name and flags 0.
- Data of up to 4 bytes (an empty value too) is kept in the data offset field, and the size's top bit is set.
- Up to 16344 bytes: one data cell. From 16345 bytes: a db cell (db , u16 segment count, u32 segment list), a list cell of u32 segment cells, and segments of 16344 bytes each - every segment cell allocated at full size, the last one too: Windows stops reading a value whose last segment cell is shorter.

13.6 The security cell (sk)

One sk cell shared by every key: sk , u16 0, u32 next and u32 previous (both itself), u32 reference count (the number of keys), u32 descriptor length, then a self-relative security descriptor. offreg's: owner and group Administrators; SYSTEM and Administrators full access, Everyone and RESTRICTED read, all container-inherit.

13.7 Reproducible hives

With every time field 0 and cells laid out depth first (a key; after the root key the security cell; the key's subkey lists, its value list, each value followed by its data; then its subkeys in sorted order), the same keys and values give the same bytes on any host. Windows reads such a hive without complaint.