

Splitter beta

A lap timer for VelociDrone that watches you fly. Gate-by-gate splits against your personal best while you race, every run saved, and afterwards a clear picture of which parts of the track cost you time and where you crash. Windows quick start, about 10 minutes.

1. Start Splitter


1. Make a folder for it, for example `Documents\Splitter`, and put `splitter-windows-x64.exe` inside. Splitter keeps all your runs in a `splitter-data` folder that appears next to the exe, so keep the two together.
2. Double-click the exe. The first launch takes a few seconds while it unpacks.
3. If Windows shows “Windows protected your PC”, click More info, then Run anyway. The beta is not code-signed yet, which is all that warning means.
4. Because it is not signed, Microsoft Defender may also flag or remove the exe when you copy or download it. If it does, open Windows Security → Virus & threat protection → Protection history, find the Splitter entry, choose Actions → Allow, then copy the exe into the folder again. It should stay put after that.
5. If the Windows Firewall asks, click Allow access. That only matters if you want to watch the timer on a phone or tablet (section 6); Cancel is fine otherwise.

A Splitter window opens on the Live page. Closing that window stops the timer.

2. Turn on the game's data feed (once)

VelociDrone can send race and telemetry data to tools like Splitter, but it is off by default.

1. In VelociDrone open Options → Main Settings.
2. Set Websocket Communication to Yes.
3. Set Websocket IMU Data to Yes as well. Both rows are at the bottom of the list. This adds speed, position and crash data. It only works when your quad uses the Betaflight flight controller model.
4. Restart VelociDrone. The game reads these settings when it starts, so the change does nothing until you do.




1 Options → Main Settings. Scroll to the bottom of the list. 2 Websocket Communication → Yes. 3 Websocket IMU Data → Yes.

3. Check that Splitter can see the game

The game only listens on your PC's network address, never on "localhost", so Splitter needs that address even though both run on the same machine. Splitter fills it in for you on first launch.

1. In Splitter open the Settings page (top menu). Game PC address should already show an address like `192.168.1.23`. Leave Port at `60003`.
2. Put your VelociDrone pilot name in Your player name. It is only used to pick you out when other pilots are in a room, but set it now so it is there.
3. Click Save.
4. If the header never shows Game connected and your PC has more than one network adapter (Wi-Fi and Ethernet, a VPN), tap one of the other addresses listed under the field and save again.




The Settings page. Only the top three fields matter for the beta.

With VelociDrone running and the feed turned on, the top-right corner of every Splitter page shows Game connected with a green dot. If it says offline or reconnecting, tap it: Splitter shows what to check. The Live page also shows a short “Getting started” checklist until everything is in place.

Two dots in the corner. Splitter is the page's own link to the timer, Game is the timer's link to VelociDrone. Both should be green while you fly.

4. Fly

1. On the Live page tap Track... and search for the track you are about to fly, then pick it. The game never says which track you are on in single player, so this is how Splitter knows. It remembers your pick until you change it.
2. Start a race in the game as normal. Splitter shows the countdown, then the race clock.
3. The big clock is coloured by how you are doing against your personal best on that track: **green** ahead, **yellow** close, **red** behind. Each gate you pass adds a line to the gate log with the split.
4. When you finish, the result card shows your laps and whether it was a new personal best.




The Live page between runs: the track picked, the last result below the clock, and the gate log on the right.

Timer stuck? If you quit the game mid-run, Splitter aborts the run by itself after about ten seconds. You can also tap the red Abort button next to the clock at any time, which ends the run in Splitter and in the game.

Personal bests need a track. A run flown without picking a track is still saved, but it cannot become a personal best, and the clock has nothing to compare against. You can fix the track later on the Races page.

5. Look at your flying afterwards

Page	What it shows
Races	Every run. Open one for the lap times, a top-down flight path coloured by speed, a speed graph, and a <i>Sections</i> table that compares each part of the track with your personal best, lap by lap. Crashes are marked with a red X.
Tracks	One entry per track and quad. Your personal best, how your times have moved run over run, and the <i>Sections</i> table: for each part of the track, how much time is “on the table” compared with your best-ever lap through it, how consistent you are, your slowest speed, how often you crash there, and a verdict of <i>line</i> (the line has time in it), <i>mistakes</i> (you blow it up sometimes) or <i>solid</i> .
Settings	The game address, your name, and display options such as the time format.



The Tracks page for one track. Sections are suggested automatically from your flying; Edit sections lets you split, merge and name them.

6. Optional: watch on a phone or tablet

While the Splitter window is open, any phone or tablet on the same Wi-Fi can open `http://YOUR-PC-ADDRESS:8100/` in its browser, using the address from step 3, for example `http://192.168.1.23:8100/`. The Live page has a fullscreen button that hides everything but the clock. This needs the firewall permission from step 1.

7. When something goes wrong

This is a beta, so please tell me about anything odd. The most useful report has three things:

- What you did and what you expected, in a sentence or two.
- A screenshot of the Splitter page, if it looks wrong.
- The log file: `splitter-data\splitter-desktop.log`, next to the exe.

Known limits in this beta

- The exe is not code-signed, so Windows warns on first run and Defender may flag it (section 1).
- In single player you must pick the track yourself (step 4). Hosted multiplayer rooms report it automatically.
- Something not obvious? Tap the thing that looks wrong: the header dots, the ? next to Track..., and the “no id” tag all open a short help note.
- Speed, flight path and crash detection need Websocket IMU Data on and the Betaflight flight controller model.
- Closing the Splitter window stops the timer. Runs already saved are kept in `splitter-data`.