

_rzilient

VPN Portal Customer Guide

Complete guide for administrators and team members — setup, access, and management.

ADMIN GUIDE

USER GUIDE

WireGuard VPN

May 2026 · v1.0 · rzilient.tech

// contents

Part I — For Administrators

1. What is the VPN Portal?
2. Accessing the Admin Panel
3. Managing Peers
4. Adding Peers Manually
5. Monitoring Traffic
6. Updating the Portal

Part II — For Team Members

7. Getting Access
8. Logging In — Google SSO
9. Logging In — Magic Link
10. Generating Your Credentials
11. Installing WireGuard
12. Connecting to the VPN
13. Troubleshooting

1. What is the VPN Portal?

The rzilient VPN Portal is a self-serve WireGuard VPN credential system. Your team members log in with their work email and generate their own WireGuard credentials without any manual intervention from IT.

Feature	Description
Google SSO	Team members log in with their @yourdomain.com Google account
Magic Link	Passwordless email login for non-Google accounts
Self-serve	Each user generates their own WireGuard key pair
Admin panel	Full peer management with live traffic stats
Auto-update	Portal updates itself from the admin panel — no SSH needed

2. Accessing the Admin Panel

The admin panel is protected by a session-based login. Your admin token acts as a password.

1 Navigate to the login page

Open <https://vpn.yourdomain.rzilient.tech/admin/login> in your browser

2 Enter your admin token

Type your ADMIN_TOKEN in the password field and click "access admin panel"

3 Session stored

A secure session cookie is set — valid for 24 hours. No token in URL.

4 Logout when done

Click "logout" in the top nav to clear your session

3. Managing Peers

The peers table shows all team members who have generated VPN credentials. Each row shows their email, VPN IP, status, live traffic stats and last seen time.

Action	Button	Effect
Block	■ block	Removes peer from WireGuard — they cannot connect but credentials are kept
Unblock	↑ unblock	Re-adds peer to WireGuard — they can connect again immediately
Revoke	✕ revoke	Permanently deletes peer and credentials — they must generate new ones
Copy config	■ config	Copies the WireGuard .conf file to clipboard — useful for manual setup
Export CSV	↓ export csv	Downloads all peers with traffic stats as a CSV file

4. Adding Peers Manually

You can add peers directly from the admin panel without requiring the user to log in. This is useful for devices or service accounts.

1 Scroll to "// add peer"

The add peer form is above the peers table on the admin panel

2 Enter email and name

Type the user's work email and full name, then click "+ add peer"

3 Copy their config

Find the new peer in the table, click "■ config" and share the .conf file securely

The user can also log in via the portal and use their credentials directly — manually added peers are fully supported.

5. Monitoring Traffic

The admin panel shows live WireGuard traffic stats, refreshed every 30 seconds.

Indicator	Meaning
● Green dot	Peer is online — last handshake less than 3 minutes ago
● Grey dot	Peer is offline — no recent handshake
↓ RX	Data received by this peer (download)
↑ TX	Data sent by this peer (upload)
Last seen	Time since last WireGuard handshake (e.g. "2m ago")
Total RX / TX	Combined traffic across all peers — shown in the header stats cards

6. Updating the Portal

When a new version of the VPN portal is available, a badge in the top navigation will show "↑ update available". You can update the portal with one click — no SSH or technical knowledge required.

1 Check the version badge

The badge in the top nav shows your current version SHA. When an update is available it turns lime green with an "update now" button.

2 Click "update now"

A confirmation dialog appears. Confirm to start the update.

3 Wait ~30 seconds

The portal pulls the new image and restarts. The page will briefly become unavailable.

4 Refresh and verify

After 30 seconds, refresh the page. The badge will show the new version SHA.

All peer data and WireGuard credentials are preserved during updates — they are stored outside the container and not affected by restarts.

7. Getting Access

To connect to your company VPN you need two things: access to the portal and WireGuard installed on your device.

Requirement	Details
Work email	A @yourdomain.com email address registered by your admin
Portal URL	Provided by your IT admin — e.g. https://vpn-company.rzilent.tech
WireGuard app	Free on all platforms — see Section 11 for installation links

8. Logging In — Google SSO

If your company uses Google Workspace, you can log in instantly with your Google account.

1 Open the portal

Navigate to your VPN portal URL in your browser

2 Click "continue with Google"

You will be redirected to the Google login page

3 Select your work account

Choose your @yourdomain.com account — personal accounts will be rejected

4 You are logged in

You will be redirected to the portal home page

9. Logging In — Magic Link

If you do not use Google Workspace, or prefer passwordless login, you can use a magic link sent to your work email.

1 Open the portal

Navigate to your VPN portal URL — you will land on the login page automatically

2 Enter your work email

Type your work email address and click "send magic link"

3 Check your email

You will receive an email with a login link — valid for 1 hour

4 Click the link

Click "Log in to VPN portal" in the email — you will be logged in automatically

The magic link is single-use and expires after 1 hour. If it expires, simply request a new one from the portal.

10. Generating Your Credentials

Once logged in, you will see the portal home page. If you have not generated credentials yet, you will see a "Generate credentials" button.

1 Click "Generate credentials"

The portal generates a WireGuard key pair and assigns you a VPN IP address

2 Download your config

Click "Download config" to save your rzilient-vpn.conf file

3 Scan the QR code (mobile)

On mobile, tap "Show QR code" and scan it directly in the WireGuard app

4 Keep your config safe

Your .conf file contains your private key — do not share it

You only need to generate credentials once. Your VPN IP address is permanent and will not change. If you lose your config, contact your admin to revoke and regenerate.

11. Installing WireGuard

WireGuard is free and available on all major platforms.

Platform	Download	Install method
macOS	Mac App Store	Search "WireGuard" and install
Windows	wireguard.com/install	Download and run the installer
iOS	App Store	Search "WireGuard" and install
Android	Google Play Store	Search "WireGuard" and install
Linux (Ubuntu)	apt package	<code>sudo apt install wireguard</code>
Linux (Arch)	pacman	<code>sudo pacman -S wireguard-tools</code>

12. Connecting to the VPN

Desktop (macOS / Windows / Linux)

- 1 Open WireGuard**
Launch the WireGuard application
- 2 Import your config**
Click "Import tunnel(s) from file" and select your rzilient-vpn.conf file
- 3 Activate the tunnel**
Click "Activate" — the tunnel status will show "Active"
- 4 You are connected**
All traffic is now routed through the VPN

Mobile (iOS / Android)

1

Open WireGuard

Launch the WireGuard app on your phone

2

Tap the + button

Select "Create from QR code"

3

Scan the QR code

Open the portal on your phone or computer and scan the QR code shown

4

Activate the tunnel

Toggle the tunnel on — allow VPN permission when prompted

13. Troubleshooting

Problem	Likely cause	Solution
Cannot log in with Google	Wrong account or domain not authorized	Make sure you are using your work email. Contact your admin if you are not.
Magic link email not received	Spam filter or wrong email	Check spam/junk folder. Make sure you typed your email correctly.
Magic link says "expired"	Link older than 1 hour	Request a new magic link from the portal login page.
WireGuard shows "Active" but no Internet	no Internetting issue	Try toggling the tunnel off and on. Ensure AllowedIPs = 0.0.0.0/0 in your config.
"No IPs available"	Subnet full	Contact your admin — the VPN subnet needs to be expanded.
Config lost	File deleted	Contact your admin. They can revoke your credentials and you can generate a new one.
Tunnel connects but disconnects	network instability	PersistentKeepalive = 25 is set — try switching networks (WiFi / mobile).

Need help?

Contact your rzilient account manager or email support@rzilient.tech. Include your portal URL and the error you are seeing.