Dockerfile


План видео


▼ Познакомиться с Dockerfile

Разобрать синтаксис основных инструкций

Типовая структура

Docker image





Простейший Dockerfile

FROM ubuntu:latest

RUN apt update && apt install -y iputils-ping

COPY docker-entrypoint.sh /docker-entrypoint.sh

ENTRYPOINT ["/docker-entrypoint.sh"]

Инструкция FROM

FROM ubuntu:18.04

FROM [--platform=<platform>] <image>[AS <name>]

FROM [--platform=<platform>] <image >[:<tag>][AS <name>]

FROM [--platform=<platform>] <image >[@<digest>][AS <name>]

ARG CODE_VERSION=latest

FROM base:\${CODE_VERSION}

CMD /code/run-app

FROM extras:\${CODE_VERSION}

CMD /code/run-extras

Инструкция RUN

```
RUN apt update && apt install -y iputils-ping
RUN apt update && apt install –y iputils-ping — shell-форма
RUN ["apt", "update", "&&", "apt", "install", "-y", "iputils-ping"] — ехес-форма
RUN apt-get update && apt-get install -y \
  aufs-tools \
  automake \
  build-essential \
  curl \
  all\
  your\
  other\
  packages\
&& rm -rf /var/lib/{apt,dpkg,cache,log}/
```

COPY u ADD

COPY docker-entrypoint.sh /docker-entrypoint.sh

```
ADD git@git.example.com:foo/bar.git /bar
```

СОРҮ и ADD примеры

ADD --chown=www-data:www-data src/html, /var/www/html/

COPY --chown=www-data:www-data src/html, /var/www/html/

ADD srcFolder1, srcFolder2, srcFile, dstFolder/

COPY srcFolder1, srcFolder2, srcFile, dstFolder/

ADD hom* /mydir/

ADD hom?.txt /mydir/

COPY hom* /mydir/

COPY hom?.txt /mydir/

ENTRYPOINT u CMD

ENTRYPOINT ["ping"]

CMD ["127.0.0.1"]

	No ENTRYPOINT	ENTRYPOINT exec_entry p1_entry	ENTRYPOINT ["exec_entry", "p1_entry"]
No CMD	error, not allowed	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry
CMD ["exec_cmd", "p1_cmd"]	exec_cmd p1_cmd	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry exec_cmd p1_cmd
CMD exec_cmd p1_cmd	/bin/sh -c exec_cmd p1_cmd	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry /bin/sh -c exec_cmd p1_cmd

Изображение: Взаимоотношения ENTRYPOINT и CMD

Итоги

Dockerfile — это FROM \rightarrow RUN \rightarrow RUN \rightarrow RUN \rightarrow ENTRYPOINT \rightarrow CMD

FROM ubuntu

RUN apt update && apt install -y iputils-ping

#ENTRYPOINT ping 127.0.0.1

ENTRYPOINT ["ping"] CMD ["127.0.0.1"]

ENTRYPOINT ping 127.0.0.1