

費率層級管理指南

Rate Level Management Guide · UPS Reconciliation

1 · 核心觀念:結構共用,費率分層 Shared structure, per-level rates

「有哪些渠道、哪些附加費、哪幾段 Demand 期間」是全帳號一份的結構:新增或停用一項,所有費率層級同步生效。
「各層要收多少錢」才是分層的:每一層各自一份費率,互不影響。每位客戶指定一個層級;重新計價一律沿「客戶 → 所屬層級 → 該層費率」取價。

What exists — channels, surcharges, demand periods — is one account-wide structure: adding or disabling an item takes effect in every rate level at once. What each of them costs is per level: every level keeps its own figures. Each client is assigned one level, and repricing always follows client → level → that level's rates.

2 · 四個設定分頁 The four Configuration tabs

分頁 Tab	內容 Contents	範圍 Scope
01 一般設定 General Setting	1. 層級設定(建立/複製/切換層級、費率設定檔).2. 費用代碼設置.3. 系統設定(判定來源、燃油適用、啟用/停用) 1. Level Setup (levels & the rate configuration file) · 2. Charge Codes · 3. System (classification source, fuel eligibility, enable/disable)	帳號機制
02 帳戶與客戶 Account & Client Setup	客戶名單與各客戶的層級指派;搜尋、層級篩選與清單預覽 The client directory with level assignment; search, level filter and list preview	全帳號
03 渠道與附加費設置管理 Channels & Surcharges	1. 渠道管理.2. 附加費管理.3. Demand Surcharge —— 新增即同步所有層級;各附「已設費率層級 n/N」與各層費率預覽 1. Channels · 2. Surcharges · 3. Demand — additions reach every level; each list shows a levels-priced n/N badge and a per-level rates preview	全帳號(不分層)
04 渠道與附加費費率 Channel & Surcharge Rates	渠道基本運費、附加費費率、Demand 費率、燃油率、尺寸規則(材積除數與最低計費重)—— 唯一出現「正在編輯」選單的一頁 Base rates, surcharge rates, demand rates, fuel percentage and size rules (DIM divisor, minimum billable weights) — the only page with the Editing selector	分層(每層一份)

後續分頁順延:05 WMS/TMS 資料、06 帳單匯入、07 對帳分析、08 分析儀表板、09 帳單歷史、10 使用者管理。

The remaining tabs renumber accordingly: 05 WMS/TMS Data, 06 Batch Invoice Import, 07 Reconciliation Analysis, 08 Analytics Dashboard, 09 Invoice History, 10 User Administration.

3 · 新增項目時會發生什麼 What happens when you add an item

於「03」新增渠道、附加費或 Demand 期間,系統立即在每一個費率層級建立同一筆結構,費率欄留白;清單的「已設費率層級 n/N」隨填寫進度更新。新開層級亦自動帶入 reprice 預設渠道(含 Zone)與帳號現有的全部結構,費率一律留白。刪除與停用同樣全帳號一致:停用的附加費不參與計價,停用的渠道自「04」的選單收起。

Adding a channel, surcharge or demand period under 03 creates the same structure in every rate level at once, rates left blank; the levels-priced n/N badge tracks progress. A new level likewise starts with the reprice default channels (zones included) plus the account's current structure, every rate blank. Deleting and disabling are account-wide too: a disabled surcharge is not priced, and a disabled channel drops out of the 04 pickers.

4 · 填寫各層費率 Pricing a level

到「04 渠道與附加費費率」,右上角「正在編輯」切到目標層級:渠道基本運費(匯出模板/匯入/檢視已載費率)、附加費各 Zone 費率、Demand 各期間費率、本層燃油率、尺寸規則(材積除數預設值與依渠道批量設定、AHS 與大型包裹門檻及最低計費重)都在同一頁。附加費沿用各渠道自己的 Zone —— 與基本運費同一套

Zone,只是費率不同。

Open 04 Channel & Surcharge Rates and switch the Editing selector to the target level: base rates (template export / import / view), per-zone surcharge rates, demand rates, the level's fuel percentage and its size rules (default DIM divisor with per-channel bulk set, AHS and Large Package thresholds and minimum billable weights) all live on this one page. Surcharges reuse each channel's own zones — the same zones as the base rates, only the rates differ.

5 · 每一頁的固定配備 Standard controls on every page

每個設定分頁都有搜尋框、範圍下拉選單與預覽按鈕:渠道、附加費與 Demand 的預覽可切換層級檢視已匯入費率;層級設定預覽該層摘要;系統設定預覽全帳號狀態;客戶設定預覽名單。預覽視窗支援放大縮小。

Every configuration page carries a search box, a scoped dropdown filter and a preview button. The channel, surcharge and demand previews switch between levels to inspect imported rates; Level Setup previews the level's book, System the account-wide state, Client Setup the directory. The preview dialog zooms.