

Exploratory Testing — Issues Found

- **Product:** Fresh Prints Design Tool
 - **URL:** <https://design-tool.freshprints.com>
-

Issue 1 — The chat box takes your first message as the design title

Type: Functional

After clicking Save, the next thing you type into the help chat becomes the name of your design. Only the first message does this. Everything after it behaves as a normal chat.

Steps to reproduce

1. Open <https://design-tool.freshprints.com>.
2. Leave the shirt plain. Don't add anything to it.
3. Click **Save** at the top right.
4. The help chat opens at the bottom left with a warning: **"Title your design to save it"**.
5. Under it is a box reading **"Need help? Chat with us."**
6. Type `hey hi` and send.

Expected vs. actual behaviour


Expected: the box says "Chat with us", so the message goes to support and gets a reply. Naming the design should be asked for somewhere of its own, not through the chat.

Actual: no reply. The design is saved with the title **"hey hi"**.

Send a second message and it works like a chat again, so only the first one is taken.



Before: the warning, and a box inviting you to chat.



After: the message has become the design title.

Hypothesis about the root cause

The chat box looks like it is borrowed to collect the title. After Save, whatever is waiting for a title reads the next message sent, uses it, and then stops listening — which is why only the first message is affected.

How I would verify the fix

1. Repeat the steps. The message should reach support and get a reply, and should not rename or save anything.
2. Check the title is still "Untitled Design".

3. Confirm the title is asked for somewhere of its own, away from the chat.
4. Set a title there and save. That should work as normal.
5. Send a normal question in the chat and confirm nothing is saved.

Issue 2 — No price shown when sorting by price

Type: UX

Sorting the product list by price gives no prices to compare. Every other sort shows the number it sorted on, so this one stands out.

Steps to reproduce


1. Open <https://design-tool.freshprints.com>.
2. Click **Change Product** below the **Save** button.
3. The product list opens.
4. Choose **Price: Low to High** or **Price: High to Low** from the filters.
5. Look at the products listed.

Expected vs. actual behaviour

Expected: each product shows its price, so the ordering can be seen and products compared at a glance.

Actual: no prices are shown. Finding out what anything costs means opening each product one at a time, which defeats the point of sorting by price.

The other filters already do this. **Trending**, **Most Favorited** and **Top Rated** each show their count on the product itself, so those lists can be read without opening anything.



Sorted by price, but nothing on the products says what they cost.

Hypothesis about the root cause

The product card seems to show a count that belongs to the sort being used, and price was never added as one of those. So the two price sorts reorder the list correctly but leave the cards showing nothing to explain the order.

How I would verify the fix

1. Sort by **Price: Low to High** and confirm a price appears on every product.
2. Check the prices actually ascend, and descend under **Price: High to Low**.
3. Confirm the price matches what the product itself shows when opened.
4. Check the other sorts still show their own counts and are unchanged.

Issue 3 — No visible way to delete a selected design

Type: UX

A design can only be removed by pressing the Delete key, and nothing on screen says so.

Steps to reproduce

1. Open <https://design-tool.freshprints.com>.
2. Add a few designs to the shirt.
3. Select one of them.
4. Look for a way to remove it.

Expected vs. actual behaviour

Expected: a visible Delete or Remove control on the selected design, or somewhere in the panel beside it.

Actual: there is none. The **Size & Placement** panel offers Width, Height, Distance from Collar, Rotate, Arrange, Align and Effects, but nothing to delete. There is no X on the selection box either.

Pressing the **Delete** key does work, but nothing advertises it. A user who doesn't guess the shortcut is left with Undo, which is awkward once they have made other changes they want to keep.

Hypothesis about the root cause

The keyboard shortcut looks like it was added and the matching on-screen control never was, so the panel lists everything that changes a design but nothing that removes one.

How I would verify the fix

1. Select a design and confirm a Delete control is visible without hunting for it.
2. Use it and confirm only the selected design is removed, leaving the others alone.
3. Confirm the Delete key still works alongside it.
4. Confirm the removal can be undone.

Issue 4 — Some images do not load in the Print Type Guide

Type: Functional

Some of the images in the Print Type Guide never appear, leaving blank or broken placeholders.


Steps to reproduce

1. Open <https://design-tool.freshprints.com>.
2. Click the **Print Type Info** button.
3. Look through the guide.

Expected vs. actual behaviour

Expected: every image in the guide loads and displays.

Actual: some do not, leaving gaps where a picture should be. The guide is there to show what each print type looks like, so a missing picture is the one thing it needed to provide.



Hypothesis about the root cause

Most likely the images are individually missing or moved at the address the guide points to, rather than anything wrong with the guide itself — the ones beside them load from the same place.

How I would verify the fix

1. Open the guide and confirm every image loads.
2. Check each print type in the list, not only the ones visible without scrolling.
3. Reload with the cache cleared and confirm they still load.