



Easter

Easter Basket

HOOK
5.0 mm (H-8)**LEVEL**
Beginner**TIME**
1-2 hrs**YARN**
Worsted weight (#4) cotton

About 4.25 in (11 cm) across and 3 in (7.5 cm) tall, plus a handle about 8 in (20.5 cm) long, with the yarn and hook below

Materials

- Pink worsted weight cotton yarn, about 25 yd (22 m)
- White worsted weight cotton yarn, about 15 yd (13 m)
- 5.0 mm (H-8) crochet hook
- Yarn needle
- Stitch marker
- Scissors
- Optional: fabric stiffener spray and a few small paper or crochet eggs to fill the basket

Stitch guide (US terms)

ch = chain**sl st** = slip stitch**sc** = single crochet**inc** = increase (2 sc in the same stitch)**MR** = magic ring**st** = stitch(es)**x** = times (repeat what is in the parentheses)**BLO** = back loop only

Pattern

Base and walls (pink)

Work in a spiral without joining. Use a stitch marker to mark the first stitch of each round.

Rnd 1	6 sc in MR	(6)
Rnd 2	inc in each st around	(12)
Rnd 3	(sc, inc) x 6	(18)
Rnd 4	(sc in next 2 st, inc) x 6	(24)
Rnd 5	(sc in next 3 st, inc) x 6	(30)
Rnd 6	(sc in next 4 st, inc) x 6	(36)
Rnd 7	(sc in next 5 st, inc) x 6	(42)
Rnd 8	(sc in next 6 st, inc) x 6	(48)
Rnd 9	sc in each st around in back loops only (BLO). This makes a sharp corner where the base meets the walls	(48)
Rnds 10-16	sc in each st around	(48)
Color	Change to white.	
Rnds 17-20	sc in each st around	(48)
Rnd 21	sl st in each st around (48). Fasten off and weave in the end	(48)

Handle (white)

Worked flat in rows, back and forth.

Row 1	ch 29, sc in 2nd ch from hook and in each ch across	(28)
Rows 2-4	ch 1, turn, sc in each st across	(28)
Finish	Fasten off leaving long tails for sewing.	

Finishing

1. Weave in all the ends.
2. Fold the handle in half to find the middle, then lay it inside the basket with the short ends on opposite sides of the rim, 24 st apart (half of the 48 st around).
3. Sew each end of the handle to the inside of the basket over the top 4 rounds, using a strong double strand of white yarn. Sew through the handle and the wall in several rows.

4. Optional: spray the basket lightly with fabric stiffener and let it dry standing upright so it keeps its shape.

Tips

- Cotton makes a firmer basket than acrylic. Use a hook one size smaller for an even stiffer fabric.
- For a taller basket, add more plain rounds in pink before you change to white. The handle does not change.
- This basket is made for light things such as eggs or candy. Do not fill it with heavy items.

Sizes are approximate and depend on your yarn and tension. The photo is an illustration of the finished piece. For your personal use.