



Bags & Backpacks

Phone Crossbody Bag

HOOK
4.0 mm (G-6)

LEVEL
Beginner

TIME
2-3 hrs

YARN
Worsted weight (#4) cotton or acrylic

About 4.5 in (11.5 cm) wide and 7 in (18 cm) tall, plus a 2.5 in (6 cm) flap. Strap about 46 in (117 cm). Fits most standard-size phones; check yours against 4 in (10 cm) wide by 6.5 in (16.5 cm) tall inside. Measurements are approx.

Materials

- Worsted weight yarn, about 75 yd (68 m)
- 4.0 mm (G-6) crochet hook
- Yarn needle
- Scissors
- One 3/4 in (19 mm) button
- Sewing needle and matching thread (for the button)

Stitch guide (US terms)

ch = chain

sc = single crochet

st = stitch(es)

Pattern

Body (front, back and flap)

Worked in flat rows in one piece. Turning chains do not count as stitches.

Row 1	ch 17, sc in 2nd ch from hook and in each ch across	(16)
Rows 2-28	ch 1, turn, sc in each st across	(16)
Front	Rows 1-28 are the front of the bag. Row 28 will be the bottom fold. Keep going without a break.	
Rows 29-56	ch 1, turn, sc in each st across	(16)
Back	Rows 29-56 are the back of the bag.	
Rows 57-65	ch 1, turn, sc in each st across	(16)
Row 66	Button loop: ch 1, turn, sc in first 6 st, ch 4, skip next 4 st, sc in last 6 st (12 sc and 1 ch-4 loop). Fasten off and weave in the end	(16)

Side seams

Fold the body so rows 1-28 (front) lie on top of rows 29-56 (back). The flap continues past the back top edge and folds down over the front.

Seam 1	Join yarn at a top corner of the front and back, working through both layers. Sc evenly down the side edge, 1 sc in each row-end (28 sc). Fasten off	(28)
Seam 2	Repeat on the other side (28 sc). Weave in the ends	(28)

Strap

Worked in flat rows. Turning chains do not count as stitches.

Row 1	ch 161, sc in 2nd ch from hook and in each ch across	(160)
Rows 2-4	ch 1, turn, sc in each st across	(160)
Finish	Fasten off leaving a long tail for sewing.	

Finishing

1. Sew each end of the strap to the inside of the bag at a top side corner, right at the seam, with a square of small stitches.

2. Sew the button to the center of the front, about 2 in (5 cm) below the top edge, so the loop reaches it when the flap is closed.
3. Weave in all the ends.

Tips

- Use a hook one size smaller than the yarn label suggests for a tight, dense fabric that holds its shape.
- For a longer or shorter strap, add or remove 7 ch at the start. Every 7 ch changes the length by about 2 in (5 cm).
- A single crochet strap stretches a little with weight. Cotton stretches less than acrylic.

Sizes are approximate and depend on your yarn and tension. The photo is an illustration of the finished piece. For your personal use.