Internet Engineering Task Force (IETF)

Request for Comments: 6850 Category: Standards Track

ISSN: 2070-1721

A. Rijhsinghani Hewlett-Packard K. Zebrose HW Embedded January 2013

Definitions of Managed Objects for Routing Bridges (RBridges)

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols. In particular, it defines objects for managing a Routing Bridge (RBridge), also known as a TRILL Switch, based on the IETF TRILL (Transparent Interconnection of Lots of Links) protocol.

Status of This Memo

This is an Internet Standards Track document.

This document is a product of the Internet Engineering Task Force (IETF). It represents the consensus of the IETF community. It has received public review and has been approved for publication by the Internet Engineering Steering Group (IESG). Further information on Internet Standards is available in Section 2 of RFC 5741.

Information about the current status of this document, any errata, and how to provide feedback on it may be obtained at http://www.rfc-editor.org/info/rfc6850.

Copyright Notice

Copyright (c) 2013 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to BCP 78 and the IETF Trust's Legal Provisions Relating to IETF Documents (http://trustee.ietf.org/license-info) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Simplified BSD License text as described in Section 4.e of the Trust Legal Provisions and are provided without warranty as described in the Simplified BSD License.

Table of Contents

1.	Introduction2
	The Internet-Standard Management Framework
- :	Overview
4.	
5	Structure of the MIB Module4
J .	5.1. Textual Conventions
	5.2. The rbridgeBase Subtree
	5.3. The rbridgeFdb Subtree
	5.4. The rbridgeVlan Subtree
	5.5. The rbridgeEsadi Subtree
	5.6. The rbridgeCounters Subtree4
	5.7. The rbridgeSnooping Subtree5
	5.8. The rbridgeDtree Subtree5
	5.9. The rbridgeTrill Subtree5
_	5.10. The Notifications Subtree
6.	Relationship to Other MIB Modules 6.1. Relationship to IF-MIB 6.2. Relationship to BRIDGE-MIB 6.3. Relationship to P-BRIDGE-MIB 6.4. Relationship to Q-BRIDGE-MIB 6.5. Relationship to IEEE8021-BRIDGE-MIB 6.6. Relationship to IEEE8021-Q-BRIDGE-MIB
	6.1. Relationship to IF-MIB5
	6.2. Relationship to BRIDGE-MIB6
	6.3. Relationship to P-BRIDGE-MIB
	6.4. Relationship to Q-BRIDGE-MIB6
	6.5. Relationship to IEEE8021-BRIDGE-MIB
	6.6. Relationship to IEEE8021-0-BRIDGE-MIB
	6.7. Relationship to ISIS-MIB8
	6.7. Relationship to ISIS-MIB
7.	Definition of the RBridge MIB Module9
	Security Considerations
a.	IANA Considerations
10	Contributors
11.	References
+ + •	11.1. Normative References57
	11.1. NUI Mattve References
	11.2. Informative References

1. Introduction

This document describes a model for managing Routing Bridges (RBridges), also known as TRILL Switches, as defined in [RFC6325]. RBridges provide optimal pair-wise forwarding without configuration using IS-IS routing and encapsulation of traffic. RBridges are compatible with previous IEEE 802.1 customer bridges as well as IPv4 and IPv6 routers and end nodes. They are as invisible to current IP routers as bridges are and, like routers, they terminate the bridge spanning tree protocol. In creating an KBridge management model, the device is viewed primarily as a customer bridge. For a discussion of the problem addressed by TRILL (Transparent Interconnection of Lots of Links), see [RFC5556].

RBridges support features specified for transparent bridges in IEEE 802.1, and the corresponding MIB modules are used to manage those features. For IS-IS purposes, the corresponding MIB module is used to manage the protocol. This MIB module specifies those objects that are TRILL-specific and hence not available in other MIB modules.

2. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

Overview

The RBridge MIB module is intended as an overall framework for managing RBridges, also known as TRILL Switches. Where possible, the MIB references existing MIB definitions in order to maximize reuse. This results in a considerable emphasis on the relationship with other MIB modules.

Starting with the physical interfaces, there are requirements for certain elements of the IF-MIB to be implemented. These elements are required in order to connect the per-port parameters to higher-level functions of the physical device.

Transparent bridging, VLANs, traffic classes, and multicast filtering are supported by the TRILL protocol, and the corresponding management is expected to conform to the BRIDGE-MIB module [RFC4188] and to the P-BRIDGE-MIB and Q-BRIDGE-MIB modules [RFC4363].

The IS-IS routing protocol is used in order to determine the optimum pair-wise forwarding path. This protocol is managed using the IS-IS MIB module defined in [RFC4444]. Since the TRILL protocol specifies the use of a single level and a fixed area address of zero, some IS-IS MIB objects are not applicable. Some IS-IS MIB objects are used in the TRILL protocol.

4. Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [RFC2119].

5. Structure of the MIB Module

Objects in this MIB module are arranged into subtrees. Each subtree is organized as a set of related objects. The various subtrees are shown below. These are supplemented with required elements of the IF-MIB, ISIS-MIB, BRIDGE-MIB, P-BRIDGE-MIB, Q-BRIDGE-MIB, and IEEE Bridge MIB modules.

5.1. Textual Conventions

Textual conventions are defined to represent object types relevant to TRILL.

5.2. The rbridgeBase Subtree

This subtree contains system- and port-specific objects applicable to all RBridges.

5.3. The rbridgeFdb Subtree

This subtree contains objects applicable to the forwarding database used by the RBridge in making packet-forwarding decisions. Because to contains additional information used by the TRILL protocol not applicable to 802.1D/Q bridges, it is a superset of the corresponding subtrees defined in the BRIDGE-MIB and Q-BRIDGE-MIB.

5.4. The rbridgeVlan Subtree

This subtree describes objects applicable to VLANs configured on the RBridge.

5.5. The rbridgeEsadi Subtree

This subtree describes objects relevant to RBridges that support the optional End-Station Address Distribution Information (ESADI) protocol.

5.6. The rbridgeCounters Subtree

This subtree contains statistics maintained by RBridges that can aid in monitoring and troubleshooting networks connected by them.

5.7. The rbridgeSnooping Subtree

This subtree describes objects applicable to RBridges capable of snooping IPv4 and/or IPv6 multicast control frames and pruning IP multicast traffic based on detection of IP multicast routers and listeners.

5.8. The rbridgeDtree Subtree

This subtree contains objects relevant to distribution trees computed by RBridges for the forwarding of multi-destination frames.

5.9. The rbridgeTrill Subtree

This subtree contains objects applicable to the TRILL IS-IS protocol, beyond what is available in the ISIS-MIB.

The Notifications Subtree

The defined notifications are focused on the TRILL protocol functionality. Notifications are defined for changes in the Designated RBridge status and the topology.

6. Relationship to Other MIB Modules

The IF-MIB, BRIDGE-MIB, P-BRIDGE-MIB, Q-BRIDGE-MIB, IEEE8021-BRIDGE-MIB, IEEE8021-Q-BRIDGE-MIB, and ISIS-MIB modules all contain objects relevant to the RBridge MIB. Management objects contained in these modules are not duplicated here, to reduce overlap to the extent possible.

The Bridge MIB modules were originally written in the IETF and implemented by many vendors. Per [RFC4663], this has recently been transferred to the IEEE 802.1 working group. As vendors may have implemented either the IETF or IEEE Bridge MIB modules, this RBridge MIB module is designed to work with either one.

6.1. Relationship to IF-MIB

The port identification elements MUST be implemented in order to allow them to be cross-referenced. The Interfaces MIB [RFC2863] requires that any MIB module that is an adjunct of the Interfaces MIB clarify specific areas within the Interfaces MIB module. These areas were intentionally left vague in the Interfaces MIB module to avoid over-constraining the MIB, thereby precluding management of certain media types. Section 4 of [RFC2863] enumerates several areas that a

media-specific MIB module must clarify. The implementor is referred to [RFC2863] in order to understand the general intent of these areas.

6.2. Relationship to BRIDGE-MIB

The following subtrees in the BRIDGE-MIB [RFC4188] contain information relevant to RBridges when the corresponding functionality is implemented.

- o dot1dBase
- o dot1dTp
- o dot1dStatic

6.3. Relationship to P-BRIDGE-MIB

The following subtrees in the P-BRIDGE-MIB [RFC4363] contain information relevant to RBridges when the corresponding functionality is implemented.

- o dot1dExtBase
- o dot1dPriority
- o dot1dGarp
- o dot1dGmrp
- o dot1dTpHCPortTable
- o dot1dTpPort0verflowTable

6.4. Relationship to Q-BRIDGE-MIB

The following groups in the Q-BRIDGE-MIB [RFC4363] contain information relevant to RBridges when the corresponding functionality is implemented. This functionality is also contained in the IEEE8021-Q-BRIDGE-MIB.

- o dot1qBase
- o dot1qTp
- o dot1qStatic

- o dot1qVlan
- o dot1vProtocol

6.5. Relationship to IEEE8021-BRIDGE-MIB

The following subtrees in the IEEE8021-BRIDGE-MIB contain information relevant to RBridges when the corresponding functionality is implemented.

- o ieee8021BridgeBase
- o ieee8021BridgeTp
- o ieee8021BridgePriority
- o ieee8021BridgeMrp
- o ieee8021BridgeMmrp
- o ieee8021BridgeInternalLan
- o ieee8021BridgeDot1d

6.6. Relationship to IEEE8021-Q-BRIDGE-MIB

The following subtrees in the IEEE8021-Q-BRIDGE-MIB contain information relevant to RBridges when the corresponding functionality is implemented.

- o ieee8021QBridgeBase
- o ieee8021QBridgeTp
- o ieee8021QBridgeStatic
- o ieee8021QBridgeVlan
- o ieee8021QBridgeProtocol

6.7. Relationship to ISIS-MIB

"Management Information Base for Intermediate System to Intermediate System (IS-IS)" [RFC4444] defines a MIB module for the IS-IS routing protocol when it is used to construct routing tables for IP networks. While most of these objects are applicable to the TRILL layer 2 implementation, note the IS-IS constraints for the current version of TRILL [RFC6325]:

- The TRILL IS-IS instance uses a single Level 1 IS-IS area.
- The TRILL Level 1 IS-IS area uses the fixed area address zero.
- The TRILL IS-IS instance is not used for IP address advertisement.
- The TRILL IS-IS instance is used for only a single protocol: TRILL.

Accordingly, tables that report IP address reachability and tables that allow configuration or reporting of multiple IS-IS areas, multiple IS-IS levels, or multiple protocols will be empty in the ISIS-MIB module for the current version of TRILL.

Note also that when more than one instance of the IS-IS protocol is running on a device, as in the case of a device performing both RBridge and IS-IS IP router functions, multiple instances of the ISIS-MIB module can be distinguished by the use of SNMPv3 contexts or SNMPv1 communities.

6.8. MIB Modules Required for IMPORTS

The following MIB module imports objects from the SNMPv2-SMI [RFC2578], SNMPv2-TC [RFC2579], SNMPv2-CONF [RFC2580], IF-MIB [RFC2863], INET-ADDRESS-MIB [RFC4001], BRIDGE-MIB [RFC4188], and Q-BRIDGE-MIB [RFC4363]. (The IEEE Bridge MIB modules import similar TCs.)

7. Definition of the RBridge MIB Module

```
RBRIDGE-MIB DEFINITIONS ::= BEGIN
-- MIB for RBRIDGE devices, also known as TRILL Switches
IMPORTS
   MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE,
   Counter32, Counter64, Unsignéd32, mib-2
       FROM SNMPv2-SMI
                                -- RFC2578
   TEXTUAL-CONVENTION, TruthValue, MacAddress, RowStatus
   FROM SNMPv2-TC -- RFC2579
MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
                                 -- RFC2580
       FROM SNMPv2-CONF
   VlanId, PortList
       FRÓM Q-BRIDGE-MIB
                                 -- RFC4363
   InetAddress, InetAddressType
       FROM INET-ADDRESS-MIB -- RFC4001
   BridgeId
       FROM BRIDGE-MIB
                               -- RFC4188
   InterfaceIndex
       FROM IF-MIB
                               -- RFC2863
rbridgeMIB MODULE-IDENTITY
LAST-UPDATED "201301070000Z"
ORGANIZATION "IETF TRILL Working Group"
CONTACT-INFO
     "http://datatracker.ietf.org/wg/trill/charter/
    Email: trill@ietf.org
           Anil Rijhsinghani
           Hewlett-Packard
      Tel: +1 508 323 1251
    Email: anil@charter.net
           Kate Zebrose
           HW Embedded
      Tel: +1 617 840 9673
    Email: zebrose@alum.mit.edu"
   DESCRIPTION
       "The RBridge MIB module for managing switches that support
       the TRILL protocol."
REVISION "201301070000Z"
```

DESCRIPTION

"Initial version, published as RFC 6850.

Copyright (c) 2013 IETF Trust and the persons identified as authors of the code. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, is permitted pursuant to, and subject to the license terms contained in, the Simplified BSD License set forth in Section 4.c of the IETF Trust's Legal Provisions Relating to IETF Documents (http://trustee.ietf.org/license-info)."

::= { mib-2 214 }

```
-- Subtrees in the RBridge MIB
rbridgeNotifications
rbridgeObjects
rbridgeConformance

OBJECT IDENTIFIER ::= { rbridgeMIB 0 }
OBJECT IDENTIFIER ::= { rbridgeMIB 1 }
OBJECT IDENTIFIER ::= { rbridgeMIB 2 }
rbridgeBase
rbridgeBase
rbridgeFdb
rbridgeVlan
rbridgeEsadi
rbridgeCounter
rbridgeSnooping
rbridgeDtree
rbridgeTrill

OBJECT IDENTIFIER ::= { rbridgeObjects 2 }

OBJECT IDENTIFIER ::= { rbridgeObjects 3 }

OBJECT IDENTIFIER ::= { rbridgeObjects 4 }

OBJECT IDENTIFIER ::= { rbridgeObjects 5 }

OBJECT IDENTIFIER ::= { rbridgeObjects 6 }

OBJECT IDENTIFIER ::= { rbridgeObjects 7 }

OBJECT IDENTIFIER ::= { rbridgeObjects 7 }

OBJECT IDENTIFIER ::= { rbridgeObjects 8 }
                                    OBJECT IDENTIFIER ::= { rbridgeObjects 1
-- Type Definitions
RbridgeAddress ::= TEXTUAL-CONVENTION DISPLAY-HINT "1x:"
       STATUS current
       DESCRIPTION
               "The Media Access Control (MAC) address used by an RBridge
       port. This may match the RBridge IS-IS SystemID." SYNTAX OCTET STRING (SIZE (6))
```

```
RbridgeNickname ::= TEXTUAL-CONVENTION DISPLAY-HINT "d"
    STATUS current
    DESCRIPTION
         "The 16-bit identifier used in TRILL as an
         abbreviation for the RBridge's 48-bit IS-IS System ID.
         The value 0 means a nickname is not specified, the values 0xFFC0 through 0xFFFE are reserved for future allocation, and the value 0xFFFF is permanently reserved."
    REFERENCE
         "RFC 6325, Section 3.7"
    SYNTAX Unsigned32 (0..65471)
-- the rbridgeBase subtree
___
-- Implementation of the rbridgeBase subtree is mandatory for all
-- RBridges.
rbridgeBaseTrillVersion OBJECT-TYPE
    SYNTAX
                  Unsigned32
    MAX-ACCESS
                  read-only
    STATUS
                  current
    DESCRIPTION
         "The maximum TRILL version number that this RBridge
         supports."
    REFERENCE
         "RFC 6325, Section 3.2"
    ::= { rbridgeBase 1 }
rbridgeBaseNumPorts OBJECT-TYPE
    SYNTAX
                  Unsigned32
                  "ports"
    UNITS
    MAX-ACCESS
                  read-only
                  current
    STATUS
    DESCRIPTION
         "The number of ports controlled by this RBridge."
    REFERENCE
         "RFC 6325, Section 2.6.1"
    ::= { rbridgeBase 2 }
rbridgeBaseForwardDelay OBJECT-TYPE
    SYNTAX
                  Unsigned32 (4..30)
                  "seconds"
    UNITS
    MAX-ACCESS
                  read-write
    STATUS
                  current
```

```
DESCRIPTION
        "Modified aging time for address entries after an appointed
        forwarder change.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.8.3"
    ::= { rbridgeBase 3 }
rbridgeBaseUniMultipathEnable OBJECT-TYPE
               TruthValue
   SYNTAX
   MAX-ACCESS read-write
   STATUS
                current
   DESCRIPTION
        "The enabled status of unicast TRILL multipathing.
        It is enabled when true.
       The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Appendix C"
    ::= { rbridgeBase 4 }
rbridgeBaseMultiMultipathEnable OBJECT-TYPE
               TruthValue
   SYNTAX
   MAX-ACCESS read-write
   STATUS
                current
   DESCRIPTION
        "The enabled status of multi-destination TRILL multipathing.
        It is enabled when true.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Appendix C"
    ::= { rbridgeBase 5 }
rbridgeBaseAcceptEncapNonadj OBJECT-TYPE
               TruthValue
   SYNTAX
   MAX-ACCESS read-write
   STATUS
                current
   DESCRIPTION
        "Accept TRILL-encapsulated frames from a neighbor with which
        this RBridge does not have an IS-IS adjacency, when the value
        of this object is 'true'.
```

```
The value of this object MUST be retained across
        re-initializations of the management system.'
    REFERENCE
        "RFC 6325, Section 4.6.2"
    ::= { rbridgeBase 6 }
rbridgeBaseNicknameNumber OBJECT-TYPE SYNTAX Unsigned32 (1..256)
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The number of nicknames this RBridge should acquire.
        These can be acquired dynamically or configured
       statically. This value represents the maximum number of entries in rbridgeBaseNicknameTable.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        "RFC 6325, Section 3.7.3"
    ::= { rbridgeBase 7 }
-- The RBridge Base Nickname Table
rbridgeBaseNicknameTable OBJECT-TYPE
    SYNTAX SEQUENCE OF RbridgeBaseNicknameEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A table that contains information about nicknames
        configured by an operator or learned dynamically
        by this RBridge."
    REFERÈNCE
        "RFC 6325, Section 3.7"
    ::= { rbridgeBase 8 }
rbridgeBaseNicknameEntry OBJECT-TYPE
    SYNTAX
                RbridgeBaseNicknameEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A list of information for each nickname of the RBridge."
    REFERENCE
        "RFC 6325, Section 3.7"
    INDEX { rbridgeBaseNicknameName }
    ::= { rbridgeBaseNicknameTable 1 }
```

```
RbridgeBaseNicknameEntry ::=
     SEQUENCE {
          rbridgeBaseNicknameName
               RbridgeNickname,
          rbridgeBaseNicknamePriority
          Unsigned32, rbridgeBaseNicknameDtrPriority
               Unsigned32,
          rbridgeBaseNicknameType
               INTEGER.
          rbridgeBaseNicknameRowStatus
               RowStatus
     }
rbridgeBaseNicknameName OBJECT-TYPE
     SYNTAX
                    RbridgeNickname
     MAX-ACCESS
                    not-accessible
     STATUS
                    current
     DESCRIPTION
          "Nicknames are 16-bit quantities that act as
          abbreviations for RBridge's 48-bit IS-IS System ID to
          achieve a more compact encoding."
     REFERENCE
          "RFC 6325. Section 3.7"
     ::= { rbridgeBaseNicknameEntry 1 }
rbridgeBaseNicknamePriority OBJECT-TYPE SYNTAX Unsigned32 (0..255)
     MAX-ACCESS read-create
     STATUS
                    current
     DESCRIPTION
          "This RBridge's priority to hold this nickname.
          the nickname is configured, the default value of this object is 192. When the nickname is configured, the most significant bit (0x80) must be set and the bottom 7 bits have the default value of 0x40, so 0x80 + 0x40 == 0xCO,
          which is 192 decimal. Additionally, the bottom 7 bits could be configured to a value other than 0x40.
          The value of this object MUST be retained across
          re-initializations of the management system."
     REFERENCE
          "RFC 6325, Section 3.7"
AL { 192 }
     DEFVAL
     ::= { rbridgeBaseNicknameEntry 2 }
```

```
rbridgeBaseNicknameDtrPriority OBJECT-TYPE
   SYNTAX
                Unsigned32 (1..65535)
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "The distribution tree root priority for this nickname.
        The default value of this object is 32768.
       The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.5"
               { 32768 }
   DEFVAL
    ::= { rbridgeBaseNicknameEntry 3 }
rbridgeBaseNicknameType OBJECT-TYPE
   SŸNTAX
                INTEGER {
                    static(1),
                    dynamic(2)
   MAX-ACCESS
                read-only
                current
   STATUS
   DESCRIPTION
        "This object indicates the status of the entry. The
        default value is static(1).
            static(1) - this entry has been configured and
                will remain after the next reset of the RBridge.
            dynamic(2) - this entry has been acquired by the
                RBridge nickname acquisition protocol.
   REFERENCE
        "RFC 6325, Section 3.7"
                { static }
    ::= { rbridgeBaseNicknameEntry 4 }
rbridgeBaseNicknameRowStatus OBJECT-TYPE
   SYNTAX
                RowStatus
   MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "This object indicates the status of the entry."
    ::= { rbridgeBaseNicknameEntry 5 }
```

```
-- The RBridge Port Table
rbridgeBasePortTable OBJECT-TYPE
   SYNTAX SEQUENCE OF RbridgeBasePortEntry
   MAX-ACCESS not-accessible
              current
   STATUS
   DESCRIPTION
        "A table that contains generic information about every
       port that is associated with this RBridge."
   REFERENCE
       "RFC 6325, Section 5.3"
    ::= { rbridgeBase 9 }
rbridgeBasePortEntry OBJECT-TYPE
              RbridgeBasePortEntry
   SYNTAX
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION
       "A list of information for each port of the bridge."
   REFERENCE
       "RFC 6325, Section 5.3"
   INDEX { rbridgeBasePort }
    ::= { rbridgeBasePortTable 1 }
RbridgeBasePortEntry ::=
   SEQUENCE {
       rbridgeBasePort
           Unsigned32,
       rbridgeBasePortIfIndex
           InterfaceIndex,
       rbridgeBasePortDisable
       TruthValue, rbridgeBasePortTrunkPort
           TruthValue,
       rbridgeBasePortAccessPort
           TruthValue,
       rbridgeBasePortP2pHellos
           TruthValue,
       rbridgeBasePortState
           IÑTEGER,
       rbridgeBasePortInhibitionTime
           Unsigned32,
       rbridgeBasePortDisableLearning
           TruthValue,
       rbridgeBasePortDesiredDesigVlan
```

VlanId,

RBridges: TRILL Base MIB

```
rbridgeBasePortDesigVlan
             VlanId,
        rbridgeBasePortStpRoot
             BridgeId,
        rbridgeBasePortStpRootChanges
        Counter32, rbridgeBasePortStpWiringCloset
             BridgeId
}
rbridgeBasePort OBJECT-TYPE
                 Unsigned32 (1..65535)
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "The port number of the port for which this entry
        contains RBridge management information."
        "RFC 6325, Section 5.3"
    ::= { rbridgeBasePortEntry 1 }
rbridgeBasePortIfIndex OBJECT-TYPE
    SŸNTAX
                 InterfaceIndex
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
        "The value of the instance of the ifIndex object, defined in the IF-MIB, for the interface corresponding
        to this port. The RBridge port sits on top of this interface."
    ::= { rbridgeBasePortEntry 2 }
rbridgeBasePortDisable OBJECT-TYPE
    SYNTAX
                 TruthValue
    MAX-ACCESS
                 read-write
    STATUS
                current
    DESCRIPTION
        "Disable port bit. When this bit is set (true), all frames
        received or to be transmitted are discarded, with the
        possible exception of some layer 2 control frames that may
        be generated and transmitted or received and processed
        locally. Default value is 'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
```

```
REFERENCE
    "RFC 6325, Section 4.9.1"
DEFVAL { false }
    ::= { rbridgeBasePortEntry 3 }
rbridgeBasePortTrunkPort OBJECT-TYPE
    SYNTAX
                 TruthValue
    MAX-ACCESS
                 read-write
    STATUS
                 current
    DESCRIPTION
        "End-station service disable (trunk port) bit. When this bit
        is set (true), all native frames received on the port and all
        native frames that would have been sent on the port are
        discarded. Default value is 'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        ::= { rbridgeBasePortEntry 4 }
rbridgeBasePortAccessPort OBJECT-TYPE
                TruthValue
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
        "TRILL traffic disable (access port) bit. If this bit is set, the goal is to avoid sending any TRILL frames, except
        TRILL-Hello frames, on the port, since it is intended only
        for native end-station traffic. This ensures that the link is not on the shortest path for any destination. Default
        value is 'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        "RFC 6325, Section 4.9.1"
               { false }
    ::= { rbridgeBasePortEntry 5 }
rbridgeBasePortP2pHellos OBJECT-TYPE
                 TruthValue
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
        "Use point-to-point (P2P) Hellos bit. If this bit is set,
        Hello's sent on this port are IS-IS P2P Hellos, not the
```

```
default TRILL-Hellos. In addition, the IS-IS P2P three-way
        handshake is used on P2P RBridge links. Default value is
         'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        DEFVAL
    ::= { rbridgeBasePortEntry 6 }
rbridgeBasePortState OBJECT-TYPE
    SŸNTAX
                 INTEGER {
                         uninhibited(1),
portInhibited(2),
                         vlanInhibited(3),
                         disabled(4).
                         broken(5)
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
         "The port's current state. If the entire port is
        inhibited, its state is portInhibited(2). If specific VLANs
        are inhibited, the state is vlanInhibited(3), and
        rbridgeVlanPortTable will tell which VLANs are inhibited.
        For ports that are disabled (see rbridgeBasePortDisable), this object will have a value of disabled(4). If the RBridge has detected a port that is malfunctioning, it will
        place that port into the broken(5) state.
    REFERENCE
        "RFC 6325, Section 4.2.4.3"
    ::= { rbridgeBasePortEntry 7 }
rbridgeBasePortInhibitionTime OBJECT-TYPE
                 Unsigned32
    SŸNTAX
                 "seconds"
    UNITS
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "Time in seconds that this RBridge will inhibit forwarding
        on this port after it observes a spanning tree root bridge
        change on a link or receives conflicting VLAN forwarder
        information. The default value is 30.
```

The value of this object MUST be retained across re-initializations of the management system."

```
REFERENCE
   "RFC 6325, Section 4.2.4.3"
DEFVAL { 30 }
    ::= { rbridgeBasePortEntry 8 }
rbridgeBasePortDisableLearning OBJECT-TYPE
    SYNTAX
                TruthValue
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "Disable learning of MAC addresses seen on this port.
        To disable learning, the value of this object must be
        set to 'true'. The default is 'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        ::= { rbridgeBasePortEntry 9 }
rbridgeBasePortDesiredDesigVlan OBJECT-TYPE
    SŸNTAX
                VlanId
    MAX-ACCESS
               read-write
    STATUS
                current
    DESCRIPTION
        "The VLAN that a Designated RBridge (DRB) will specify in
        its TRILL-Hellos as the VLAN to be used by all RBridges on
the link for TRILL frames. This VLAN must be enabled on
        this port.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        "RFC 6325, Section 4.4.3"
    ::= { rbridgeBasePortEntry 10 }
rbridgeBasePortDesigVlan OBJECT-TYPE
    SYNTAX
                VlanId
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The VLAN being used on this link for TRILL frames."
    REFERENCE
        "RFC 6325, Section 4.4.3"
    ::= { rbridgeBasePortEntry 11 }
```

```
rbridgeBasePortStpRoot OBJECT-TYPE
    SYNTAX
                  BridgeId
    MAX-ACCESS
                  read-only
    STATUS
                  current
    DESCRIPTION
         "The bridge identifier of the root of the spanning tree,
         as learned from a Bridge PDU (BPDU) received on this port. For the Multiple Spanning Tree Protocol (MSTP), this is
         the root bridge of the Common and Internal Spanning Tree
         (CIST). If no BPDU has been heard, the value returned
         is a string of zeros."
    REFERENCE
         "RFC 6325, Section 4.2.4.3"
    ::= { rbridgeBasePortEntry 12 }
rbridgeBasePortStpRootChanges OBJECT-TYPE
    SYNTAX
                  Counter32
                  "changes"
    UNITS
    MAX-ACCESS read-only
    STATUS
                  current
    DESCRIPTION
         "The number of times a change in the root bridge is seen from
         spanning tree BPDUs received on this port, indicating a
         change in bridged LAN topology. Each such change may cause
         the port to be inhibited for a period of time. This counter should be synchronized with ifCounterDiscontinuityTime.
         Discontinuities in the value of this counter can occur
         at re-initialization of the management system.'
    REFERENCE
         "RFC 6325, Section 4.9.3.2"
    ::= { rbridgeBasePortEntry 13 }
rbridgeBasePortStpWiringCloset OBJECT-TYPE
    SÝNTAX
                  BridgeId
    MAX-ACCESS
                  read-write
    STATUS
                  current
    DESCRIPTION
         "The Bridge ID to be used as the spanning tree root in BPDUs
         sent for the Wiring Closet topology solution described in [RFC6325]. Note that the same value of this object must be
         set on all RBridge ports participating in this solution.
The default value is all 0s. A non-zero value configured
         into this object indicates that this solution is in use.
         The value of this object MUST be retained across
```

re-initializations of the management system."

```
REFERENCE
        "RFC 6325, Appendix A.3.3"
    ::= { rbridgeBasePortEntry 14 }
-- RBridge Forwarding Database
rbridgeConfidenceNative OBJECT-TYPE
   SŸNTAX
            Unsigned32 (0..255)
   MAX-ACCESS read-write
   STATUS
              current
   DESCRIPTION
        "The confidence level associated with MAC addresses
        learned from native frames. This is applicable to
        all RBridge ports.
       The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.8.1"
    ::= { rbridgeFdb 1 }
rbridgeConfidenceDecap OBJECT-TYPE
   SYNTAX
               Unsigned32 (0..255)
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION
        "The confidence level associated with inner MAC addresses
        learned after decapsulation of a TRILL data frame.
        This is applicable to all RBridge ports.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.8.1"
    ::= { rbridgeFdb 2 }
rbridgeConfidenceStatic OBJECT-TYPE
   SYNTAX Unsigned32 (0..255)
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION
        "The confidence level associated with MAC addresses that
        are statically configured. The default value is 255.
       The value of this object MUST be retained across
        re-initializations of the management system."
```

```
REFERENCE
    "RFC 6325, Section 4.8.2"
DEFVAL { 255 }
    ::= { rbridgeFdb 3 }
-- Multiple Forwarding Databases for RBridges
-- This allows for an instance per FdbId, as defined in the
-- Bridge MIB.
-- Each VLAN may have an independent FDB, or multiple VLANs may
rbridgeUniFdbTable OBJECT-TYPE
    SYNTAX SEQUENCE OF RbridgeUniFdbEntry MAX-ACCESS not-accessible
    STATUS current DESCRIPTION
        "A table that contains information about unicast entries
        for which the device has forwarding and/or filtering
        information. This information is used by the
        transparent bridging function in determining how to propagate a received frame."
    REFERENCE
        "RFC 6325, Section 4.8"
    ::= { rbridgeFdb 4 }
rbridgeUniFdbEntry OBJECT-TYPE
    SYNTAX
            RbridgeUniFdbEntry
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "Information about a specific unicast MAC address for
        which the RBridge has some forwarding and/or filtering
        information."
    INDEX { rbridgeFdbId, rbridgeUniFdbAddr }
    ::= { rbridgeUniFdbTable 1 }
RbridgeUniFdbEntry ::=
    SEQUENCE {
        rbridgeFdbId
            Unsigned32.
        rbridgeUniFdbAddr
            MacAddress,
```

RFC 6850

```
rbridgeUniFdbPort
         Unsigned32, rbridgeUniFdbNickname
              RbridgeNickname,
         rbridgeUniFdbConfidence
              Unsigned32.
         rbridgeUniFdbStatus
              INTEGER
    }
rbridaeFdbId OBJECT-TYPE
                   Unsigned32 (0..4294967295)
    SYNTAX
    MAX-ACCESS
                   not-accessible
    STATUS
                   current
    DESCRIPTION
         "The identity of this Filtering Database."
    ::= { rbridgeUniFdbEntry 1 }
rbridgeUniFdbAddr OBJECT-TYPE
    SYNTAX
                  MacAddress
    MAX-ACCESS
                   not-accessible
    STATUS
                  current
    DESCRIPTION
         "A unicast MAC address for which the device has
         forwarding information."
    ::= { rbridgeUniFdbEntry 2 }
rbridgeUniFdbPort OBJECT-TYPE
    SYNTAX
                  Unsigned32 (0..65535)
    MAX-ACCESS
                   read-only
    STATUS
                   current
    DESCRIPTION
         "Either the value '0', or the RBridge port number of the port on which a frame having a source address equal to the value of the corresponding instance of rbridgeUniFdbAddr has been seen. A value of '0' indicates that the port
         number has not been learned but that the device does have
         some information about this MAC address.
         Implementors are encouraged to assign the port value to
         this object whenever it is available, even for addresses
         for which the corresponding value of rbridgeUniFdbStatus is not learned(3)."
     ::= { rbridgeUniFdbEntry 3 }
rbridgeUniFdbNickname OBJECT-TYPE
    SYNTAX
                   RbridgeNickname
    MAX-ACCESS read-only
```

```
STATUS
                 current
    DESCRIPTION
         "The RBridge nickname that is placed in the egress
        nickname field of a TRILL frame sent to this
        rbridgeFdbAddress in this rbridgeFdbId."
    REFERENCE
        "RFC 6325, Section 4.8.1"
    ::= { rbridgeUniFdbEntry 4 }
rbridgeUniFdbConfidence OBJECT-TYPE
                 Unsigned32 (0..255)
                 read-only
    MAX-ACCESS
    STATUS
                 current
    DESCRIPTION
         "The confidence level associated with this entry."
    REFERENCE
    "RFC 6325, Section 4.8.1"
::= { rbridgeUniFdbEntry 5 }
rbridgeUniFdbStatus OBJECT-TYPE
                 INTEGER {
    SYNTAX
                      other(1),
invalid(2),
                      learned(3).
                      self(4),
                      mgmt(5)
                      esadi(6)
                 }
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
         "The status of this entry. The meanings of the values
        are:
             other(1) - none of the following.
             invalid(2) - this entry is no longer valid (e.g., it
   was learned but has since aged out) but has not
                 yet been flushed from the table.
             learned(3) - the information in this entry was learned
                 and is being used.
             self(4) - the value of the corresponding instance of
                 rbridgeFdbAddress represents one of the device's
                 addresses. The corresponding instance of
```

RFC 6850

ports has this address.

rbridgeFdbPort indicates which of the device's

```
mgmt(5) - the value of the corresponding instance of
                  rbridgeFdbAddress was configured by management.
             esadi(6) - the value of the corresponding instance of
                  rbridgeFdbAddress was learned from ESADI.'
    ::= { rbridgeUniFdbEntry 6 }
-- RBridge Forwarding Information Base (FIB)
rbridgeUniFibTable OBJECT-TYPE
              SEQUENCE OF RbridgeUniFibEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
         "A table that contains information about nicknames known by
         the RBridge. If Equal-Cost Multipath (ECMP) is implemented,
         there are as many entries for a nickname as there are ECMP
         paths available for it.'
    ::= { rbridgeFdb 5 }
rbridgeUniFibEntry OBJECT-TYPE
    SŸNTAX
             RbridgeUniFibEntry
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "A list of information about nicknames known by the RBridge.
If ECMP is implemented, there are as many entries as there
are ECMP paths available for a given nickname."
             { rbridgeUniFibNickname, rbridgeUniFibPort,
    INDEX
                rbridgeUniFibNextHop }
    ::= { rbridgeUniFibTable 1 }
RbridgeUniFibEntrv ::=
    SEQUENCE { rbridgeUniFibNickname
             RbridgeNickname,
         rbridgeUniFibPort
             Unsigned32,
         rbridgeUniFibNextHop
             RbridgeNickname,
         rbridgeUniFibHopCount
             Unsigned32
    }
rbridgeUniFibNickname OBJECT-TYPE
    SYNTAX RbridgeNickname MAX-ACCESS not-accessible
```

```
STATUS
                 current
    DESCRIPTION
        "An RBridge nickname for which this RBridge has
        forwarding information."
    ::= { rbridgeUniFibEntry 1 }
rbridgeUniFibPort OBJECT-TYPE
                Unsigned32 (0..65535)
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "The RBridge port number of the port attached to the
    next-hop RBridge for the path towards the RBridge whose
nickname is specified in this entry."
::= { rbridgeUniFibEntry 2 }
rbridgeUniFibNextHop OBJECT-TYPE
                RbridgeNickname
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "The nickname of the next-hop RBridge for the path
        towards the RBridge whose nickname is specified in this
    ::= { rbridgeUniFibEntry 3 }
rbridgeUniFibHopCount OBJECT-TYPE
                Unsigned32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
        "The hop count from this ingress RBridge to the egress
        RBridge whose nickname is specified in
        rbridgeUniFibNickname."
    ::= { rbridgeUniFibEntry 4 }
rbridgeMultiFibTable OBJECT-TYPE
                 SEQUENCE OF RbridgeMultiFibEntry
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                 current
    DESCRIPTION
        "A table that contains information about egress nicknames
        used for multi-destination frame forwarding by this RBridge."
    ::= { rbridgeFdb 6 }
```

```
rbridgeMultiFibEntry OBJECT-TYPE
    SYNTAX
                 RbridgeMultiFibEntry
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
         "A list of information about egress nicknames used for
        multi-destination frame forwarding by this RBridge."

X { rbridgeMultiFibNickname }
    ::= { rbridgeMultiFibTable 1 }
RbridgeMultiFibEntry ::=
    SEQUENCE { rbridgeMultiFibNickname
             RbridgeNickname,
        rbridgeMultiFibPorts
             PortList
    }
rbridgeMultiFibNickname OBJECT-TYPE
    SYNTAX
                 RbridgeNickname
    MAX-ACCESS
                 not-accessible
                 current
    STATUS
    DESCRIPTION
         "The nickname of the multicast distribution tree."
    ::= { rbridgeMultiFibEntry 1 }
rbridgeMultiFibPorts OBJECT-TYPE
                 PortList
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The list of ports to which a frame destined to this
        multicast distribution tree is flooded. This may be pruned
    further based on other forwarding information."
::= { rbridgeMultiFibEntry 2 }
```

```
-- The RBridge VLAN Table
rbridgeVlanTable OBJECT-TYPE
   SYNTAX SEQUENCE OF RbridgeVlanEntry MAX-ACCESS not-accessible
               current
    STATUS
    DESCRIPTION
        "A table that contains information about VLANs on the
        RBridge.'
    ::= { rbridgeVlan 1 }
rbridgeVlanEntry OBJECT-TYPE SYNTAX RbridgeVlanEntry
    MAX-ACCESS not-accessible
    STATUS
               current
    DESCRIPTION
        "A list of information about VLANs on the RBridge."
    INDEX { rbridgeVlanIndex }
::= { rbridgeVlanTable 1 }
RbridgeVlanEntry ::=
    SEQUENCE {
        rbridgeVlanIndex
            Unsigned32,
        rbridgeVlanForwarderLosts
            Counter32,
        rbridgeVlanDisableLearning
            TruthValue,
        rbridgeVlanSnooping
            INTEGER
    }
rbridgeVlanIndex OBJECT-TYPE
               Unsigned32 (1..4094|4096..4294967295)
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
              current
    DESCRIPTION
        "The VLAN-ID referring to this VLAN."
    ::= { rbridgeVlanEntry 1 }
rbridgeVlanForwarderLosts OBJECT-TYPE
    SŸNTAX
               Counter32
                "times"
    UNITS
    MAX-ACCESS read-only
    STATUS current
```

```
DESCRIPTION
         "The number of times this RBridge has lost appointed
         forwarder status for this VLAN on any of its ports.
        Discontinuities in the value of this counter can occur
         at re-initialization of the management system."
    REFERENCE
    "RFC 6325, Section 4.8.3"
::= { rbridgeVlanEntry 2 }
rbridgeVlanDisableLearning OBJECT-TYPE
    SYNTAX
                 TruthValue
    MAX-ACCESS read-write
    STATUS
                  current
    DESCRIPTION
         "Disable learning of MAC addresses seen in this VLAN.
        One application of this may be to restrict learning to ESADI. To disable learning, the value of this object should be set to 'true'. The default is 'false'.
        The value of this object MUST be retained across
         re-initializations of the management system."
    REFERENCE
         "RFC 6325, Section 4.8"
                 { false }
    ::= { rbridgeVlanEntry 3 }
rbridgeVlanSnooping OBJECT-TYPE
                  INTEGER {
    SÝNTAX
                      notSupported(1),
                       ipv4(2),
                      ipv6(3),
                      ipv4v6(4)
    MAX-ACCESS
                  read-only
    STATUS
                  current
    DESCRIPTION
         "IP Multicast Snooping on this VLAN. For RBridges
         performing both IPv4 and IPv6 IP Multicast Snooping, the
         value returned is ipv4v6(4)."
    REFERENCE
         "RFC 6325, Section 4.7"
    ::= { rbridgeVlanEntry 4 }
```

```
-- The RBridge VLAN Port Table
rbridgeVlanPortTable OBJECT-TYPE
    SYNTAX SEQUENCE OF RbridgeVlanPortEntry MAX-ACCESS not-accessible
                current
    STATUS
    DESCRIPTION
        "A table that contains information about VLANs on an RBridge
        port."
    ::= { rbridgeVlan 2 }
rbridgeVlanPortEntry OBJECT-TYPE
    SYNTAX
                RbridgeVlanPortEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "A list of information about VLANs on the RBridge port."
    INDEX { rbridgeBasePort, rbridgeVlanIndex }
::= { rbridgeVlanPortTable 1 }
RbridgeVlanPortEntry ::=
    SEQUENCE {
        rbridgeVlanPortInhibited
            TruthValue,
        rbridgeVlanPortForwarder
            TruthValue,
        rbridgeVlanPortAnnouncing
            TruthValue,
        rbridgeVlanPortDetectedVlanMapping
            TruthValue
    }
rbridgeVlanPortInhibited OBJECT-TYPE
             TruthValue
    SYNTAX
    MAX-ACCESS read-only
               current
    STATUS
    DESCRIPTION
        "This VLAN has been inhibited by the RBridge due to
        conflicting forwarder information received from another
        RBridge, when the value of this object is 'true'."
    REFERENCE
        "RFC 6325, Section 4.2.4.3"
    ::= { rbridgeVlanPortEntry 1 }
rbridgeVlanPortForwarder OBJECT-TYPE
```

SYNTAX TruthValue

```
MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "This RBridge is an appointed forwarder for this VLAN
        on this port, when the value of this object is 'true'."
    REFERENCE
    "RFC 6325, Section 4.2.4.3"
::= { rbridgeVlanPortEntry 2 }
rbridgeVlanPortAnnouncing OBJECT-TYPE
              TruthValue
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "TRILL-Hellos tagged with this VLAN can be sent by this
        RBridge on this port, when the value of this object
        is 'true'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
    "RFC 6325, Section 4.4.3" DEFVAL { true }
    ::= { rbridgeVlanPortEntry 3 }
rbridgeVlanPortDetectedVlanMapping OBJECT-TYPE
    SYNTAX
             TruthValue
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "VLAN mapping has been detected on the link attached
        to this port, when the value of this object is 'true'."
    REFERENCE
    "RFC 6325, Section 4.4.5"
::= { rbridgeVlanPortEntry 4 }
-- The RBridge Port Counter Table
-- These counters supplement counters in the Bridge MIB.
-- For example, total frames received by a bridge port and total
-- frames transmitted by a bridge port are reported in the
-- Port In Frames and Port Out Frames counters of the Bridge MIB.
-- These total bridge frame counters include native as well as
-- encapsulated frames.
```

```
-- As another example, frames discarded due to excessive frame
-- size are reported in the port counter MTU Exceeded Discards
-- in the Bridge MIB.
rbridgePortCounterTable OBJECT-TYPE SYNTAX SEQUENCE OF RbridgePortCounterEntry
    SYNTAX SEQUENCE OF Rbi
MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
         "A table that contains per-port counters for this RBridge."
    ::= { rbridgeCounter 1 }
rbridgePortCounterEntry OBJECT-TYPE
    SYNTAX
               RbridgePortCounterEntry
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "Counters for a port on this RBridge."
    INDEX { rbridgeBasePort }
::= { rbridgePortCounterTable 1 }
RbridgePortCounterEntry ::=
    SEQUENCE {
        rbridgePortRpfCheckFails
             Counter32,
        rbridgePortHopCountExceeds
             Counter32,
        rbridgePortOptionDrops
        Counter32, rbridgePortTrillInFrames
        Counter64, rbridgePortTrillOutFrames
             Counter64
    }
rbridgePortRpfCheckFails OBJECT-TYPE
    SŶNTAX
                 Counter32
                 "frames"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The number of times a multi-destination frame was
        dropped on this port because the Reverse Path Forwarding
        (RPF) check failed.
        Discontinuities in the value of this counter can occur
        at re-initialization of the management system, and at
```

```
other times as indicated by the value of the
        ifCounterDiscontinuityTime object of the associated
        interface."
   REFERENCE
        "RFC 6325, Section 4.5.2"
    ::= { rbridgePortCounterEntry 1 }
rbridgePortHopCountExceeds OBJECT-TYPE
   SYNTAX
                Counter32
                "frames"
   UNITS
   MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION
        "The number of times a frame was dropped on this port
        because its hop count was zero.
       Discontinuities in the value of this counter can occur
        at re-initialization of the management system, and at
        other times as indicated by the value of the
        ifCounterDiscontinuityTime object of the associated
        interface."
   REFERENCE
        "RFC 6325, Section 3.6"
    ::= { rbridgePortCounterEntry 2 }
rbridgePortOptionDrops OBJECT-TYPE
                Counter32
   SYNTAX
                "frames"
   UNITS
   MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION
        "The number of times a frame was dropped on this port
        because it contained unsupported options.
       Discontinuities in the value of this counter can occur
        at re-initialization of the management system, and at
       other times as indicated by the value of the
        ifCounterDiscontinuityTime object of the associated
        interface."
   REFERENCE
        "RFC 6325, Section 3.5"
    ::= { rbridgePortCounterEntry 3 }
rbridgePortTrillInFrames OBJECT-TYPE
   SYNTAX
                Counter64
                "frames"
   UNITS
   MAX-ACCESS read-only
   STATUS
               current
```

```
DESCRIPTION
         "The number of TRILL-encapsulated frames that have been
         received by this port from its attached link, including
         management frames.
         Discontinuities in the value of this counter can occur
        at re-initialization of the management system, and at other times as indicated by the value of the ifCounterDiscontinuityTime object of the associated
         interface."
    REFERENCE
         "RFC 6325, Section 2.3"
    ::= { rbridgePortCounterEntry 4 }
rbridgePortTrillOutFrames OBJECT-TYPE
    SYNTAX Counter64
                  "frames'
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
        "The number of TRILL-encapsulated frames that have been transmitted by this port to its attached link, including
         management frames.
         Discontinuities in the value of this counter can occur
         at re-initialization of the management system, and at
         other times as indicated by the value of the
         ifCounterDiscontinuityTime object of the associated
         interface."
    REFERENCE
         "RFC 6325, Section 2.3"
    ::= { rbridgePortCounterEntry 5 }
-- The RBridge VLAN ESADI Table
rbridgeEsadiTable OBJECT-TYPE
    SYNTAX SEQUENCE OF RbridgeEsadiEntry
    MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "A table that contains information about ESADI instances on
         VLANs, if available."
    REFERENCE
    "RFC 6325, Section 4.2.5" ::= { rbridgeEsadi 1 }
```

```
rbridgeEsadiEntry OBJECT-TYPE
    SYNTAX
                RbridgeEsadiEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "Information about an ESADI instance on a VLAN."
    INDEX { rbridgeVlanIndex }
::= { rbridgeEsadiTable 1 }
RbridgeEsadiEntry ::=
    SEQUENCE {
        rbridgeEsadiEnable
            TruthValue,
        rbridgeEsadiConfidence
            Unsigned32,
        rbridgeEsadiDrbPriority
            Unsigned32,
        rbridgeEsadiDrb
            RbridgeAddress,
        rbridgeEsadiDrbHoldingTime
            Unsigned32,
        rbridgeEsadiRowStatus
            RowStatus
    }
rbridgeEsadiEnable OBJECT-TYPE
              TruthValue
    SYNTAX
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
        "If the RBridge is participating in an ESADI instance for
        this VLAN, the value of this object is 'true'. To disable
        participation, set it to 'false'.
        The value of this object MUST be retained across
        re-initializations of the management system."
    REFERENCE
        "RFC 6325, Section 4.2.5"
                { true }
    DEFVAL
    ::= { rbridgeEsadiEntry 1 }
rbridgeEsadiConfidence OBJECT-TYPE
                Unsigned32 (0..255)
    SYNTAX
    MAX-ACCESS
                read-create
    STATUS
                current
    DESCRIPTION
```

"Confidence level of address entries sent by this

ESADI instance. The default is 16.

```
The value of this object MUST be retained across
        re-initializations of the management system.'
   REFERENCE
        "RFC 6325, Section 4.2.5"
AL { 16 }
   DEFVAL
    ::= { rbridgeEsadiEntry 2 }
rbridgeEsadiDrbPriority OBJECT-TYPE
                Unsigned32 (0..127)
   SYNTAX
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "The priority of this RBridge for being selected as the
        DRB for this ESADI instance.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.2.5"
    ::= { rbridgeÉsadiEntry 3 }
rbridgeEsadiDrb OBJECT-TYPE
   SŸNTAX
                RbridgeAddress
   MAX-ACCESS
               read-only
   STATUS
                current
   DESCRIPTION
        "The DRB on this ESADI instance's virtual link."
   REFERENCE
        "RFC 6325, Section 4.2.5"
    ::= { rbridgeEsadiEntry 4 }
rbridgeEsadiDrbHoldingTime OBJECT-TYPE
                Unsigned32 (0..127)
   SYNTAX
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "The holding time for this ESADI instance.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.2.5"
    ::= { rbridgeÉsadiEntry 5 }
rbridgeEsadiRowStatus OBJECT-TYPE
   SYNTAX
                RowStatus
   MAX-ACCESS
               read-create
   STATUS
                current
```

```
DESCRIPTION
         "This object indicates the status of the entry."
    ::= { rbridgeEsadiEntry 6 }
-- The RBridge IP Multicast Snooping Port Table
rbridgeSnoopingPortTable OBJECT-TYPE
                 SEQUENCE OF RbridgeSnoopingPortEntry
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
        "For RBridges implementing IP Multicast Snooping, information about ports on which the presence of IPv4
        or IPv6 multicast routers has been detected.'
    REFERENCE
        "RFC 6325, Section 4.7"
    ::= { rbridgeSnooping 1 }
rbridgeSnoopingPortEntry OBJECT-TYPE
    SŸNTAX
                 RbridgeSnoopingPortEntry
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
        "Information about ports on which the presence of IPv4
        or IPv6 multicast routers has been detected for a
        VLAN."
            { rbridgeBasePort, rbridgeVlanIndex }
    INDEX
    ::= { rbridgeSnoopingPortTable 1 }
RbridgeSnoopingPortEntry ::=
    SEQUENCE {
        rbridgeSnoopingPortAddrType
             INTEGER
    }
rbridgeSnoopingPortAddrType OBJECT-TYPE
    SYNTAX
                 INTEGER {
                     ipv4(1),
                     ipv6(2)
                     ipv4v6(3)
```

MAX-ACCESS

DESCRIPTION

STATUS

read-only current

"The IP address type of an IP multicast router detected

```
on this port and VLAN. If only IPv4 router(s)
        are detected, the value returned is 'ipv4'. If only
        IPv6 routers are detected, the value returned is 'ipv6'. If both IPv4 and IPv6 routers are detected on
        this port and VLAN, the value returned is 'ipv4v6'.'
    REFERENCE
        "RFC 6325, Section 4.7"
    ::= { rbridgeSnoopingPortEntry 1 }
-- The RBridge IP Multicast Snooping Address Table
rbridgeSnoopingAddrTable OBJECT-TYPE
SYNTAX SEQUENCE OF RbridgeSnoopingAddrEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "For RBridges implementing IP Multicast Snooping,
        information about IP multicast addresses being
        snooped."
    REFERENCE
        "RFC 6325, Section 4.8"
    ::= { rbridgeSnooping 2 }
rbridgeSnoopingAddrEntry OBJECT-TYPE
    SYNTAX
                RbridgeSnoopingAddrEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        'Information about IP multicast addresses being
        snooped."
    INDEX { rbridgeVlanIndex, rbridgeSnoopingAddrType,
             rbridgeSnoopingAddr }
    ::= { rbridgeSnoopingAddrTable 1 }
RbridgeSnoopingAddrEntry ::=
    SEQUENCE {
        rbridgeSnoopingAddrType
            InetAddressType,
        rbridgeSnoopingAddr
            InetAddress,
        rbridgeSnoopingAddrPorts
            PortList
    }
rbridgeSnoopingAddrType OBJECT-TYPE
                InetAddressType
    SYNTAX
```

RFC 6850

```
MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "The IP multicast address type for which a listener has been detected by this RBridge. This MIB requires support for only
         IPv4 and IPv6 address types."
    REFERENCE
         "RFC 6325, Section 4.7"
    ::= { rbridgeSnoopingAddrEntry 1 }
rbridgeSnoopingAddr OBJECT-TYPE
                  InetAddress
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "The IP multicast address for which a listener has been
         detected by this RBridge. The address type of this object
         is specified in rbridgeSnoopingAddrType. This MIB requires
         support for only global IPv4 and IPv6 addresses, so the length of the object can be either 4 or 16 bytes. Hence,
         the index will not exceed the OID size limit.
    REFERENCE
         "RFC 6325, Section 4.7"
    ::= { rbridgeSnoopingAddrEntry 2 }
rbridgeSnoopingAddrPorts OBJECT-TYPE
                 PortList
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                  current
    DESCRIPTION
         "The set of ports on which a listener has been detected for this IP multicast address."
    REFERENCE
         "RFC 6325, Section 4.7"
    ::= { rbridgeSnoopingAddrEntry 3 }
-- Distribution Trees
rbridgeDtreePriority OBJECT-TYPE
    SYNTAX
                  Unsigned32 (1..65535)
    MAX-ACCESS read-write
    STATUS
                  current
    DESCRIPTION
         "The distribution tree root priority for this RBridge.
```

```
The default value of this object is 32768.
        The value of this object MUST be retained across
        re-initializations of the management system."
   REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtree 1 }
rbridgeDtreeActiveTrees OBJECT-TYPE
   SYNTAX
               Unsigned32
   MAX-ACCESS
               read-only
   STATUS
                current
   DESCRIPTION
        "The total number of trees being computed by all RBridges
        in the campus."
   REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtree 2 }
rbridgeDtreeMaxTrees OBJECT-TYPE
                Unsigned32
   SYNTAX
   MAX-ACCESS
               read-only
   STATUS
               current
   DESCRIPTION
        "The maximum number of trees this RBridge can compute."
   REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtree 3 }
rbridgeDtreeDesiredUseTrees OBJECT-TYPE
   SYNTAX
               Unsigned32
   MAX-ACCESS
               read-only
   STATUS
                current
   DESCRIPTION
        "The maximum number of trees this RBridge would like to
        use for transmission of ingress multi-destination frames."
   REFERENCE
        "RFC 6325. Section 4.5"
    ::= { rbridgeDtree 4 }
rbridgeDtreeTable OBJECT-TYPE
   SYNTAX
              SEQUENCE OF RbridgeDtreeEntry
   MAX-ACCESS not-accessible
   STATUS
                current
   DESCRIPTION
        "Information about distribution trees being computed
        by this RBridge."
```

```
REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtree 5 }
rbridgeDtreeEntry OBJECT-TYPE
    SYNTAX
                RbridgeDtreeEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "List of information about distribution trees being computed
        by this RBridge."
    INDEX { rbridgeDtreeNumber }
    ::= { rbridgeDtreeTable 1 }
RbridgeDtreeEntry ::=
    SEQUENCE {
        rbridgeDtreeNumber
            Unsigned32,
        rbridgeDtreeNickname
            RbridgeNickname,
        rbridgeDtreeIngress
            TruthValue
    }
rbridgeDtreeNumber OBJECT-TYPE
                Unsigned32 (0..65535)
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "The tree number of a distribution tree being computed by
        this RBridge."
    REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtreeEntry 1 }
rbridgeDtreeNickname OBJECT-TYPE
                RbridgeNickname
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The nickname of the distribution tree."
    REFERENCE
        "RFC 6325, Section 4.5"
    ::= { rbridgeDtreeEntry 2 }
rbridgeDtreeIngress OBJECT-TYPE
                TruthValue
    SŸNTAX
    MAX-ACCESS read-only
```

```
current
   STATUS
   DESCRIPTION
        "Indicates whether this RBridge might choose this
       distribution tree to ingress a multi-destination frame."
   REFERENCE
       "RFC 6325, Section 4.5"
    ::= { rbridgeDtreeEntry 3 }
-- TRILL Neighbor List
rbridgeTrillMinMtuDesired OBJECT-TYPE
   SYNTAX
           Unsigned32
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION
       "The desired minimum acceptable inter-RBridge link MTU for
       the campus, that is, originatingLSPBufferSize.
       The value of this object MUST be retained across
       re-initializations of the management system."
   REFERENCE
       "RFC 6325, Section 4.3"
    ::= { rbridgeTrill 1 }
rbridgeTrillSz OBJECT-TYPE
   SYNTAX
              Unsigned32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
       "The minimum acceptable inter-RBridge link size for the
       campus for the proper operation of TRILL IS-IS.
   REFERENCE
    "RFC 6325, Section 4.3" ::= { rbridgeTrill 2 }
rbridgeTrillMaxMtuProbes OBJECT-TYPE
   SÝNTAX Unsigned32 (1..255)
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION
        'The number of failed MTU-probes before the RBridge
       concludes that a particular MTU is not supported by
       a neighbor.
```

The value of this object MUST be retained across re-initializations of the management system.' REFERENCE "RFC 6325, Section 4.3" ::= { rbridgeTrill 3 } rbridgeTrillNbrTable OBJECT-TYPE SEQUENCE OF RbridgeTrillNbrEntry SYNTAX MAX-ACCESS not-accessible STATUS current **DESCRIPTION** "Information about this RBridge's TRILL neighbors." REFERENCE "RFC 6325, Section 4.4.2.1" ::= { rbridgeTrill 4 } rbridgeTrillNbrEntry OBJECT-TYPE RbridgeTrillNbrEntry SYNTAX MAX-ACCESS not-accessible STATUS current **DESCRIPTION** "List of information about this RBridge's TRILL neighbors." INDEX { rbridgeTrillNbrMacAddr } ::= { rbridgeTrillNbrTable 1 } RbridgeTrillNbrEntry ::= SEQUENCE { rbridgeTrillNbrMacAddr MacAddress, rbridgeTrillNbrMtu Unsigned32, rbridgeTrillNbrFailedMtuTest TruthValue } rbridgeTrillNbrMacAddr OBJECT-TYPE **MacAddress** SYNTAX MAX-ACCESS not-accessible STATUS current **DESCRIPTION** "The MAC address of a neighbor of this RBridge." REFERENCE "RFC 6325, Section 4.4.2.1"

SYNTAX

::= { rbridgeTrillNbrEntry 1 }

Unsigned32

rbridgeTrillNbrMtu OBJECT-TYPE

MAX-ACCESS read-only

```
STATUS
                 current
    DESCRIPTION
         "MTU size for this neighbor for IS-IS communication
         purposes."
    REFERENCE
         "RFC 6325, Section 4.3.2"
    ::= { rbridgeTrillNbrEntry 2 }
rbridgeTrillNbrFailedMtuTest OBJECT-TYPE
               TruthValue
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
         "If true, indicates that the neighbor's tested MTU is less
        than the minimum acceptable inter-bridge link MTU for the
         campus (1470)."
    REFERENCE
         "RFC 6325, Section 4.3.1"
    ::= { rbridgeTrillNbrEntry 3 }
-- Notifications for use by RBridges
rbridgeBaseNewDrb NOTIFICATION-TYPE
    -- OBJECTS { }
    STATUS
                 current
    DESCRIPTION
         'The rbridgeBaseNewDrb notification indicates that the
         sending agent has become the new Designated RBridge; the
    notification is sent by an RBridge soon after its election as the new DRB root, e.g., upon expiration of the Topology Change Timer, immediately subsequent to its election."

::= { rbridgeNotifications 1 }
rbridgeBaseTopologyChange NOTIFICATION-TYPE
    -- OBJECTS
                   { }
                 current
    STATUS
    DESCRIPTION
         "The rbridgeBaseTopologyChange notification is sent by an
        RBridge when any of its configured ports transition to/from
         the VLAN-x designated forwarder. The notification is not
        sent if an rbridgeBaseNewDrb notification is sent for the
         same transition.
    ::= { rbridgeNotifications 2 }
```

-- Compliance and Group sections rbridgeCompliances OBJECT IDENTIFIER ::= { rbridgeConformance 1 } OBJECT IDENTIFIER ::= { rbridgeConformance 2 } rbridgeGroup -- Units of Conformance rbridgeBaseGroup OBJECT-GROUP OBJECTS { rbridgeBaseTrillVersion. rbridgeBaseNumPorts, rbridgeBaseForwardDelay, rbridgeBaseUniMultipathÉnable, rbridgeBaseMultiMultipathEnable, rbridgeBaseAcceptEncapNonadj, rbridgeBaseNicknameNumber **STATUS** current **DESCRIPTION** "A collection of objects providing basic control and status information for the RBridge.' ::= { rbridgeGroup 1 } rbridgeBaseNicknameGroup OBJECT-GROUP OBJECTS { rbridgeBaseNicknamePriority, rbridgeBaseNicknameDtrPriority, rbridgeBaseNicknameType, rbridgeBaseNicknameRowStatus **STATUS** current **DESCRIPTION** "A collection of objects providing basic control and status information for RBridge nicknames." ::= { rbridgeGroup 2 } rbridgeBasePortGroup OBJECT-GROUP OBJECTS { rbridgeBasePortIfIndex, rbridgeBasePortDisable, rbridgeBasePortTrunkPort rbridgeBasePortAccessPort,

rbridgeBasePortP2pHellos, rbridgeBasePortState.

```
rbridgeBasePortDesiredDesigVlan,
        rbridgeBasePortDesigVlan,
        rbridgeBasePortInhibitionTime,
        rbridgeBasePortDisableLearning,
        rbridgeBasePortStpRoot,
        rbridgeBasePortStpRootChanges,
        rbridgeBasePortStpWiringCloset
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing basic control
        and status information for RBridge ports."
    ::= { rbridgeGroup 3 }
rbridgeFdbGroup OBJECT-GROUP
    OBJECTS {
        rbridgeConfidenceNative.
        rbridgeConfidenceDecap,
        rbridgeConfidenceStatic,
        rbridgeUniFdbPort,
        rbridgeUniFdbNickname,
        rbridgeUniFdbConfidence,
        rbridgeUniFdbStatus
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information about the Unicast Address Database."
    ::= { rbridgeGroup 4 }
rbridgeFibGroup OBJECT-GROUP
    OBJECTS {
        rbridgeUniFibHopCount,
        rbridgeMultiFibPorts
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information
        about the Unicast and Multicast FIBs."
    ::= { rbridgeGroup 5 }
rbridgeVlanGroup OBJECT-GROUP
    OBJECTS {
        rbridgeVlanForwarderLosts,
        rbridgeVlanDisableLearning,
        rbridgeVlanSnooping,
        rbridgeVlanPortInhibited,
        rbridgeVlanPortForwarder,
```

```
rbridgeVlanPortAnnouncing,
        rbridgeVlanPortDetectedVlanMapping
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information
        about VLANs on the RBridge."
    ::= { rbridgeGroup 6 }
rbridgePortCounterGroup OBJECT-GROUP
    OBJECTS {
        rbridgePortRpfCheckFails,
        rbridgePortHopCountExceeds,
        rbridgePortOptionDrops,
        rbridgePortTrillInFrames,
        rbridgePortTrillOutFrames
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing per-port counters for the RBridge."
    ::= { rbridgeGroup 7 }
rbridgeEsadiGroup OBJECT-GROUP
    OBJECTS {
        rbridgeEsadiEnable,
        rbridgeEsadiConfidence,
        rbridgeEsadiDrbPriority.
        rbridgeEsadiDrb,
        rbridgeEsadiDrbHoldingTime,
        rbridgeEsadiRowStatus
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information
        about ESADI instances on the RBridge."
    ::= { rbridgeGroup 8 }
rbridgeSnoopingGroup OBJECT-GROUP
    OBJECTS {
        rbridgeSnoopingPortAddrType,
        rbridgeSnoopingAddrPorts
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information about
        IP Multicast Snooping. This MIB requires support for
        only global IPv4 and IPv6 address types in
```

```
rbridgeSnoopingPortAddrType and rbridgeSnoopingAddrType.
        so the length of rbridgeSnoopingAddr can be either 4 or
        16 bytes.
    ::= { rbridgeGroup 9 }
rbridgeDtreeGroup OBJECT-GROUP
    OBJECTS { rbridgeDtreePriority,
        rbridgeDtreeActiveTrees,
        rbridgeDtreeMaxTrees,
        rbridgeDtreeDesiredUseTrees,
        rbridgeDtreeNickname,
        rbridgeDtreeIngress
    STATUS
                current
    DESCRIPTION
        "A collection of objects providing information
        about distribution trees.
    ::= { rbridgeGroup 10 }
rbridgeTrillGroup OBJECT-GROUP
   OBJECTS { rbridgeTrillMinMtuDesired,
        rbridgeTrillSz,
        rbridgeTrillMaxMtuProbes.
        rbridgeTrillNbrMtu,
        rbridgeTrillNbrFailedMtuTest
   }
STATUS
                current
    DESCRIPTION
        "A collection of objects providing information
        about TRILL neighbors."
    ::= { rbridgeGroup 11 }
rbridgeNotificationGroup NOTIFICATION-GROUP
    NOTIFICATIONS {
        rbridgeBaseNewDrb,
        rbridgeBaseTopologyChange
    STATUS
                current
    DESCRIPTION
        "A collection of objects describing notifications (traps)."
    ::= { rbridgeGroup 12 }
```

-- Compliance Statement rbridgeCompliance MODULE-COMPLIANCE STATUS current **DESCRIPTION** "The compliance statement for support of RBridge services." MODULE MANDATORY-GROUPS { rbridgeBaseGroup, rbridgeBaseNicknameGroup, rbridgeBasePortGroup, rbridgeFdbGroup, rbridgeFibGroup, rbridgeVlanGroup, rbridgeDtreeGroup, rbridgeTrillGroup, rbridgeNotificationGroup } **GROUP** rbridgePortCounterGroup DESCRIPTION "Implementation of this group is optional." GROUP rbridgeEsadiGroup **DESCRIPTION** "Implementation of this group is optional." rbridgeSnoopingGroup GROUP **DESCRIPTION** "Implementation of this group is optional." ::= { rbridgeCompliances 1 } rbridgeReadOnlyCompliance MODULE-COMPLIANCE STATUS current **DESCRIPTION** "When this MIB is implemented in read-only mode, then

the implementation can claim read-only compliance. In that case, RBridge objects can be monitored but cannot be configured with this implementation.'

```
MODULE
   MANDATORY-GROUPS {
        rbridgeBaseGroup,
        rbridgeBaseNicknameGroup,
        rbridgeBasePortGroup,
        rbridgeFdbGroup,
        rbridgeFibGroup,
        rbridgeVlanGroup,
        rbridgeDtreeGroup,
        rbridgeTrillGroup,
        rbridgeNotificationGroup
    }
OBJECT rbridgeBaseForwardDelay
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeBaseUniMultipathEnable
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeBaseMultiMultipathEnable
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeBaseAcceptEncapNonadj
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeBaseNicknameNumber
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeBaseNicknamePriority
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
```

OBJECT rbridgeBaseNicknameDtrPriority

"Write access is not required."

read-only

MIN-ACCESS

DESCRIPTION

OBJECT rbridgeBaseNicknameRowStatus
SYNTAX INTEGER { active(1) }
MIN-ACCESS read-only
DESCRIPTION
 "Write access is not required, and 'active' is the only status that needs to be supported."

OBJECT rbridgeBasePortDisable
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

OBJECT rbridgeBasePortTrunkPort
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

OBJECT rbridgeBasePortAccessPort
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

OBJECT rbridgeBasePortP2pHellos MIN-ACCESS read-only DESCRIPTION "Write access is not required."

OBJECT rbridgeBasePortInhibitionTime
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

OBJECT rbridgeBasePortDisableLearning
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

OBJECT rbridgeBasePortDesiredDesigVlan MIN-ACCESS read-only DESCRIPTION "Write access is not required."

OBJECT rbridgeBasePortStpWiringCloset
MIN-ACCESS read-only
DESCRIPTION
"Write access is not required."

RFC 6850

OBJECT rbridgeConfidenceNative MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

RFC 6850

OBJECT rbridgeConfidenceDecap MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeConfidenceStatic MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeVlanDisableLearning MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeVlanPortAnnouncing MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeEsadiEnable MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeEsadiConfidence MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeEsadiDrbPriority MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

OBJECT rbridgeEsadiDrbHoldingTime MIN-ACCESS read-only **DESCRIPTION** "Write access is not required."

rbridgeEsadiRowStatus OBJECT SYNTAX INTEGER { active(1) } MIN-ACCESS read-only

```
DESCRIPTION
    "Write access is not required, and 'active' is the only
    status that needs to be supported."
OBJECT rbridgeDtreePriority
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeTrillMinMtuDesired
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT rbridgeTrillMaxMtuProbes
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
GROUP
       rbridgePortCounterGroup
DESCRIPTION
    "Implementation of this group is optional."
GROUP
       rbridgeEsadiGroup
DESCRIPTION
    "Implementation of this group is optional."
GROUP rbridgeSnoopingGroup
DESCRIPTION
    "Implementation of this group is optional."
::= { rbridgeCompliances 2 }
```

END

RFC 6850 RBridges: TRILL Base MIB January 2013

8. Security Considerations

This MIB relates to a system that will provide network connectivity and packet-forwarding services. As such, improper manipulation of the objects represented by this MIB may result in denial of service to a large number of end-users.

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write and/or read-create. objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and their sensitivity/vulnerability:

The following tables and objects in the RBRIDGE-MIB can be manipulated to interfere with the operation of RBridges:

- o rbridgeBaseUniMultipathEnable affects the ability of the RBridge to route unicast traffic over multiple paths, and rbridgeBaseMultiMultipathEnable affects the ability of the RBridge to route multi-destination traffic over multiple paths.
- o rbridgeBasePortTable contains a number of objects that may affect network connectivity. Actions that may be triggered by manipulating objects in this table include disabling of an RBridge port, discarding of native packets, disabling learning, and others.
- o rbridgeEsadiTable contains objects that affect the operation of the EŠADI protocol used for learning, and manipulation of the objects contained therein can be used to confuse the learning ability of RBridges.
- o rbridgeDtreePriority can affect computation of distribution trees within an RBridge campus, thereby affecting the forwarding of multi-destination traffic.
- o rbridgeTrillMinMtuDesired can affect the size of packets being used to exchange information between RBridges.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over

the network via SNMP. For example, access to network topology and RBridge attributes can reveal information that should not be available to all users of the network.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPsec), there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

Implementations SHOULD provide the security features described by the SNMPv3 framework (see [RFC3410]), and implementations claiming compliance to the SNMPv3 standard MUST include full support for authentication and privacy via the User-based Security Model (USM) [RFC3414] with the AES cipher algorithm [RFC3826]. Implementations MAY also provide support for the Transport Security Model (TSM) [RFC5591] in combination with a secure transport such as SSH [RFC5592] or TLS/DTLS [RFC6353].

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

For other RBridge security considerations, see [RFC6325].

9. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER value recorded in the SMI Numbers registry:

Descriptor OBJECT IDENTIFIER value rbridgeMIB { mib-2 214 }

10. Contributors

The authors would like to acknowledge the contributions of Donald Eastlake, Radia Perlman, Anoop Ghanwani, Dan Romascanu, Mahesh Akula, Sue Hares, and Joan Cucchiara.

RFC 6850 RBridges: TRILL Base MIB January 2013

11. References

11.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- McCloghrie, K., Ed., Perkins, D., Ed., and J. Schoenwaelder, Ed., "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April 1999. [RFC2578]
- McCloghrie, K., Ed., Perkins, D., Ed., and J. Schoenwaelder, Ed., "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999. [RFC2579]
- McCloghrie, K., Ed., Perkins, D., Ed., and J. Schoenwaelder, Ed., "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999. [RFC2580]
- McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000. [RFC2863]
- Blumenthal, U. and B. Wijnen, "User-based Security Model [RFC3414] (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", STD 62, RFC 3414, December 2002.
- Blumenthal, U., Maino, F., and K. McCloghrie, "The Advanced Encryption Standard (AES) Cipher Algorithm in the SNMP User-based Security Model", RFC 3826, June 2004. [RFC3826]
- Daniele, M., Haberman, B., Routhier, S., and J. Schoenwaelder, "Textual Conventions for Internet Network Addresses", RFC 4001, February 2005. [RFC4001]
- Norseth, K., Ed., and E. Bell, Ed., "Definitions of Managed Objects for Bridges", RFC 4188, September 2005. [RFC4188]
- Levi, D. and D. Harrington, "Definitions of Managed [RFC4363] Objects for Bridges with Traffic Classes, Multicast Filtering, and Virtual LAN Extensions", RFC 4363, January 2006.
- [RFC4444] Parker, J., Ed., "Management Information Base for Intermediate System to Intermediate System (IS-IS)", RFC 4444, April 2006.

- Harrington, D. and W. Hardaker, "Transport Security Model [RFC5591] for the Simple Network Management Protocol (SNMP)", RFC 5591, June 2009.
- Harrington, D., Salowey, J., and W. Hardaker, "Secure Shell Transport Model for the Simple Network Management Protocol (SNMP)", RFC 5592, June 2009. [RFC5592]
- Perlman, R., Eastlake 3rd, D., Dutt, D., Gai, S., and A. Ghanwani, "Routing Bridges (RBridges): Base Protocol [RFC6325] Specification", RFC 6325, July 2011.
- Hardaker, W., "Transport Layer Security (TLS) Transport Model for the Simple Network Management Protocol (SNMP)", RFC 6353, July 2011. [RFC6353]

Informative References 11.2.

- Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", RFC 3410, December 2002. [RFC3410]
- Harrington, D., "Transferring MIB Work from IETF Bridge MIB WG to IEEE 802.1 WG", RFC 4663, September 2006. [RFC4663]
- Touch, J. and R. Perlman, "Transparent Interconnection of [RFC5556] Lots of Links (TRILL): Problem and Applicability Statement", RFC 5556, May 2009.

RFC 6850 RBridges: TRILL Base MIB January 2013

Authors' Addresses

Anil Rijhsinghani Hewlett-Packard 153 Taylor St. Littleton, MA USA

Phone: +1 508 323 1251 EMail: anil@charter.net

Kate Zebrose HW Embedded 26 Josephine Ave. Somerville, MA USA

Phone: +1 617 840 9673

EMail: zebrose@alum.mit.edu