JavaScript is disabled on your browser.



compact1, compact2, compact3

java.lang

# Class AssertionError

java.lang.Object
    java.lang.Throwable
        java.lang.Error
            java.lang.AssertionError

**All Implemented Interfaces:**

Serializable

---

```
public class AssertionError
extends Error
```

Thrown to indicate that an assertion has failed.

The seven one-argument public constructors provided by this class ensure that the assertion error returned by the invocation:

```
new AssertionError(expression)
```

has as its detail message the *string conversion* of *expression* (as defined in section 15.18.1.1 of *The Java™ Language Specification*), regardless of the type of *expression*.

**Since:**

1.4

**See Also:**

Serialized Form

## *Constructor Summary*

**Constructors**

| Constructor | Description |
| --- | --- |
| `AssertionError()` | Constructs an AssertionError with no detail message. |
| `AssertionError(boolean detailMessage)` | Constructs an AssertionError with its detail message derived from the specified `boolean`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| `AssertionError(char detailMessage)` | Constructs an AssertionError with its detail message derived from the specified `char`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| `AssertionError(double detailMessage)` | Constructs an AssertionError with its detail message derived from the specified `double`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| `AssertionError(float detailMessage)` | Constructs an AssertionError with its detail |

| | |
|---|---|
| | message derived from the specified `float`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| **`AssertionError`**`(int detailMessage)` | Constructs an AssertionError with its detail message derived from the specified `int`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| **`AssertionError`**`(long detailMessage)` | Constructs an AssertionError with its detail message derived from the specified `long`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |
| **`AssertionError`**`(`**`Object`**` detailMessage)` | Constructs an AssertionError with its detail message derived from the specified object, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*. |

| | |
|---|---|
| `AssertionError(String message, Throwable cause)` | Constructs a new `AssertionError` with the specified detail message and cause. |

## *Method Summary*

### Methods inherited from class java.lang.Throwable

`addSuppressed`, `fillInStackTrace`, `getCause`, `getLocalizedMessage`, `getMessage`, `getStackTrace`, `getSuppressed`, `initCause`, `printStackTrace`, `printStackTrace`, `printStackTrace`, `setStackTrace`, `toString`

### Methods inherited from class java.lang.Object

`clone`, `equals`, `finalize`, `getClass`, `hashCode`, `notify`, `notifyAll`, `wait`, `wait`, `wait`

## *Constructor Detail*

### AssertionError

```
public AssertionError()
```

Constructs an AssertionError with no detail message.

### AssertionError

```
public AssertionError(Object detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified object, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

If the specified object is an instance of `Throwable`, it becomes the *cause* of the newly constructed assertion error.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

**See Also:**

`Throwable.getCause()`

### AssertionError

```
public AssertionError(boolean detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `boolean`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(char detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `char`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(int detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `int`,

which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(long detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `long`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(float detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `float`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(double detailMessage)
```

Constructs an AssertionError with its detail message derived from the specified `double`, which is converted to a string as defined in section 15.18.1.1 of *The Java™ Language Specification*.

**Parameters:**

`detailMessage - value to be used in constructing detail message`

### AssertionError

```
public AssertionError(String message,
                      Throwable cause)
```

Constructs a new `AssertionError` with the specified detail message and cause.

Note that the detail message associated with `cause` is *not* automatically incorporated in this error's detail message.

**Parameters:**

`message - the detail message, may be null`

`cause - the cause, may be null`

**Since:**

`1.7`



Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.