

EH&S WWI Generation Server and Expert Server Installation

1	SUMM	ARY	3
2	PRE-R	EQUISITES	3
3		NSTALLATION	
	3.1 WV	WI User Creation	3
	3.1.1	Create WWI user account	3
	3.1.2	Privilege 'Logon as a service	4
	3.1.3	DCOM privileges	
	3.2 Ins	talling WWI	
		Up RFC Destination in SAP System	
	3.3.1	Set up RFC Destination for EH&S Management Server	11
	3.3.2	Set Up of RFC Destination for WWI	12
	3.4 Ins	talling WWI Generation Servers As Services	
	3.5 Cu	stomizing of WWI Server in SAP System	16
	3.5.1	Specify Generation Servers	
	3.5.2	Check WWI Destinations and Assign Generation Servers	17
	3.5.3	Job for Document Generation on WWI Server	17
	3.5.4	Apply License	18
4	EH&S	EXPERT INSTALLATION	18
	4.1 Set	up RFC Destination to EHS Expert in SAP	2.2.
		talling EH&S Expert Servers As Services	

1 Summary

This document outlines the detailed steps EH&S WWI and Expert server installation on MS windows platform.

2 Pre-requisites

Processor: ☐ Standard 32 bit, compatible with Microsoft Windows ☐ or 64bit, Microsoft Windows x64 Edition compatible with the WoW64 subsys-tem
Main memory:
□ min. 256 MB (recommended: 512MB or more)
☐ For Microsoft Windows Vista, Server 2008 and later, we recommend 2 GB.
Free hard disk space for the software:
☐ Minimum of 50MB (more during the installation)
☐ Free hard disk space for WWI generation:
☐ 1 GB free memory for temporary files
Operating system:
☐ Microsoft Windows 2000 Professional/Server
☐ Microsoft Windows XP Professional
☐ Microsoft Windows 2003 Server (see Note 703684)
☐ Microsoft Windows Vista (see Note 1012557)
☐ Microsoft Windows Server 2008 (see Note1145085)

Communication:

WWI and Expert communicate with the SAP system via Remote Function Call (RFC). For RFC, the TCP/IP ports 3300 to 3399 are used. You must enable these accordingly.

3 WWI Installation

3.1 WWI User Creation

3.1.1 Create WWI user account

Create a new local user 'WWIUSER' who is a member of the 'Power users' or 'Users' group with a password that does not expire.










3.1.2 Privilege 'Logon as a service

The user must have the 'Log on as a service' authorization




3.1.3 DCOM privileges








3.2 Installing WWI

Execute WWI set up exe:




























Add a new RFC connection:

DEST = EHS_MANSRV_<HOSTNAME>


TYPE = Server


PROGID = EHS_MANSRV_<HOSTNAME>


GWHOST = <HOSTNAME>.<company>.com

GWSERV = sapgw03

MANAGED = 1








vistributed file bystelli	integrates		Marinar	LULA
🌄 Distributed Link Tracking Client	Enables cli	Started	Automatic	Loca
nistributed Link Tracking Server	Enables th		Disabled	Loca
🧠 Distributed Transaction Coordinator	Coordinate	Started	Automatic	Netv
DNS Client	Resolves a	Started	Automatic	Netv
EH&S Administration Management Server		Started	Automatic	Loca
~2°				
Error Reporting Service	Collects, st	Started	Automatic	Loca
Error Reporting Service Event Log	Collects, st Enables ev	Started Started	Automatic Automatic	Loca Loca
Error Reporting Service	•			


3.3 Set Up RFC Destination in SAP System

3.3.1 Set up RFC Destination for EH&S Management Server

RFC Destination EHS_MANSRV_HOSTNAME



3.3.2 Set Up of RFC Destination for WWI




Edit the saprfc.ini file to include:

```
File Edit Format View Help
Cols=200
Lines=400
Delay=20
/* this entry points to TCP/IP-Destination WWI_GENPC1 */
DEST=WWI_GENPC1
PROGID=WWI_GENPC1
TYPE=R
GWHOST=L<HOSTNAME>+COMPANH.COM
GWSERV=sapgwu3
/* this entry points to TCP/IP-Destination WWI_GENPC2 */
; [PC2]
DEST=WWI_GENPC2
PROGID=WWI_GENPC2
TYPE=R
GWHOST=
```

Test the RFC


RFC - Connection Test



3.4 Installing WWI Generation Servers As Services

In SAP system, execute tcode CGSADM


Display Server Services: EHSMANAGEMENTSERVER



Click on 'Install WWI Generation Server'



Display Server Services: EHSMANAGEMENTSERVER



The below entry is added in saprfc.ini file


```
/* this entry points to TCP/IP-Destination EHS_MANSRV */
DEST=EHS_MANSRV_ HOSTAME.
PROGID=EHS_MANSRV_ HOSTAME.
TYPE=R
GWHOST= HOSTAME.COMPANY.COM
GWSERV=sapgw03
MANAGED=1
DEST=WWI_GENPC1_SBE_01
TYPE=R
PROGID=WWT GFNPC1
GWHOST= HOSTAME.COMPANY.COM
GWSERV=sapgw03
RFC_TRACE=0
```

ı


3.5 Customizing of WWI Server in SAP System

3.5.1 Specify Generation Servers

SPRO→




Change View "EHS: Definition of PCs Used for WWI Document Generation":



Activate the WWI server

3.5.2 Check WWI Destinations and Assign Generation Servers



3.5.3 Job for Document Generation on WWI Server


- a) Call the SAP system in the client for which the dispatcher is to be started manually.
- **b**) In the *SAP Easy Access* screen, choose *Tools* \square *ABAP Workbench* \square *Develop-ment* \square *ABAP Editor*. The *ABAP Editor: Initial Screen* appears.
- c) Enter **RC1WWIDS** in the *Program* field.
- d) Choose Execute.

The RC1WWIDS report creates the WWI dispatch process for the corresponding cli-ent.


3.5.4 Apply License


A license is required to operate a WWI generation server. For information about obtaining a license key, see SAP Note 513330


Start program LC_EHS.EXE on the WWI installation directory and enter the company name and license key.





4 EH&S Expert Installation





















4.1 Set up RFC Destination to EHS Expert in SAP




RFC - Connection Test



4.2 Installing EH&S Expert Servers As Services

CGSADM→Click on the server →Click on 'Install EH&S Expert'



Display Server Services: EHSMANAGEMENTSERVER

