2015-02-23

Parameters:

- Number of km driven [0, 800] → 16 bits (needed = 10)
- Duration of the drive [0, 240] → 8 bits
- Number of km/l [0, 30] → 8 bits (needed = 5)
- Number of dl/100km [0, 250] → 8 bits
- Average speed [km/hour] [0, 200] → 8 bits
- Number of dl in the tank [0, 320] → 16 bits (needed = 9)
- Number of drivable km with the available fuel in the tank [max 800] → 16 bits (needed = 10)

Tank fully refilled = 32 l = 320 dl (max each 4 hours)

Initialization: tank full, all parameters equal to Ø

UPDATE DB 3 DUP (?)



When the user select "Enter an update" from the menu, the 3 values are read and put in UPDATE variable.

Needed variables:

KM_DRIVEN	DW	Ø	
DRIVE_DURATION	DB	Ø	; overall duration in minutes
DL_USED	DW	Ø	
L_TANK	DB	32	; liters still in the tank (at the beginning = 32)
AVERAGE_SPEED	DB	Ø	
DURATION_HOUR	DB	Ø	
DURATION_MIN	DB	Ø	
KM_PER_L	DB	Ø	
DL_PER_100KM	DB	Ø	
DRIVABLE_KM	DW	Ø	

ESEMPIO PER LEGGERE NUMERI A PIÙ DI UNA CIFRA

```
; Example of update (all the 3 values - dl, km, m - are read in the same way)
    mov cx, 0          ; read the first digit
    mov ah, 1          <-|
    int 21h
    sub al, '0'
    add cl, al
    int 21h            ; read the second digit
    cmp al, 13         ; compare with new line ascii code...
    je insertkm        ; ... to stop the reading
    sub al, '0'
    mov dl, al
    mov al, 10
    mul cl
    mov cl, al
    add cl, dl
    mov ah, 1
    int 21h            ; read the third digit
    cmp al, 13
    je insertkm
    sub al, '0'
    mov dl, al
    mov al, 10
    mul cl
    mov cl, al
    add cl, dl

insertkm:
    mov UPDATE[0], cl      ; save deciliters
    ...                    ; make the same thing to read kilometers
```

Each time a new update is inserted, all the variables representing the parameters are updated (and also the supporting variables), so, when the user select "display", the program simply prints all those variables. (Variables needed are reported for each item)

```
; ITEM 1
KM_DRIVEN        DW  0          ← Those variables are updated each time a new input is given
DRIVE_DURATION   DB  0                and displayed by request.
DL_USED          DW  0
L_TANK           DB  32

; Assume of having the input in UPDATE variable
; - Compute the overall number of km driven:        UPDATE[1] = kkkkkkkkk
  xor ah, ah
  mov al, UPDATE[1]
  add KM_DRIVEN, ax
; - Compute overall duration (min):                 UPDATE[2] = 00mmmmmm
  mov al, UPDATE[2]
  add DRIVE_DURATION, al
; - Compute the overall decaliters of fuel:         UPDATE[0] = dddddddd
  mov al, UPDATE[0]
  xor ah, ah
  add DL_USED, ax
; - Compute the number of liters still in the tank
; To have the maximun precision, liters still in the tank are computed each time starting from the maximum
  capacity of the tank (320) and the used decaliters of fuel
  MAX = 320 dl
  L_TANK = (MAX - DL_USED) / 10  ⟹  [16 bits] - [16 bits] = [16 bits] ⟹ AL ← RESULT
                                    [8 bits]    [8 bits]    [8 bits]      1_ 8 bits

  mov ax, 320
  sub ax, DL_USED
  mov cl, 10
  div cl
  mov L_TANK, al
```

; ITEM 2

; AVERAGE_SPEED DB 0

You have to use KM_DRIVEN and DRIVE_DURATION variables.

Pay attention: drive duration is stored in minutes, so you have to convert minutes in hours

hours = minutes / 60

$$AVERAGE\_SPEED = \frac{KM\_DRIVEN}{DRIVE\_DURATION / 60} = \frac{KM\_DRIVEN * 60}{DRIVE\_DURATION} \longrightarrow \frac{[32\ bits]}{[16\ bits]} \longrightarrow AX = result$$

(16 bits: KM_DRIVEN * 60; AX: [32 bits] / [16 bits])

8 bits (to be transformed in 16): DRIVE_DURATION

For MAXIMUM PRECISION: FIRST MULTIPLICATE, THEN DIVIDE

Average speed can be represented on 8 bits, so only the content of AL is useful.

```
mov ax, 60
mov cx, KM_DRIVEN
mul cx
mov cl, DRIVE_DURATION
xor ch, ch
div cx
mov AVERAGE_SPEED, al
```

; ITEM 3

; DURATION_HOUR DB 0

DURATION_MIN DB 0

DRIVE_DURATION / 60 ⟶ [16 bits] / [8 bits] ⟹ AL = result (HOURS)

↳ 8 bits (to be tranformed in 16 bits) AH = remainder (MINUTES)

```
xor ah,ah
mov al, DRIVE_DURATION
mov cl, 60
div cl
mov DURATION_HOUR, al
mov DURATION_MIN, ah
```

; ITEM 4

; To compute km/liter you need: KM_DRIVEN (DW) and DL_USED (DW)

The new variable is KM_PER_L DB ∅ (at the beginning)

$$KM\_PER\_L = \frac{KM\_DRIVEN}{DL\_USED / 10} = \frac{KM\_DRIVEN * 10}{DL\_USED} \longrightarrow \frac{[32\ bits]}{[16\ bits]} \longrightarrow AX = result$$

(16 bits: KM_DRIVEN * 10; 16 bits: DL_USED)

(only AL is useful: 8 bits)

To obtain maximum precision: first multiplicate, then divide

```
mov ax, KM_DRIVEN
mov cx, 100
mul cx
mov cx, DL_USED
div cx
mov KM_PER_L, al
```

; ITEM 5

; DL_PER_100KM DB ?

Variables needed: DL_USED (WORD) and KM_DRIVEN

$$DL\_PER\_100KM = \frac{DL\_USED}{KM\_DRIVEN} * 100 = \frac{DL\_USED * 100}{KM\_DRIVEN} \longrightarrow \frac{[32\ bits]}{[16\ bits]} \longrightarrow AX = result$$

(16 bits: DL_USED * 100; 16 bits: KM_DRIVEN)

(only AL contains useful information)

```
mov ax, DL_USED
mov cx, 100
mul cx
mov cx, KM_DRIVEN
div cx
mov DL_PER_100KM, al
```

; ITEM 6

$$\frac{KM\_DRIVEN}{DL\_USED} = \frac{DRIVABLE\_KM}{DL\_AVAILABLE}$$ ← To obtain maximum precision

$$\frac{KM\_DRIVEN * (320 - DL\_USED)}{DL\_USED} \longrightarrow \frac{[32\ bits]}{[16\ bits]} \longrightarrow AX = result$$

```
mov ax, 320
sub ax, DL_USED
mov cx, KM_DRIVEN
mul cx
mov cx, DL_USED
div cx
mov DRIVABLE_KM, ax
```