Fold & Print Card

geniusjunkie.net

The panel layout, both page sizes, and the settings. Verified 2 October 2026.

THE ONE THAT GETS EVERYONE

Rotate the LEFT panel 180° on the sheet

Fold a sheet and the top half flips over — so the left panel becomes the back of the card, upside down.

WRONG — back prints upside down

RIGHT — rotated on the sheet

The INSIDE (page 2) is never rotated — it reads as one spread, left to right.

SIZES

WHAT	METRIC	US EQUIVALENT
Card (finished)	105 x 148 mm (A6)	5.5 x 4.25 in
Sheet you print	210 x 148 mm (A5 landscape)	8.5 x 5.5 in
Margin, all round	10 mm	0.4 in
Fold guide	105 mm — the exact centre	4.25 in

PRINTING

- Export PDF Print (300 DPI). PDF Standard is 96 DPI and this has type on it.
- Double-sided: your printer says "flip on long edge" or "flip on short edge". The names differ by make.
- DO NOT guess it. Print ONE, fold it, look at it. Wrong way up? Change the flip edge, print one more.
- Write the printer and the setting that worked on the back of that test card, in pencil. Keep it.
- Four up: four A6 fronts on an A4 sheet, artwork touching on the shared line, then cut down it.
- Steel rule and a sharp blade, three light passes. Scissors wander.

THE FOLD

Score before you fold. Run the back of a butter knife, or a bone folder, down the centre line against a ruler — you are crushing the fibres in a straight line, not cutting them. Unscored card stock cracks along the spine and you get a white line through the fold. Once it cracks, that card is finished.

A-series figures computed from ISO 216 (A4 = 210 x 297 mm, halved across the long side).