

Steps to Unprovision a LUN

1. Clean up on the Linux host (VERY IMPORTANT)

Before touching storage:

- Stop usage
- Stop applications using the LUN
- Unmount filesystem:
- COMMAND - `umount /mountpoint`

2. Remove from LVM (if used)

- `lvremove /dev/vg_name/lv_name`
- `vgremove vg_name`
- `pvremove /dev/sdb`

3. Remove multipath device (if applicable)

- `multipath -f mpathX (linux )`

4. Delete SCSI device

- COMMAND - `echo 1 > /sys/block/sdb/device/delete`

5. Remove LUN mapping (Unmasking)

- On storage system:

Remove LUN from:

Host / Initiator

Host group / igroup / masking view

- This ensures host cannot see the LUN anymore

6. Remove SAN zoning

- Delete zone or remove WWNN /WWPN from zone in SAN switch

7. Delete LUN from storage

- Now remove it from storage array:
Delete volume / LUN from storage pool
This frees storage space