




NAT overview



Static NAT



Configure Static NAT




```
Router(config)#interface GigabitEthernet 0/1
Router(config-if)#ip address 209.165.201.1 255.255.255.240
Router(config-if)#ip nat outside
Router(config-if)#exit


Router(config)#interface GigabitEthernet 0/0
Router(config-if)#ip address 10.1.1.1 255.255.255.0
Router(config-if)#ip nat inside
Router(config-if)#exit

Router(config)#ip nat inside source static 10.1.1.2 209.165.201.5
```

Dynamic NAT



Configure Dynamic NAT




```
Router(config)#access-list 1 permit 10.1.1.0 0.0.0.255
Router(config)#ip nat pool NAT-POOL 209.165.201.5 209.165.201.10 netmask
255.255.255.240

Router(config)#interface GigabitEthernet 0/1
Router(config-if)#ip address 209.165.201.1 255.255.255.240
Router(config-if)#ip nat outside
Router(config-if)#exit

Router(config)#interface GigabitEthernet 0/0
Router(config-if)#ip address 10.1.1.1 255.255.255.0
Router(config-if)#ip nat inside
Router(config-if)#exit


Router(config)#ip nat inside source list 1 pool NAT-POOL
```



```
Router#show ip nat translations
```


Pro	Inside global	Inside local	Outside local	Outside global
icmp	209.165.201.5:3	10.1.1.100:3	209.165.202.155:3	209.165.202.155:3
---	209.165.201.5	10.1.1.100	---	---
icmp	209.165.201.6:1	10.1.1.101:1	209.165.201.125:1	209.165.201.125:1
tcp	209.165.201.6:1030	10.1.1.101:1030	209.165.201.125:23	209.165.201.125:23
---	209.165.201.6	10.1.1.101	---	---

PAT(Port Address Translation)



Protocol	Inside Local IPv4 Address	Inside Global IPv4 Address	Outside Global IPv4 Address
TCP	10.1.1.100:1723	209.165.201.5:1723	209.165.202.131:23
TCP	10.1.1.101:1927	209.165.201.5:1927	209.165.202.132:23
TCP	10.1.1.101:1723	209.165.201.5:1724	209.165.202.131:23


PAT(Port Address Translation)



```
Router(config)#access-list 1 permit 10.1.1.0 0.0.0.255
Router(config)#interface GigabitEthernet 0/0
Router(config-if)#ip address 10.1.1.1 255.255.255.0
Router(config-if)#ip nat inside

Router(config-if)#interface GigabitEthernet 0/1
Router(config-if)#ip address 209.165.201.1 255.255.255.240
Router(config)#ip nat outside

Router(config)#ip nat inside source list 1 interface Gi 0/1 overload
```

```
Router#show ip nat translations
```

Pro	Inside global	Inside local	Outside local	Outside global
tcp	209.165.201.5:27497	10.1.1.100:27497	209.165.202.155:80	
	209.165.202.155:80			
tcp	209.165.201.5:2597	10.1.1.100:2597	209.165.201.125:443	
	209.165.201.125:443			