Dynamic Trunk Protocol(DTP)

⊙ Switchport Mode

	Dynamic Auto	Dynamic Desirable	Trunk	Access
Dynamic Auto	Access	Trunk	Trunk	Access
Dynamic Desirable	Trunk	Trunk	Trunk	Access
Trunk	Trunk	Trunk	Trunk	Not recommended
Access	Access	Access	Not recommended	Access

- show dtp interface - DTP 동작확인

802.1Q Trunk Configuration

```
Switch(config)#interface fastethernet 5/8

Switch(config-if)#shutdown

Switch(config-if)#switchport trunk encapsulation dot1q

Switch(config-if)#switchport trunk allowed vlan 1,5,11,1002-1005

Switch(config-if)#switchport mode trunk

Switch(config-if)#switchport trunk native vlan 99

Switch(config-if)#switchport nonegotiate

Switch(config-if)#no shutdown
```

802.1Q Configuration 확인

Switch#show running-config interface {fastethernet | gigabitethernet} *slot/port*

Switch#show interfaces [fastethernet | gigabitethernet] *slot/port* [switchport | trunk]

Switch#show interfaces fastEthernet 5/8 switchport
Name: fa5/8
Switchport: Enabled
Administrative Mode: trunk
Operational Mode: trunk
Administrative Trunking Encapsulation: dot1q
Operational Trunking Encapsulation: dot1q
Negotiation of Trunking: Off
Access Mode VLAN: 1 (default)
Trunking Native Mode VLAN: 99 (trunk_only)
Trunking VLANs Enabled: 1,5,11,1002-1005
Pruning VLANs Enabled: 2-1001