TCS CORPORATE WEBSITE

TCS Header — Authoring Guide

Role / audience	Authoring — Content authors, content managers, AEM authoring leads
Version	1.0
Status	Draft for review
Owner	Content Lead / AEM Authoring Lead (proposed)
Last validated	2026-11-13
Documents	1
Classification	INTERNAL — classification to be confirmed

Generated from the Markdown sources of docs/handover (branch migrated-page-content-edam); do not edit this PDF.

Contents

TCS Header — Authoring Guide
- Where to see it
- For Content Authors
- Authorable Fields
- Screenshot-Based Authoring Steps
- Variations
- Complete Authoring Example
- Content and Asset Guidelines
- Troubleshooting
- Screenshots
- Known limitations
- Open items
- Change history

TCS Header — Authoring Guide

Attribute	Value
Document ID	AUT-C-tcs-header
Audience	Content authors, content managers, AEM authoring leads
Purpose	How to add, fill in and check the TCS Header component
Scope	—
Prerequisites	—
Owner	Content Lead / AEM Authoring Lead (proposed)
Approver	Product Owner (to be confirmed)
Version	1.0
Status	Draft for review
Last updated	13 November 2026
Last validated	13 November 2026
Source files	blocks/tcs-header/README.md, blocks/tcs-header/_tcs-header.json
Related documents	—
Related AEM paths	—

1. Where to see it

No block library page.

2. For Content Authors

1. **Open the Navigation page** (`references/nav` of the locale, or the area's nav page) in Universal Editor.
2. **Add the block** to the first section: section › Add › **TCS Header** (offered in every section).
3. **Open its properties** (select the block, Properties panel).
4. **Content tab:** select the TCS Logo asset, enter TCS Logo Alt Text, choose the TCS Logo Link (the locale Home); select the TATA Logo, enter TATA Logo Alt Text, enter the TATA Logo Link (`https://www.tata.com`). Optional: Menu root path and Menu depth (tablet / mobile menu); **Header over the first block** (every width): Auto (default: over an opening light Hero), Always (over any first block, which starts at the top of the page; give a block other than a Hero a Padding top so its content clears the logos), Never (the page starts below the header).
5. **Additional tab** (optional): Anchor ID, Hide block, padding and margin. On the Navigation page they have no effect in the site header.
6. **Preview** the nav page and a content page using it (desktop, tablet, mobile).
7. **Publish** the Navigation page and the logo assets.
8. **Validate** on the published site: both logos show, link to the right pages and are announced by their alt texts.

Minimum required: one logo image or one link. Recommended: both images (transparent SVG), both alt texts and both links. Optional: the Additional tab.

3. Authorable Fields

TCS Header (`tcs-header`)

Model `tcs-header`; template name "TCS Header" (the block class AEM renders); key-value block (one row per property).

Content tab — TCS Header

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
TCS Logo	`tcsLogo`	reference	No	—	—	—	/content/dam/tcs-corp/block-library/header/tcs-logo.png
TCS Logo Alt Text	`tcsLogoAlt`	text	No	`Tata Consultancy Services`	—	Names the logo link for screen readers. Delivered with `tcsLogo` (field collapse).	Tata Consultancy Services
TCS Logo Link	`tcsLogoLink`	aem-content	No	—	—	Usually the locale Home page.	/design-block-master/en/curated-design-pages/home
TATA Logo	`tataLogo`	reference	No	—	—	—	/content/dam/tcs-corp/block-library/header/tata-logo.png
TATA Logo Alt Text	`tataLogoAlt`	text	No	`TATA Group`	—	Names the logo link for screen readers. Delivered with `tataLogo` (field collapse).	TATA Group
TATA Logo Link	`tataLogoLink`	aem-content	No	—	—	Usually https://www.tata.com/.	https://www.tata.com
Header over the first block	`headerOverlay`	select	No	""	Auto (over a light Hero) (""), Always (over the first block) (`always`), Never (the page starts below the header) (`never`)	At every width: whether the logo bar lies transparent over the page's first block. Auto: over an opening light Hero.	—

Additional tab — TCS Header

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	`classes_anchor`	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	A unique ID of the block on the page, starting with anchor-, e.g. anchor-our-services; link to it with #anchor-our-services. Delivered as a block class.	—
Hide block	`classes_hideblock`	boolean	No	`false`	on / off	Hides the whole block on the page until it is turned off. Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Padding left	classes_paddingleft	select	No	""	Default (""), 0 (none) (pl-0), 0.25rem (space-100) (pl-100), 0.5rem (space-200) (pl-200), 0.75rem (space-300) (pl-300), 1rem (space-400) (pl-400), 1.25rem (space-500) (pl-500), 1.5rem (space-600) (pl-600), 2rem (space-800) (pl-800), 2.5rem (space-1000) (pl-1000), 3rem (space-1200) (pl-1200), 4rem (space-1600) (pl-1600), 5rem (space-2000) (pl-2000), 6rem (space-2400) (pl-2400), 7.5rem (space-3000) (pl-3000)	Delivered as a block class.	—
Padding right	classes_paddingright	select	No	""	Default (""), 0 (none) (pr-0), 0.25rem (space-100) (pr-100), 0.5rem (space-200) (pr-200), 0.75rem (space-300) (pr-300), 1rem (space-400) (pr-400), 1.25rem (space-500) (pr-500), 1.5rem (space-600) (pr-600), 2rem (space-800) (pr-800), 2.5rem (space-1000) (pr-1000), 3rem (space-1200) (pr-1200), 4rem (space-1600) (pr-1600), 5rem (space-2000) (pr-2000), 6rem (space-2400) (pr-2400), 7.5rem (space-3000) (pr-3000)	Delivered as a block class.	—
Padding top	classes_paddingtop	select	No	""	Default (""), 0 (none) (pt-0), 0.25rem (space-100) (pt-100), 0.5rem (space-200) (pt-200), 0.75rem (space-300) (pt-300), 1rem (space-400) (pt-400), 1.25rem (space-500) (pt-500), 1.5rem (space-600) (pt-600), 2rem (space-800) (pt-800), 2.5rem (space-1000) (pt-1000), 3rem (space-1200) (pt-1200), 4rem (space-1600) (pt-1600), 5rem (space-2000) (pt-2000), 6rem (space-2400) (pt-2400), 7.5rem (space-3000) (pt-3000)	Delivered as a block class.	—
Padding bottom	classes_paddingbottom	select	No	""	Default (""), 0 (none) (pb-0), 0.25rem (space-100) (pb-100), 0.5rem (space-200) (pb-200), 0.75rem (space-300) (pb-300), 1rem (space-400) (pb-400), 1.25rem (space-500) (pb-500), 1.5rem (space-600) (pb-600), 2rem (space-800) (pb-800), 2.5rem (space-1000) (pb-1000), 3rem (space-1200) (pb-1200), 4rem (space-1600) (pb-1600), 5rem (space-2000) (pb-2000), 6rem (space-2400) (pb-2400), 7.5rem (space-3000) (pb-3000)	Delivered as a block class.	—
Margin left	classes_marginleft	select	No	""	Default (""), 0 (none) (ml-0), 0.25rem (space-100) (ml-100), 0.5rem (space-200) (ml-200), 0.75rem (space-300) (ml-300), 1rem (space-400) (ml-400), 1.25rem (space-500) (ml-500), 1.5rem (space-600) (ml-600), 2rem (space-800) (ml-800), 2.5rem (space-1000) (ml-1000), 3rem (space-1200) (ml-1200), 4rem (space-1600) (ml-1600), 5rem (space-2000) (ml-2000), 6rem (space-2400) (ml-2400), 7.5rem (space-3000) (ml-3000)	Delivered as a block class.	—
Margin right	classes_marginright	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	Delivered as a block class.	—
Margin top	classes_margintop	select	No	""	Default (""), 0 (none) (mt-0), 0.25rem (space-100) (mt-100), 0.5rem (space-200) (mt-200), 0.75rem (space-300) (mt-300), 1rem (space-400) (mt-400), 1.25rem (space-500) (mt-500), 1.5rem (space-600) (mt-600), 2rem (space-800) (mt-800), 2.5rem (space-1000) (mt-1000), 3rem (space-1200) (mt-1200), 4rem (space-1600) (mt-1600), 5rem (space-2000) (mt-2000), 6rem (space-2400) (mt-2400), 7.5rem (space-3000) (mt-3000)	Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Margin bottom	`classes_marginbottom`	select	No	""	Default (""), 0 (none) (`mb-0`), 0.25rem (space-100) (`mb-100`), 0.5rem (space-200) (`mb-200`), 0.75rem (space-300) (`mb-300`), 1rem (space-400) (`mb-400`), 1.25rem (space-500) (`mb-500`), 1.5rem (space-600) (`mb-600`), 2rem (space-800) (`mb-800`), 2.5rem (space-1000) (`mb-1000`), 3rem (space-1200) (`mb-1200`), 4rem (space-1600) (`mb-1600`), 5rem (space-2000) (`mb-2000`), 6rem (space-2400) (`mb-2400`), 7.5rem (space-3000) (`mb-3000`)	Delivered as a block class.	—

Notes on the significant fields:

- **TCS Logo / TATA Logo.** Rendered as the picture AEM delivers, inside `a.tcs-header-brand` / `a.tcs-header-group` (a `span` when the logo has no link). In the site header, the CSS sets the height per breakpoint (see Content and Asset Guidelines).
- **TCS Logo Alt Text / TATA Logo Alt Text.** Fields ending in Alt collapse into their image (AEM delivery rule): the text arrives as the image's `alt`, not as a row of its own. It names the logo link for screen readers. When a linked logo has an empty alt, the code uses the placeholder `tcsLogo` ("Tata Consultancy Services") / `tataLogo` ("TATA Group").
- **TCS Logo Link / TATA Logo Link.** A link or text; a domain typed without a scheme (`www.tata.com`, `tata.com/…`) gets `https://` added, so it isn't a relative link. Without a link the logo isn't a link.
- **No image.** A logo with a link but no image renders its placeholder name as text in the link; without image and link it isn't rendered.
- **Data layer impact.** Logo clicks are `cmp:click` (see Data Layer and Analytics).
- **Legacy mapping.** None.
- **Additional tab.** As every block (AGENTS.md "Additional tab"), without animation fields; the styles apply only inside `main`, so on the Navigation page they don't reach the site header.

4. Screenshot-Based Authoring Steps

Authoring Step 1: Add the TCS Header to the Navigation page

```
[Screenshot Placeholder]

File name:
tcs-header-authoring-step-1.png

Purpose:
The first section of the Navigation page with the Add menu open and TCS Header highlighted.

Annotations:
A = First section of the nav page
B = Add (+)
C = TCS Header in the component list
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Section	The first section of `references/nav`	The header reads the logos from the block, whatever its section	The block's section becomes the header's brand and tools
C	Component	TCS Header	Logo fields	An empty TCS Header block

Author action: Add › TCS Header. Expected preview: an empty block until the fields are filled in. Business rule: one TCS Header per nav page (the header uses the first one). Validation: the content tree shows the block in the first section. Common mistake: adding it to a content page instead of the nav page; resolution: open the page's Navigation page.

Authoring Step 2: The TCS logo

```
[Screenshot Placeholder]

File name:
tcs-header-authoring-step-2.png

Purpose:
The Content tab with the TCS Logo fields filled in.

Annotations:
A = TCS Logo
B = TCS Logo Alt Text
C = TCS Logo Link
```

Values to Enter

Call out	Field	Value	Reason	Expected result
A	TCS Logo	`/content/dam/tcs-corp/block-library/header/tcs-logo.png` (production: `/content/dam/tcs-corp/header/tcs-logo.svg`)	One asset for all breakpoints	TCS logo shown
B	TCS Logo Alt Text	`Tata Consultancy Services`	Names the link	Announced name
C	TCS Logo Link	`/language-masters/en/curated-design-pages/home` (the locale Home)	Brand links Home	The logo is a link

Expected published result: every page using the nav page shows the logo. Validation: the logo link's accessible name is the alt text. Common mistake: a JPG with a white background (F-81); use the transparent SVG.

Authoring Step 3: The TATA logo

```
[Screenshot Placeholder]

File name:
tcs-header-authoring-step-3.png

Purpose:
The Content tab with the TATA Logo fields filled in.

Annotations:
A = TATA Logo
B = TATA Logo Alt Text
C = TATA Logo Link
```

Values to Enter

Call out	Field	Value	Reason	Expected result
A	TATA Logo	`/content/dam/tcs-corp/block-library/header/tata-logo.png` (production: `/content/dam/tcs-corp/header/tata-logo.svg`)	Group logo	TATA logo shown

Call out	Field	Value	Reason	Expected result
B	TATA Logo Alt Text	`TATA Group`	Names the link	Announced name
C	TATA Logo Link	`https://www.tata.com`	Group site	Opens tata.com

Business rule: `www.tata.com` without `https://` is completed by the code. Validation: the published link is `https://www.tata.com`. Common mistake: a relative path; resolution: enter the full address.

Authoring Step 4: Preview and publish

```
[Screenshot Placeholder]

File name:
tcs-header-authoring-step-4.png

Purpose:
A content page in preview at 1440px and 390px showing the logos from the nav page.

Annotations:
A = TCS logo in the header
B = TATA logo in the header
C = Menu button (390px)
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Publish	The Navigation page and both assets	Pages load the published nav page	Logos on the live site

Validation: check the logo heights per breakpoint and both links. Common mistake: publishing the page but not the DAM assets.

5. Variations

On the Navigation page (header logos)

- **Purpose:** the site header's brand and tools.
- **When to use / not:** always on nav pages; not needed on positional nav pages authored before (brand, sections, tools), which still work.
- **Fields:** the six logo fields, and **Menu root path** / **Menu depth** for the tablet and mobile menu.
- **Rendering:** `blocks/header` `applyLogoBar` replaces the block's section with `div.section.nav-brand > p > a.tcs-header-brand` and `div.section.nav-tools > p > a.tcs-header-group`; the first other section becomes the menu. A TCS Header in the same section as a Conversation Canvas is kept as the logo bar (only the Canvas goes to the header Canvas). Sizes and layout come from `header.css`.
- **Tablet and mobile menu (below 1200px):** a nav page without a menu list of its own gets one from this block: decorated in the nav fragment (before the header reads it), it adds `div.section.tcs-header-menu` after its section, the list of the pages below its **Menu root path** (else the Menu root path of the Conversation Canvas in its section) up to its **Menu depth** (else the Canvas's, else 1), from the query index (`utils/query-index.js` `getPageTree`; `scripts.js` `prefetchData` starts the index on every page at the start of the lazy phase, so the header doesn't wait for it). `blocks/header` (unchanged) makes it the menu: menu button, levels, Escape, focus, `header:menu`. No pages (or AEM author, which has no query index): no menu, no menu button. `tcs-header.css` styles the header below 1200px as Figma Mobile Nav 2325:55704 / 1124:25497 (24px gutters, TCS logo 30.7px, TATA logo 38px, the menu icon's 2px lines 26px wide and 8px apart in `--color-icon-default`). The open menu's title row ("Menu",

or a level's Back arrow and title) starts at the gutter, left-aligned with the rows below, and a linked section's arrow (on its button) is at the right edge, in line with the other rows' arrows. While the menu is open the header Canvas is hidden (`blocks/conversation-canvas`); it shows again in its place when the menu closes. Below 1200px the Conversation Canvases don't show their own site menu button (`blocks/conversation-canvas`): the header's menu button is the site navigation there; on desktop the Canvas menu lists the same pages, one level at a time like this menu.

- **Menu root path fallback:** the menu takes the first of the block's own Menu root path and the Conversation Canvas's (in the same section) with pages in the site's query index. A Menu root path of another site (e.g. the language master, `/content/tcs-corp/language-masters/en/...`, on an `/en` page) has none there, so the Canvas's is used; without pages in either, there's no menu and no menu button.
- **The logo bar stays at the top** while the page scrolls, at every width (fixed, `z-index: 20`), in every Header over the first block mode; over the first block it is transparent at the top of the page and turns solid once the page has scrolled by the bar's height (a scroll-driven animation; browsers without one keep it transparent); the open tablet / mobile menu keeps it solid, and the menu button has no box of its own. In-page targets (a # link to a heading or an Anchor ID, `anchor-*`) scroll clear of the bar (`scroll-margin-top: calc(var(--nav-height) + 1.5rem)` on pages with a TCS Header); the Anchor List keeps its own offset.
- **Header over the first block (every width): Auto** (default) keeps the behaviour before: the logo bar lies transparent over an opening light Hero (Home), else it's a bar above the page. **Always**: the bar is transparent over the page's first block, whatever it is, which starts at the top of the page; a Hero keeps its content below the logos, other blocks need their own top space (their Padding top, Additional tab, or `var(--header-overlay-space, 0rem)` in a block's CSS); the logos should be transparent images (a JPG keeps its white box over a coloured block) and dark logos aren't visible over a dark block. **Never**: the bar is above the page also over a light Hero (the page starts below the 64px / 124px bar). The block sets `<html data-header-overlay>` (`utils/header-space.js setHeaderOverlay`) when decorated in the nav fragment, not on the nav page itself; the layout is in `styles/styles.css` (it applies before the header loads), the transparent bar in `tcs-header.css`. The mode is remembered per browser and applied before the header loads on the next pages, so only a visitor's first page with Always or Never can move once when the header arrives (decision log KB-D-052, Proposed).
- **Desktop / tablet / mobile:** as the Header.
- **Accessibility:** logo links named by their alt texts, inside the header's `nav`.
- **Data layer:** clicks report the header component (`header-1`).
- **Personalization / fallback:** none; an area nav page can use other logos.

```
[Screenshot Placeholder]

File name:
tcs-header-in-header-desktop.png

Purpose:
The logos in the site header (see Visual Reference).

Annotations:
A = TCS logo
B = TATA logo
```

Standalone logo bar

- **Purpose:** the logo bar inside a page section.
- **Rendering:** `div.tcs-header-bar` (flex, 1.7391rem gap between the logos; `justify-content: space-between` from 1200px). In a Full Width section (any section without `fixed-width`) the bar keeps the header's gutters (1rem / 1.5rem / 5rem); in a Fixed Width section the section gutter applies.
- **Accessibility / data layer:** the block is its own component (`tcs-header-1`); logo clicks `cmp:click`.

```
[Screenshot Placeholder]
```

```
File name:
tcs-header-standalone-desktop.png

Purpose:
The standalone logo bar (see Visual Reference).

Annotations:
A = TCS logo
B = TATA logo
```

6. Complete Authoring Example

Scenario: the default Navigation page of `/en` gets the corporate logos.

Field	Example value	Guidance
TCS Logo	`/content/dam/tcs-corp/header/tcs-logo.svg`	Transparent SVG exported from the Figma TCS Logo
TCS Logo Alt Text	`Tata Consultancy Services`	Translate per locale
TCS Logo Link	The `/en` Home page	
TATA Logo	`/content/dam/tcs-corp/header/tata-logo.svg`	Transparent SVG
TATA Logo Alt Text	`TATA Group`	
TATA Logo Link	`https://www.tata.com`	Full address

Steps: open `/content/tcs-corp/us/en/references/nav`, add the TCS Header to the first section, fill in the fields, publish the page and the two SVGs.

Expected output: the header logo bar on every `/en` page. Responsive: heights 1.2104 / 1.9165 / 2.175rem (TCS) and 1.5 / 2.375 / 2.75rem (TATA). Accessibility: two named logo links. Analytics: logo clicks on `component.header-1`. Personalization fallback: none.

Pre-publish checklist:

- [ ] Both images selected (SVG), both alt texts, both links.
- [ ] Block in the nav page's first section, menu list in the next one.
- [ ] Assets published.
- [ ] Checked at 390px, 1024px, 1440px.

7. Content and Asset Guidelines

- **Logos.** One asset per logo for every breakpoint (Figma uses the same vector at every size); upload SVGs to `/content/dam/tcs-corp/header/` (`tcs-logo.svg`, `tata-logo.svg`, F-77). The width follows the aspect ratio, except the TCS logo has a fixed 9.125rem (146px) desktop width:

Logo	Mobile	Tablet (>= 600px)	Desktop (>= 1200px)
TCS logo	1.2104rem (19.4px)	1.9165rem (30.7px)	2.175rem (34.8px)
TATA logo	1.5rem (24px)	2.375rem (38px)	2.75rem (44px)

- **Alt text.** The organisation's name ("Tata Consultancy Services", "TATA Group"), translated per locale.
- **Links.** The locale Home for TCS; the full `https://` address for external links.
- **Icons, tags, metadata.** None.
- **Min / max items.** Two logos (fixed by the model).
- **Loading.** The images AEM delivers (no `createOptimizedPicture` in the block); in the header they load with the nav page in the lazy phase.
- **Missing asset.** Linked logo without image: its placeholder name as text; neither: nothing.

8. Troubleshooting

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
No logos in the header	Assets not uploaded / published (F-77), or block not on the nav page in use	Check the page's Navigation; image requests	Upload / publish the SVGs; edit the right nav page	Logos visible
Logo with a white box	JPG / PNG with background (F-81)	Inspect the asset	Use the transparent SVG	Clean logo
TATA link leads to a 404 on the site	Old content with a relative link	Inspect `href`	Enter `https://www.tata.com`	Correct target
Logo name shown as text	No image selected	Properties panel	Select the asset	Image shown
Spacing options have no effect in the header	Additional tab styles apply only inside `main`	—	Expected	—
No menu button on tablet / mobile	No Menu root path with pages in the site: e.g. a language master path on an `/en` nav page and no Conversation Canvas Menu root path	The nav page's TCS Header and Canvas Menu root paths; `/{locale}/query-index.json`	Set the TCS Header's Menu root path to a page of the site (`/en/...`) or clear it	Menu button shown
Header over the first block has no effect	Nav page not published, or the page uses another nav page	`<html data-header-overlay>` on the page; the page's Navigation	Publish the nav page	Attribute set, layout as chosen
The page moves once when the header loads (Always / Never)	The visitor's first page: the mode isn't known before the header loads	Second page view: no shift	Expected (KB-D-052, Proposed)	CLS 0 on the next page
Text of the first block under the logos (Always)	The block has no space for the header	Inspect the block's top padding	Padding top (Additional tab) or `--header-overlay-space` in the block's CSS	Text below the logos

Evidence to collect: the nav page path, the rendered `a.tcs-header-*` markup, the asset paths, a screenshot per breakpoint.

9. Screenshots

> **Screenshot required**
>
> - Required screen: TCS Header dialog in Universal Editor (every tab, including Additional)
> - Required role/access: AEM Sites author with Universal Editor (content author)
> - Required navigation steps: AEM Sites console > /content/tcs-corp/language-masters/en > open a page in Universal Editor
> - Reason unavailable: No AEM author access in the documentation program (access blocker AB-01)
> - Owner: Content Lead / AEM Authoring Lead (proposed)
> - Target completion date: To be confirmed

10. Known limitations

- Universal Editor screenshots are placeholders: no author access in this program.

11. Open items

- None.

12. Change history

Version	Date	Author	Change
1.0	13 November 2026	Delivery team (documentation program)	First version of the role-specific documentation (master documentation prompt), generated from the repository and the published reference pages