
## TCP Server - Client



Server: listen()

클라이언트 접속 요청받음, 최대 접속 지정 가능

Client: connect()

클라이언트가 서버에게 접속

Server: accept()

접속한 클라이언트의 정보 제공

send(), recv() == write(), read()

send(fd, buf, len, flag) recv(fd, buf, len, flag) 데이터 송수신용

### ▶ 실습 01: Basictcpsrv.c

```
1 #include <stdio.h>
2 #include <netinet/in.h>
3 #include <sys/socket.h>
4 #include <string.h>
5 #include <arpa/inet.h>
6 #define PORT 9001

7 int main()
9 {
10 //실제 소켓
11 int srvSd, clntSd;
```

```
//소켓의 주소 구조체
12
13
       struct sockaddr_in srvAddr, clntAddr;
14
       int clntAddrLen, readLen;
15
       char rBuff[BUFSIZ];
16
       char wBuff[] = "I am 20 years old.";
17
       //IPv4, TCP로 소켓 생성
18
19
       srvSd = socket(AF_INET, SOCK_STREAM, 0);
20
       if(srvSd == -1)
21
           printf("Socket Error\n");
23
24
       }
25
       //메모리 초기화
26
27
       memset(&srvAddr, 0, sizeof(srvAddr));
28
       srvAddr.sin_family = AF_INET;
29
       //INADDR_ANY: 어느 IP든 접속 가능
30
       srvAddr.sin_addr.s_addr = htonl(INADDR_ANY);
31
       //9001
32
       srvAddr.sin_port = htons(PORT);
       //소켓에 주소 설정해줌 (실제 소켓 <- 소켓 주소(sockaddr))
34
       if(bind(srvSd, (struct sockaddr *) &srvAddr, sizeof(srvAddr)) == -1)
37
           printf("Bind Error");
39
40
       //최대 5개 connection 허용
41
42
       if(listen(srvSd, 5) == -1)
43
           printf("Listen Error");
44
47
48
       clntAddrLen = sizeof(clntAddr);
49
       //client로부터 연결 오면 clntSd 소켓에 저장
50
51
       clntSd = accept(srvSd, (struct sockaddr*)&clntAddr, &clntAddrLen);
52
       if(clntSd == -1)
       {
54
           printf("Accept Error");
57
58
       //client가 write 값 읽기
       readLen = read(clntSd, rBuff, sizeof(rBuff)-1);
       if(readLen == -1)
60
61
       {
62
           printf("Read Error");
64
65
       //개행문자 추가
66
       rBuff[readLen] = '\0';
       printf("Client: %s \n", rBuff);
67
```

```
//client로 값 보내기
write(clntSd, wBuff, sizeof(wBuff));

//소켓 닫기
close(clntSd);
close(srvSd);

return 0;

// **Colored by Color Scripter*
```

#### ▶ 실습 01: BsictcpcInt.c

```
1 #include <stdio.h>
 2 |
   #include <netinet/in.h>
 3 #include <sys/socket.h>
4 #include <string.h>
   #define PORT 9001
   int main()
8
   {
        //서버 소켓
10
       int clntSd;
11
       struct sockaddr_in clntAddr;
12
        int clntAddrLen, readLen;
13
        char wBuff[] = "How old are you?";
14
        char rBuff[BUFSIZ];
15
       //IPv4, TCP로 소켓 생성
16
17
        clntSd = socket(PF_INET, SOCK_STREAM, 0);
18
       if(clntSd == -1)
19
        {
20
           printf("Socket Creation Error");
21
           return -1;
22
        //주소 할당
23
24
        clntAddr.sin_family = AF_INET;
25
        clntAddr.sin_addr.s_addr = inet_addr("127.0.0.1");
26
        clntAddr.sin_port = htons(PORT);
27
        //server(clntSd)에 연결 요청
28
29
        if(connect(clntSd, (struct sockaddr *) &clntAddr, sizeof(clntAddr)) == -1)
30
           printf("Connect Error");
32
           close(clntSd);
34
        }
36
37
        //보내기
38
       write(clntSd, wBuff, sizeof(wBuff));
        printf("Client: %s\n",wBuff);
40
41
42
        readLen = read(clntSd, rBuff, sizeof(rBuff)-1);
        if(readLen == -1)
44
```

```
printf("Read Error");
return -1;

ret
```

# Q1. 서버 프로그램에서 최대 sizeof(rBuff)-1를 읽고 rBuff[readLen]에 '\0'을 추가하는 이유?

printf는 문장 종결 단위인 null을 만날 때까지 출력하기 때문에..

-> 널 추가하지 않으면 메모리 leak, 버퍼덮어씌워짐 등

혹은 null 추가 말고

```
printf("%.*s", readLen, rBuff);
```

형식으로도 가능

## **Summary**

- 네트워크 주소 Network Classes (A/B/C/D..) CIDR
- 소켓 주소 Bind
- 바이트 순서 Network order = Big Host order = Little
- 주소 변환 inet\_\*
  - addr = aton //ip to network
  - o network //ip to host
  - o ntoa //network to ip
  - -- IPv6
    - o pton //ip to network
    - ntop //network to ip
  - -- same
    - o inet\_addr() + ntohl() == inet\_network()
    - o inet\_network() + htonl() == inet\_addr()
- 소켓 프로그램 **server** socket -> bind -> listen -> accept -> read/write -> close

client socket -> connect -> read/write -> close