IBC Position Taking

Product Name: IBC System
Project Name: IBC Position Taking
Project ID:
Module:
Project Manager: Pham Nguyen Thanh Thien

Document Version: **00.02**
Release Date: DD Month YYYY

Approval by:

#	Full Name	Position
1		
2		

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

Revision History

#	Date	Version	Author	Review	Description/Changes
1	20 April 2008	00.02	Tran Thi Tham		
2					

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

Table of Contents

Revision History 2
1. Introduction 4
1.1 Purpose 4
1.2 Glossary 5
2. Admin. 5
2.1 Create Super Agent 5
2.2 Update Min PT for Super Agent 5
2.3 Update Super Agent 6
2.4 Update Min & Max PT for Master Agent 7
2.5 Update Min & Max PT for Agent 8
3. Super Agent 9
3.1 Create Master Agent 9
3.2 Update Min PT for Master Agent 10
3.3 Update Master Agent 10
3.4 Update PT for Multiple Master Agents 13
3.5 Update PT for Individual Member 15
3.6 Update PT for Multiple Members 17
4. Master Agent 19
4.1 Create Agent 19
4.2 Update Min PT for Agent 20
4.3 Update Agent 20
4.4 Update PT for Multiple Agents 21
4.5 Update PT for Individual Member 22
4.6 Update PT for Multiple Members 22
5. Agent 23
5.1 Create Member 23
5.2 Update Member 23
5.2 Update PT for Multiple Members 24
Appendices 26

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

1. Introduction


1.1 Purpose

In order to train new staff (both operations and IT), discuss with external stakeholders easier, and make our internal discussions easier, the core of this documentation explains the whole picture about **Position Taking** (PT), the most important concept of the IBC system, on all levels. The organizational structure of the IBC System behaves as a "tree structure". Let's look at the following structure and try to understand deeply how the position taking share will be set.

The **Figure 1** shows five very important levels of the IBC Organizational System. Each level has each appropriate access rights to the system.

Figure 1: IBC Organizational Structure

Some figures to illustrate generally about shares of company and agent levels on member win/loss amount, like:



-Should think over the flow of the document, may be
s4, m4, a4 - create super
s3, m3 – create master
m2, a2 - create agent
s1, m1, a1 – create member

n4, l4 – set min max, update super
n3, l3 – set min max, update master
n2, l2 – set min max, update agent

Auto PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

1.2 Glossary


Term	Definition
PT	Position Taking is company/super/master/agent's share (in percentage) of each bet transaction per each particular punter.
IBC	International Betting Company

2. Admin.

2.1 Create Super Agent

The following **Picture 1** shows maximum PT for Super, Master and Agent. All of these following settings can be modified at any time by an administrator user.

- **Super Max Position (s4):** specify the Super Max PT value per each bet type that admin intends to take for each particular super agent and then that value is greater than the Master and Agent's Max PT.
- **Master Max Position (m4):** specify the Master Max PT value per each bet type that admin intends to take for and then that value will affect to Master and Agent.
- **Agent Max Position (a4):** specify the Agent Max PT value per each bet type that admin intends to take for and then that value will affect to Agent.



Picture 1: Admin presets PT for Super Agent "akhoo"

v Notes:

- 0.9 is set as maximum default value for s4 <==> s4 <= 0.9
- Super Max Position >= Master Max Position <==> s4 >= m4
- Master Max Position >= Agent Max Position <==> m4 >= a4
- 0.9 >= s4 >= m4 >= a4 <==> 0.9 >= 0.8 >= 0.7 >= 0.6
- By default Super Min PT (n4) is 0. <==> n4 = 0

To make sure that you can catch up all above information. Let's have a look at **Table 1** as below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	s4:0.8	m4:0.7	a4:0.6			n4:0.00	l4 = s4 :0.8


Table 1: Super Agent "akhoo" PT

2.2 Update Min PT for Super Agent

Provide a very important function to assist company in decreased losing the exposure in case super, master and agent do not intended to take their own share.

- **Super Min PT (n4):** is minimum value that company prefers to set for each specified super agent. In practice Super and Master must take their own share not less than n4. In this situation, the optional values of Min Position are 0, 0.01, 0.02, 0.03 … 0.8 because the company set 0.8 as maximum value for Super Agent "**akhoo**". See **Picture 2**, company sets Min Position for **"akhoo"** 0.3

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.



Picture 2: Admin updates Min PT for Super Agent "akhoo"

- **Notes:**
  - The message **"Wrong min/max position taking"** will appear if new Min Position exceeds **Max Position** <==> n4 <= s4 <= 0.9
  - If the admin increases super min position (n4), the values of super taking per members (s1) will automatically increase until s1 + m1 + a1 equal to n4. <==> n4 <= s1 + m1 + a1 <= s4.


To make a summary for **Super Min & Max Position**, look at **Table 2** below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.8**	**m4:0.7**	**a4:0.6**			**n4:0.3**	**l4 = s4 :0.8**

Table 2: Super Agent "akhoo" after updating Min PT

2.3 Update Super Agent

- The following **Picture 3** shows updating preset maximum PT for Super, Master and Agent. In this case, the limitation values for Super named **"akhoo"** Max & Min Position must be 0.3, 0.31, 0.32 … 0.9 because the company set 0.3 as minimum value for him. At this time, the company intends to update s4 = 0.85, m4 = 0.75, and a4 = 6.5



Picture 3: Admin updates PT for Super Agent "akhoo"

- **Notes:**
  - 0.9 is set as maximum default value for s4 <==> s4 <= 0.9
  - Super Max Position >= Master Max Position <==> s4 >= m4
  - Master Max Position >= Agent Max Position <==>m4 >= a4
  - n4 <= s4 <= 0.9 <==> 0.3 <= 0.85 <= 0.9
  - 0.9 >= s4 >= m4 >= a4 <==> 0.9 >= 0.85 >= 0.75 >= 0.65
  - In case of not auto existing masters PT, if Master Preset Position + Super Preset Position > = Super Max Position. *Existing masters exceeded new super position taking (xxx, xxx). ==> All s3+m3<=s4 if i3 = 0
  - New Super PT must be greater than existing members (s1 + m1 + a1) ==> *Existing members exceeded new super position taking (xxx, xxx,) ==> s4 >= s1 + m1 + a1

The following **Table 3** draws general picture of Super Agent Level.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**


Table 3: Super Agent "akhoo" PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

2.4 Update Min & Max PT for Master Agent

From normal user's point of view the system allows company to set Min & Max for Master Agent in order to avoid losing the exposure. Illustrated in the **Picture 4** below:

- **Max Position (l3):** specify new limit maximum PT per each bet type that company intends to take for each particular Master Agent. In practice the new limit maximum PT means that another constrains set by company instead of Super Agent. For instance, Super **"akhoo"** set m3 = 0.65 for Master Agent **"akhoo01"**. On the other hand, company wants to set l3 = 0.6 for Master Agent **"akhoo01".** Thus, Master Max Position is minimum value between m3 and l3 <==> Master Max Position = min (m3, l3). The optional values of Max Position are between n3 to 0.9.
- **Min Position (n3):** specify minimum PT value in percentage per each bet type that company intends to take for each particular Master Agent. It is importance to notice that Master Agent and Agent must take their own share not less than n3. The optional values of Min Position are 0, 0.01, 0.02, 0.03 … 0.65 because it's usually in the range of 0 to m3. In this case, the admin prefers to set 0.2 as Min Position for Master Agent **"akhoo01".**



Picture 4: Admin updates Min & Max PT for Master Agent "akhoo01"

v Notes:

- The message **"*Current account position taking violates new minimum position taking setting (xxx)"** will show if new Master Min Position exceeds Master preset Position ==> n3 <= m3
- The message **"*Wrong min/max position taking"** will appear if new Min PT exceeds Max PT ==> n3 <= l3
- If the admin wants to increase master min position (n3), the values of master taking per members (m1) will automatically increase until m1 + a1 equal to n3. ==> n3 <= m1 + a1 <= l3
- Check new max PT cannot exceed existing min agents *Existing agents (minimum position taking) exceeded new maximum position taking (xxx) ==> n2<= l3
- If the super wants to decrease master max position (l3), the values of master taking per members (m1) will automatically decrease until m1 + a1 equal to l3. ==> n3 <= m1 + a1 <= l3

The following **Table 4** makes a summary about Master Min & Max PT setting by company.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.2**	**m3:0.65**		**u3:0.00**	**i3:0**	**n3:0.2**	**l3:0.6**


Table 4: Admin sets Min & Max PT for Master Agent "akhoo01"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

2.5 Update Min & Max PT for Agent

From normal user's point of view the system allows company to set Min & Max for each particular Agent in order to avoid losing the exposure. Illustrated in the **Picture 5** below:

- **Max Position (l2):** specify new limit maximum PT value in percentage per each bet type that company intends to take for each particular Agent. In practice the new limit maximum PT means that another constrains set by company instead of Master Agent. For instance, Master **"akhoo01"** set a2 = 0.35 for Agent **"akhoo0101"**. On the other hand, company wants to set l2 = 0.4 for Agent **"akhoo0101".** Thus, Agent Max Position must be within minimum (a2, l2) <==> Agent Max Position = min (a2, l2). The optional values of Max Position are between n2 to 0.9.
- **Min Position (n2):** specify minimum PT value in percentage per each bet type that company intends to take for each particular Agent. It is importance to notice that Agent must take his own share not less than n2. The optional values of Min Position are 0, 0.01, 0.02, 0.03 … 0.35 because it's usually in the range of 0 to a2. In this case, the admin prefers to set 0.2 as Min Position for Agent **"akhoo0101".**



Picture 5: Admin updates Min & Max PT for Agent "akhoo0101"

v Notes:

- The admin has fully permission to change l2 less than a2 ==> l2 <= a2.
- The message **"*Wrong min/max position taking"** will appear if new Min PT exceeds Max PT ==> n2 <= l2
- The message **"*Current account position taking violates new minimum position taking setting (xxx)"** will appear if new Min PT exceeds current Agent PT. ==> n2 <= a2.
- If the admin wants to decrease agent max position (l2), the values of agent taking per members (a1) will automatically decrease until a1 equal to l2.

The following **Table 5** draws a summary about Agent Min & Max PT setting by company.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.2**	**m3:0.65**		**u3:0.00**	**i3:0**	**n3:0.2**	**l3:0.6**
Agent		**m2:0.2**	**a2:0.35**			**n2:0.2**	**l2:0.4**

Table 5: Admin sets Min & Max PT for Master Agent "akhoo0101"


Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

3. Super Agent

3.1 Create Master Agent

The Super Agent can create new Master Agent very easy via the **New Master** menu. All of these following pre-settings can be modified at any time by an administrator user or by Super Agent. The **Picture 6** illustrates that the Super Agent intends to preset maximum PT for Master Agent.

- **Super Preset Position (s3):** specify the super own share in percentage per each bet type that he would like to preset. The optional values of s3 are 0, 0.01, 0.02 … 0.85 because company preferred to set for super **"akhoo"** 0.85.
- **Master Preset Position (m3):** specifies the maximum PT value in percentage per each bet type that super intends to take for master and then that value will affect to Master and Agent.



Picture 6: Super Agent presets Position Taking for Master Agent named "akhoo01"

v Notes:

- Master Preset Position and Super Preset Position must not be less than Super Min Position. Otherwise, the message "***Wrong position taking (min/max set by company)…"** appears <==> s3 + m3 >= n4 <==> 0.2 + 0.65 >= 0.3
- Master Preset Position and Super Preset Position cannot exceed Super Max Position, which is setting by Company <==> s3 + m3 <= s4 <==> 0.2 + 0.65 <= 0.85
- One important to notice that the system does not allow Super Agent to take **Max auto Position (u3)**. Therefore, by default u3 is equal to Zero. <==> u3 = 0
- **i3:** verify that Master Agent is auto PT or not.
- **n3:** is known as **Master Min Position,** which is setting by Super or Company. 0 is set as minimum default value for n3 <==> n3 = 0
- **l3:** is known as another **Master Max Potion**, which is setting by Company. 0.9 is set as maximum default value for l3 <==> l3 = 0.9
- Master Preset Position must be within min (m4, l3) <==> m3 <= min (m4, l3).

The **Table 6** briefly describes what Master Agent could be set position taking at this time.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.2**	**m3:0.65**		**u3:0.00**	**i3:0**	**n3:0.00**	**l3:0.9**


Table 6: Master Agent "akhoo01"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

3.2 Update Min PT for Master Agent

From normal user's point of view the system allows Super Agent to set Min Position for Master Agent in order to avoid losing the exposure. Illustrated in the **Picture 7** below:

- **Min Position (n3):** specify minimum PT value in percentage per each bet type that Super Agent intends to take for each particular Master Agent. It is importance to notice that Master Agent and Agent must take their own share not less than n3. The optional values of Min Position are 0, 0.01, 0.02, 0.03 … 0.65 because it's usually in the range of 0 to m3. In this case, the Super Agent prefers to set 0.25 as Min Position for Master Agent **"akhoo01".**



Picture 7: Super Agent updates Min PT for Master Agent "akhoo01"

v Notes:

- The message **"*Wrong min/max position taking."** will appear if new Master Min Position exceeds current Master Max Position ==> n3 <= min (m3, l3)

The following **Table 7** makes a summary about Master Min PT setting by Super Agent.


	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.2**	**m3:0.65**		**u3:0.00**	**i3:0**	**n3:0.25**	**l3:0.6**

Table 7: Super Agent sets Min PT for Master Agent "akhoo01"

3.3 Update Master Agent

Master Agent settings can be modified at any time via the **Master Agent List** menu. The following **Picture 8** shows that the super agent updates PT for Master Agent named **"akhoo01".**

- **Super Preset Position (s3):** the optional values of **Super Preset Position** are 0, 0.01, 0.02 … 0.6 because Master Min Position has been updated 0.25 by Super Agent **"akhoo"** <==> **Super Preset Position = s4 - n3 =** 0.85 - 0.25 **=** 0.6. In this situation, the Super intends to take his own share 0.3.
- **Master Preset Position (m3):** the optional values of **Master Preset Position** are 0.25, 0.26, 0.27 … 0.6 because Master Min Position has been updated 0.25 by Super Agent **"akhoo"** and Master Max Position must be within **min (m4, l3).** In this case, the Super wants to set 0.55 for Master Agent **"akhoo01"**.



Picture 8: Super Agent updates PT for Master Agent "akhoo01"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- **Notes:**
  - Master Preset Position and Super Preset Position must not be less than Super Min Position. Otherwise, the message "***Wrong position taking (min/max set by company)…"** appears <==> s3 + m3 >= n4
  - Master Preset Position and Super Preset Position cannot exceed Super Max Position, which is setting by Company <==> s3 + m3 <= s4

  - New Master Preset PT cannot be less than Master Preset Position + Agent Position ==> Existing Agents cannot exceed new master PT *Existing agents exceeded new master positiontaking (xxx, xxx,) (for SportType).==> m2 + a2 <= m3

The following **Table 8** makes a summary about updating Master Position Taking.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.3**	**m3:0.55**		**u3:0.00**	**i3:0**	**n3:0.25**	**l3:0.6**

Table 8: Super Agent updates PT for Master Agent "akhoo01"

The Super Agent is permitted to specify Auto Position Taking for particular Master Agent. In practice the Auto Position Taking means that the Super Agent takes an extremely good opportunity to use the limited sharing by company in the case of Master Agent and Agent not taking their own share as expected.

- **Auto Super Preset Position (u3):** When auto position taking is being applied its status is usually changed from one state to another, which is i3 = 1. The optional values of Auto Super Preset Position are 0, 0.01, 0.02 … 0.85 because the company set 0.85 for **"akhoo".**
- **Super Preset Position (s3):** not usage in case of Super intended taking auto position taking for specific master agent. <==> s3 = 0
- **Master Preset Position (m3):** the optional values of **Master Preset Position** are 0.25, 0.26, 0.27 … 0.6 because Master Min Position has been updated 0.25 by Super Agent **"akhoo"** and Master Max Position must be within **min (m4, l3).** In this case, the Super wants to set 0.55 for Master Agent **"akhoo01"**.

For more information regarding with Auto Position Taking, see **Picture 9** below:



Picture 9: Super Agent specifies Auto PT for particular Master Agent "akhoo01"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- **Notes:**
  - Master Preset Position and Auto Super Preset Position must not be less than Super Min Position. Otherwise, the message "***Wrong position taking (min/max set by company)…"** appears <==> u3 + m3 >= n4


The following **Table 9** summaries auto position taking for Master Agent "akhoo01"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.00**	**m3:0.55**		**u3:0.85**	**i3:1**	**n3:0.25**	**l3:0.6**

Table 9: Super Agent identifies Auto PT for Master Agent "akhoo01"

The following **Picture 10** displays the message to verify that Super Agent wants to change Master Agent **"akhoo01"** into not to be taken Auto Position Taking. IBC System provides the Super Agent to have an option in order to execute the updating his own members' PT. The optional confirmation values must be within 0 to Super Max Position - Master Preset Position. Notice that all bet types must be followed by the new value confirmation by Soccer Handicap.

If Super intends to take Auto Position Taking on Master, the modifying PT directly on all his members will not updated. It is important to notice that s1 is only updated when u3 = 0 and i3 = 0.



Picture 10: Super Agent takes directly PT on his Members

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

3.4 Update PT for Multiple Master Agents

On Super Agent level, the Updating Multiple Master Agents functionality can be used to centrally modify PT for many Master Agents at the same time. Have a look at the following explanation to understand deeply about this function.

First of all, we must have two Master Agents named **"akhoo01" and "akhoo02"** settings (reference to two **Tables 10 - 11** below).

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master "akhoo01"	**s3:0.00**	**m3:0.55**		**u3:0.85**	**i3:1**	**n3:0.25**	**l3:0.7**
Agent "akhoo0101"		**m2:0.25**	**a2:0.3**			**n2:0.1**	**l2:0.4**
Member "akhoo0101001"	**s1:0.35**	**m1:0.25**	**a1:0.25**	**u1:0.00**	**i1:0**		

Table 10: The Current Setting of Master Agent "akhoo01"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master "akhoo02"	**s3:0.2**	**m3:0.65**		**u3:0.00**	**i3:0**	**n3:0.00**	**l3:0.9**
Agent "akhoo0201"		**m2:0.3**	**a2:0.35**			**n2:0.00**	**l2:0.9**
Member "akhoo0201001"	**s1:0.2**	**m1:0.3**	**a1:0.35**	**u1:0.00**	**i1:0**		

Table 11: The Current Setting of Master Agent "akhoo02"

It is very important to notice that all of these Master Agent settings have difference of PT shares so that the Super Agent must follow the following rules to make it convenience for updating:

- Master Preset Position and Super Preset Position cannot exceed Super Max Position, which is setting by Company <==> s3 + m3 <= s4.
- The message "***Wrong position taking (min/max set by company)…"** will appear, if Master Preset Position and Super Preset Position are less than Super Min Position. ==> s3 + m3 >= n4
- The message "***Existing agents exceeded new master positiontaking…"** will appear, if new Master Preset Position is less than each Master Min Position. ==> m3 >= n3.
- The message **"*Existing agents exceeded new master positiontaking…"** will display, if new Master Preset is less than current Master Preset Position and Agent Position ==> m3 >= m2 + a2
- The message **"*Existing members exceeded new master positiontaking…"** will display, if new Master Preset is less than existing member(s)<==> m3 >= m1 + a1
- Especially, every time updating Multiple Master Agents, the system must always allow Super Agent to have an option to choose, or not. If the Super Agent agrees to take new PT directly on all Members, **s1** will be changed.

Another situation is still none the less important that is related mostly Auto Position Taking:

- The message "***Wrong position taking (min/max set by company)…"** will appear, if Master Preset Position and Auto Super Preset Position are less than Super Min Position. <==> u3 + m3 >= n4
- If Super intends to take Auto Position Taking on Master per each specific bet type, the modifying PT directly on all his members will not updated. It means that s1 is only updated when u3 = 0 and i3 = 0.

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

Example 1: The Super intends to set for Master Agents **"akhoo01"** and **"akhoo02"**: u3 = 0.85 and m3 = 0.65. Look at two **Tables 12 - 13** below showing the changes.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.00	m3:0.65		u3:0.85	i3:1	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 12: Master Agent "akhoo01" after modified PT

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo02"	s3:0.00	m3:0.65		u3:0.85	i3:1	n3:0.00	l3:0.9
Agent "akhoo0201"		m2:0.3	a2:0.35			n2:0.00	l2:0.9
Member "akhoo0201001"	s1:0.2	m1:0.3	a1:0.35	u1:0.00	i1:0		

Table 13: Master Agent "akhoo02" after modified PT

Example 2: The Super intends to set for Master Agents **"akhoo01"** and **"akhoo02":** s3 = 0.2 ==> u3 = 0 and i3 = 0; m3 = 0.65. At this time, especially this Super prefers to take directly **0.15** on all his members ==> s1 = 0.15. See two **Tables 14 - 15** below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.15	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 14: Master Agent "akhoo01" after modified PT

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo02"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.00	l3:0.9
Agent "akhoo0201"		m2:0.3	a2:0.35			n2:0.00	l2:0.9
Member "akhoo0201001"	s1:0.15	m1:0.3	a1:0.35	u1:0.00	i1:0		


Table 15: Master Agent "akhoo02" after Modified PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

3.5 Update PT for Individual Member

The system permits Super Agent to specify directly auto and non-auto position taking on each individual member. First of all, we must have an instance of current settings on Member **"akhoo0101001".** See the following **Picture 11** and **Table 16**:

- **Agent (a1)**: specify the actual Agent Own Share for each individual Member. <==> a1 = 0.25
- **Master (m1)**: specify the actual Master Agent Own Share for each individual Member <==> m1 = 0.25
- **Super (s1)**: specify the actual Super Agent Own Share for each individual Member. <==> s1 = 0.15. If n4 - (m1 + a1) < 0, the optional values of Super Position MUST be within 0 to s4 - (m1 + a1). On the other hand, the remaining value of n4 - (m1 + a1) will be the minimum value allowable Super Agent taking.
- **Super Auto (u1)**: specify the maximum Auto Position Taking that Super Agent intends to take for each individual Member. The optional values of Super Auto Position are within 0 to s4. If u1 > n4 and u1 > s4 - (m1 + a1), the value of s1 MUST be increased until equal to s4 - (m1 + a1). Otherwise, if u1 > n4 and u1 < s4 - (m1 + a1), the value of s1 MUST be increased until equal to **u1 ==>** n4 <= s1 + m1 + a1 <= s4.



Picture 11: The Current Setting of Member "akhoo0101001

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.15	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 16: The Current Setting of Member "akhoo0101001"

- **Example 1:** The super **"akhoo"** prefers to take s1 = 0.2 for Member **"akhoo0101001".** From the **Table 16** above, current settings of Member **"akhoo0101001"**, the optional values are 0, 0.01, 0.02….0.35 because of n4 - (m1 + a1) = 0.3 - (0.25 + 0.25) < 0 and s4 - (m1 + a1) = 0.85 - (0.25 + 0.25) = 0.35 ==> n4 <= s1 + m1 + a1 <= s4. See **Table 17** below:

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.2	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 17: Member "akhoo0101001" after Super modified PT

- **Example 2:** The super **"akhoo"** prefers to take u1 = 0.5 for Member **"akhoo0101001".** The optional values are 0, 0.01, 0.02….0.85 because of s4 = 0.85. Look at the **Table 18** below, the value of s1 MUST be increased until equal to s4 - (m1 + a1) = 0.85 - (0.25 + 0.25) = 0.35 because of u1 > n4 and u1 > s4 - (m1 + a1).

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.50	i1:1		


Table 18: Member "akhoo0101001" after Super modified PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

3.6 Update PT for Multiple Members

If an update single individual member is available, the system will also allow Super Agent useful function to specify directly auto and non-auto position taking on multiple members as well as modifying individual member. We must have an instance of current settings on Members **"akhoo0101001"** and **"akhoo0101002".** See **Picture 12 and Tables 19 - 20**:

- **Super (s1)**: specify the actual Super Agent Own Share for multiple selected Members at the same time. The optional values of Super Position are within 0 to s4 - min (m3, l3).
- **Super Auto (u1)**: specify the maximum Auto Position Taking that Super Agent intends to take for multiple selected Members at the same time. The optional values of Super Auto Position are within 0 to s4. If u1 > n4 and u1 > (s4 - (m1 + a1)), the value of s1 MUST be increased until equal to (s4 - (m1 + a1)). On the other hand, if u1 > n4 and u1 < (s4 - (m1 + a1)), the value of s1 MUST be increased until equal to **u1 ==>** n4 <= s1 + m1 + a1 <= s4.



Picture 12: Super updates PT for Multiple Members "akhoo0101001" and "akhoo0101002"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.50	i1:1		

Table 19: The Current Setting of Member "akhoo0101001"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101002"	s1:0.15	m1:0.25	a1:0.30	u1:0.00	i1:0		

Table 20: The Current Setting of Member "akhoo0101002"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- **Example 1:** The super **"akhoo"** prefers to take s1 = 0.2 for two members "**akhoo0101001"** and **"akhoo0101002".** From the **Tables 19 - 20** above, current detail of that two Members' settings, the optional values are 0, 0.01, 0.02….0.2 because of s4 - min (m3, l3). = 0.85 - 0.65 = 0.2. See **Tables 21 - 22** below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.2	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 21: Member "akhoo0101001" after Super modified PT

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101002"	s1:0.2	m1:0.25	a1:0.30	u1:0.00	i1:0		

Table 22: Member "akhoo0101002 after Super modified PT

- **Example 2:** The super **"akhoo"** prefers to take u1 = 0.6 for two members **"akhoo0101001"** and **"akhoo0101002".** From **Tables 19 - 20** above, current details of that two Members' settings, the optional values are 0, 0.01, 0.02….0.85 because of s4 = 0.85. Look at the **Tables 23 - 24** below the value of s1 MUST be increased until equal to s4 - (m1 + a1) because of u1 > n4 and u1 > s4 - (m1 + a1).

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.60	i1:1		

Table 23: Member "akhoo0101001" after Super modified PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101002"	s1:0.3	m1:0.25	a1:0.30	u1:0.60	i1:1		


Table 24: Member "akhoo0101002" after Super modified PT

4. Master Agent

4.1 Create Agent

The Master Agent can create new Agent very easy via the **New Agent** menu. All of these following pre-settings can be modified at any time by an administrator user or by a Master Agent. The following **Picture 13** illustrates that the Master Agent intends to preset maximum PT for Agent **"akhoo0101"**.

- **Master Preset Position (m2):** specify the own sharing in percentage per each bet type that Master Agent would like to preset for himself. In this case, the optional values of m2 are 0, 0.01, 0.02 … 0.55 because the Super Agent **"akhoo"** preferred to set for Master Agent **"akhoo01"** 0.55. One important to notice that the maximum value allows Master Agent to take must be within **min (m3, l3).**
- **Agent Position (a2):** specifies the maximum PT value in percentage per each bet type that Master Agent intends to take for and then that value will affect to Agent.



Picture 13: Master Agent presets Agent "akhoo0101"

v Notes:

- Master Preset Position and Agent Position must be less than Master Max Position <==> m2 + a2 <= min (m3, l3). <==> 0.2 + 0.35 <= 0.55
- Master Preset Position and Agent Position must not be less than Master Min Position setting by Super Agent or Company. Otherwise, the message "***Wrong position taking (min/max set by company)…"** appears <==> m2 + a2 >= n3 <==> 0.2 + 0.35 >= 0.25
- **n2:** is known as **Agent Min Position,** which is setting by Master Agent or Company. 0 is set as minimum default value for n2 <==> n2 = 0
- **l2:** is known as another **Agent Max Potion**, which is setting by Company. 0.9 is set as maximum default value for l2 <==> l2 = 0.9
- Agent Position must be within minimum (a4, l2) <==> a2 <= min (a4, l2).

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

The following **Table 25** draws general picture up to Agent Level


	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.00**	**m3:0.55**		**u3:0.85**	**i3:1**	**n3:0.25**	**l3:0.6**
Agent		**m2:0.2**	**a2:0.35**			**n2:0.00**	**l2:0.9**

Table 25: Agent "akhoo0101"

4.2 Update Min PT for Agent

From normal user's point of view the system allows Master Agent to set Min Position for each specific Agent in order to avoid losing the exposure. Illustrated in the **Picture 14** below:

- **Min Position (n2):** specify minimum PT value in percentage per each bet type that Master Agent intends to take for each particular Agent. It is importance to notice that Agent must take his own sharing not less than n2. The optional values of Min Position are 0, 0.01, 0.02, 0.03 … 0.35 because it's usually in the range of 0 to a2. In this case, the Super Agent prefers to set 0.1 as Min Position for Agent **"akhoo0101".**



Picture 14: Master Agent updates Min PT for Agent "akhoo0101"

v Notes:

- The message "***Wrong min/max position taking."** will appear if new Min Position exceeds current Agent Max Position ==> n2 <= min (a2, l2)

The following **Table 26** makes a summary about Agent Min PT, which is setting by Master Agent.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.00**	**m3:0.55**		**u3:0.85**	**i3:1**	**n3:0.25**	**l3:0.6**
Agent		**m2:0.2**	**a2:0.35**			**n2:0.1**	**l2:0.4**


Table 26: Min PT of Agent "akhoo0101"

4.3 Update Agent

Agent settings can be modified at any time via the **Agent List** menu. The following **Picture 15** shows that the Master Agent updates PT for Agent named **"akhoo0101".**

- **Master Preset Position (m2):** the optional values of **Master Preset Position** are 0, 0.01, 0.02 … 0.45 because Agent Min Position has been updated 0.1 by Master Agent **"akhoo01"** <==> **Master Preset Position = m3 – n2 =** 0.55 - 0.1 **=** 0.45. In this situation, the Master intends to take his own sharing 0.25.
- **Agent Position (a2):** the optional values of **Agent Position** are 0.1, 0.11, 0.12 … 0.35 because Agent Min Position has been updated 0.1 by Master Agent **"akhoo01"** and Agent Max Position must be within **min (a2, l2).** In this case, the Master wants to update 0.3 for Agent **"akhoo0101"**.

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.



Picture 15: Master Agent updates PT for Agent "akhoo0101"

- **Notes:**
  - The message "***Wrong position taking (min/max set by company)…"** appears if Master Preset Position and Agent Position are less than Master Min Position. ==> m2 + a2 >= n3
  - Master Preset Position and Agent Position cannot exceed Master Max Position, which is setting by Super/Company <==> m2 + a2 <= min (m3, l3).

The following **Table 27** makes a summary about updating Agent Position Taking.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master	s3:0.00	m3:0.55		u3:0.85	i3:1	n3:0.25	l3:0.6
Agent		m2:0.25	a2:0.3			n2:0.1	l2:0.4

Table 27: Master Agent modifies PT for Agent "akhoo0101"

4.4 Update PT for Multiple Agents

On Master Agent level, the Updating Multiple Agents functionality can be used to centrally modify PT for many Agents at the same time. Have a look at the following explanation to deeply understand about this function.

First of all, we must have two Agents named **"akhoo0101" and "akhoo0102"** settings. Look at the following two **Tables 28 – 29** for more regarding information.

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.25			n2:0.1	l2:0.4

Table 28: The Current Setting of Agent "ahoo0101"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0102"		m2:0.2	a2:0.45			n2:0.00	l2:0.9

Table 29: The Current Setting of Agent "ahoo0101"

It is important to notice that all of these Agent settings have difference PT shares so that the Master Agent must follow the following rules to make it convenience for updating:

- Master Preset Position and Agent Position cannot exceed Master Max Position, which is setting by Super/Company <==> m2 + a2 <= min (m3, l3)

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- The message "***Wrong position taking (min/max set by company)…"** will appear, if Master Preset Position and Agent Position are less than Master Min Position. ==> m2 + a2 >= n3
- The message "***…Wrong position taking (min/max set by company)…"** will appear, if new Agent Position is less than each Agent Min Position. ==> a2 >= n2
- The message "***…Wrong position taking (min/max set by company)…"** will appear, if new Agent Position is greater than each Agent Max Position, which is setting by Company. ==> a2 <= l2

Example: The Master intends to set for Agents **"akhoo0101"** and **"akhoo0102"**: m2 = 0.25; a2 = 0.35. See two **Tables 30 - 31** below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.3	a2:0.35			n2:0.1	l2:0.4

Table 30: Agent "ahoo0101" after Master modified PT

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0102"		m2:0.3	a2:0.35			n2:0.00	l2:0.9

Table 31: Agent "ahoo0101" after Master modified PT

4.5 Update PT for Individual Member


4.6 Update PT for Multiple Members

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

5. Agent

5.1 Create Member

The Agent can create new Member very easy via the **New Member** menu. The following **Picture 16** illustrates that the Agent intends to take his own sharing per Member **"akhoo010101"**. In this case, the optional values of Agent Position are 0.1, 0.11, 0.12 … 0.3 because its must be within n2 to min (a2, l2).



Picture 16: Agent presets PT for Member "akhoo0101001"

- **Notes:**
  - **s1:** specify the Super Agent Own Sharing per each particular Member. If u3 # 0 or i3 # 0 then s1 will be the remaining of min (u3, (s4 – (m1 + a1)). Otherwise, s1 will copy value from s3.
  - **m1:** specify the Master Agent Own Sharing per each particular Member.
  - **a1:** specify the Agent Own Sharing per each particular Member.
  - **u1:** is known as **Auto Position Taking,** which is taken by Super per each individual **Member**. 0 is set as default value for u1 <==> u1 = 0
  - **i1:** verify that Member is taken Auto PT by Super Agent or not. 0 is set as default value for i1 <==> i1 = 0


The following **Table 32** describes general picture up to Member Level

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	**s4:0.85**	**m4:0.75**	**a4:0.65**			**n4:0.3**	**l4 = s4 :0.85**
Master	**s3:0.00**	**m3:0.55**		**u3:0.85**	**i3:1**	**n3:0.25**	**l3:0.6**
Agent		**m2:0.25**	**a2:0.3**			**n2:0.1**	**l2:0.4**
Member	**s1:0.3**	**m1:0.25**	**a1:0.3**	**u1:0.00**	**i1:0**		

Table 32: Member "akhoo0101001" PT

5.2 Update Member

Member settings can be modified at any time via the **Member List** menu. The following **Picture 17** shows that the Agent updates PT per Member named **"akhoo0101001".** In this case, the Agent intends to update 0.25.



Picture 17: Agent Updates PT for Member "akhoo0101001"

- **Notes:**
  - If i1 # 0 or i3 # 0 then Agent Position (ap) = min (m3 - m1, s4 - s1 - m1) ==> the optional values of Agent Position must be within n2 to min (ap, a2, l2) ==> a1 must be between n2 and min (ap, a2, l2).
  - If i1 = 0 and i3 = 0 then the optional values of Agent Position must be within n2 to m3 - m1
  - One important to notice that the system will not check a1 < = a2 while updating.
  - **s1:** specify the actual Super Agent Own Share per each particular Member. If u3 # 0 or i3 # 0 then s1 will be the remaining of min (u3, (s4 – (m1 + a1)). Otherwise, s1 will copy value from s3.
  - **m1:** specify the actual Master Agent Own Share per each particular Member.

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- **a1:** specify the actual Agent Own Share per each particular Member.


The following **Table 33** makes a summary updating Position Taking for Member

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master	s3:0.00	m3:0.55		u3:0.85	i3:1	n3:0.25	l3:0.6
Agent		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member	s1:0.35	m1:0.25	a1:0.25	u1:0.00	i1:0		

Table 33: Agent Updates PT for Member "akhoo0101001"

5.2 Update PT for Multiple Members

The system allows Agent to modify the actual his own share for multiple members at the same time. The optional values of Agent Position must be within n2 to min (a2, l2). First of all, we must have an instance of current settings on Members **"akhoo0101001"** and **"akhoo0101002".** See **Picture 18** and **Tables 34 - 35**:



Picture 18: Agent resets PT for multiple members "akhoo0101001" and "akhoo0101002"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.60	i1:1		

Table 34: The Current Setting of Member "akhoo0101001"

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101002"	s1:0.3	m1:0.25	a1:0.30	u1:0.60	i1:1		

Table 35: The Current Setting of Member "akhoo0101002"

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

- **Example:** The Agent **"akhoo0101"** prefers to modify a1 = 0.25 for two members "**akhoo0101001"** and **"akhoo0101002".** From the **Tables 34 - 35** above, current detail of that two Members' settings, the optional values are 0.1, 0.11, 0.12….0.3 because of n2 = 0.1 and min (a2, l2). = 0.3. See **Tables 36 – 37** below:

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101001"	s1:0.35	m1:0.25	a1:0.25	u1:0.60	i1:1		

Table 36: Member "akhoo0101001" after Agent modified PT

	Super	Master	Agent	Auto	Is Auto	Min PT	Max PT
Super "akhoo"	s4:0.85	m4:0.75	a4:0.65			n4:0.3	l4 = s4 :0.85
Master "akhoo01"	s3:0.2	m3:0.65		u3:0.00	i3:0	n3:0.25	l3:0.7
Agent "akhoo0101"		m2:0.25	a2:0.3			n2:0.1	l2:0.4
Member "akhoo0101002"	s1:0.3	m1:0.25	a1:0.25	u1:0.60	i1:1		

Table 37: Member "akhoo0101002" after Agent modified PT

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.

Appendices

Copyright © 2007 by Sports Marketing Software Services Co., Ltd.