

This manual describes the usage of the **foryouandyo** **urcustomers translation manager** AddOn, improving the Oracle Data Modeler.

General


Before you can use the translation manager, it has to be installed into your Oracle Data Modeler (ODM) environment. See [ODM-Scripting-Installation.pdf](#) for the installation process.

Translation manager


Usage - short description

Once installed, the changing of languages is organized as follows:

Right click on Logical Model, choose Apply Customs Transformation Scripts (1).



To change the language apply *changeLanguage* (2). You will be prompted for the language change, if there are more than 2 languages to choose from. If there are only two languages, you will not be prompted to choose a language. It will switch to the other one (and back).



After changing the language, you have to reload the labels of the relations by disable / enable display of labels. (We haven't found yet a way to automate this).

The translated texts are kept in user defined properties (UDP) or in the notes field of the element (for multiline texts as comments).

A new language can be added to an existing translation environment. (see below)

Installation

To Install the scripts see in the installation manual : [ODM-Scripting-Installation.pdf](#)


The translation manager requires the library `translation` and the transformation methods `upgradeTranslation`, `changeLanguage`, `initTranslation`.

In addition to the scripts, it requires the user defined property (UDP) file called *translation.udposdm* in the configuration of your ODM environment. Copy the file *translation.udposdm* into you modelers configuration directory.

Initialization


After installing the translation manager, you have to initialize the translation functionality.

Start the script *initTranslation* (3).



After the installation, define your languages:

Open the properties of you model, select Comments (4).



Define the current language of your model: `currentLang=xx`.

Define the languages of your model (including the current one): `languages=xx,yy,zz`

Languages are always 2-letter ISO-Code, upper case: DE,EN,FR,ES,IT.

The installation is preconfigured to `currentLang= DE` and `languages=DE,EN`

DO NEVER CHANGE ANY OF THE OTHER ENTRIES! This could corrupt your model.

If you have more or other languages than DE and EN, you have to update the User Defined Properties (5).

Open Design Level settings (5)

Open *translation.udposdm*. (6)

Make sure, for every language there is an entry for a Group (uppercase ISO-Code of language) (7)


Add the following User Defined Properties (UDP) (8).

```
xx_ATTR_NAME      xx_ENTI_NAME      xx_ENTI_SYNONYM
xx_RELA_TEXT_FROM xx_RELA_TEXT_TO
```

(xx = ISO-Code of Language)

Link every property with the corresponding modeler element (Attribute, Entity, Relationship) (9)

Every UDP must be in the corresponding group (10)



Storage of translations

Where are the translation kept?

Element	Fields	Remarks
Entity	Name, Synonym, Comment,	Entity Name and Entity Synonyms are kept the corresponding UDP for the language. Entity Comment are kept in the entity Note field. see Comments below
Attribute	Name, Comment,	Attribute Name is kept in the corresponding UDP. Attribute Comment is kept in the Attribute Note field (see Comments below)
Relationships	Name on source, Name on target	the names on the relationships are kept in xx_RELA_TEXT_FROM, xx_RELA_TEXT_TO respectively.

Comments: Attribute and Entity-Comments are multiline fields. In UDP the line separation is removed after saving and reloading (due to XML-solution of storage). So the script maintains the comments in the Note property. The text of the comment field is kept in a section of the note field. This section is marked with

[xx_ENTI_COMMENT]

... comment from comment field

]xx_ENTI_COMMENT]

Other text in the note field is not changed, removed or overwritten by this storage.

Knowledge of this storage of translations in the modeler is important for the usage rules. See following sections.

What happens, if you change the language

Changing the language see (2) above.

Don't forget to disable relationship labels and enable them again to change the display of the new texts. (They are switched but not changed in the display).

This happens in the modeler by changing a language.

Current Language: the current language of the ODM. See entry currentLang in the modelers top comment. (4)

Elements: the properties / fields in the modeler (Name, Synonym, Comment, Relationshipables). They contain always the values for the current language

Current language storage: the current-language instances of the UDP's and Note-sections.
 Other language storage: the instances of the UDP's and Note-sections for all non-current languages.

Step	Effect	Remarks
Copy the elements to the current language storage	(current lang = DE) The UDPs DE_ENTI_NAME, DE_ENTI_SYNONYM, DE_ATTR_NAME, DE_RELATEXT_FROM, DE_RELATEXT_TO, and the comment section in the Note field are overwritten with the values of the elements	The current language storage is overwritten with the current values of the elements unconditionally.
Update the language storage of the other language storage	other language storage is empty: copy element text and mark it as "to be translated" (put *DE* in front of text) other language storage contains text without marks: if the current language text has changed, mark the secondary text as "to be checked" (with a * in front of the text) other language storage is marked as "to be checked" or "to be translated" : other language storage will not be changed	Example: DE_ATTR_NAME "Vorname" becomes EN_ATTR_NAME "*DE* Vorname" DE_ATTR_NAME "Vorname" -> "Rufname" becomes EN_ATTR_NAME "First Name" -> "*First Name"
Copy the language storage of the chosen new language into the elements		The display in the subview does currently not refresh relationship names. You have to "unshow" the labels and show them again.
Change the current language entry in the design-comment		

As a result of this algorithm:

DO NEVER CHANGE THE STORAGE (UDP, NOTES) FOR THE CURRENT LANGUAGE. IT WILL BE OVERWRITTEN at the next language change.

How to update entries in the current language

Use the normal interface of ODM. Change the elements in their property windows.

How to update entries in another language

1. Change the language.
Update elements in the the normal ODM-interface (see How to change entries in the current language).
Change back the language
This is the best way to do it, as you don't have to remember, what is allowed and what is not (see table above)
2. Update the text in the UDP or in the note-field-section.
Make sure to respect the section boundaries in the notes fields and make sure to never edit the UDP's for the current language.
3. Mass updates in Excel
Export your texts to Excel-files with the report functionality of the modeler. Translate or change the text of the other language(s) in the Excel-file.
Reload the excel-file into the modeler with *Upload model with previously exported XLS (XLSX) file*.
DO NEVER RELOAD AN OLD EXCEL-FILE AFTER YOU MADE CHANGES TO THE REPOSITORY.

You should define reports for translating entites, attributes and relationships, containing the translatable elements together with their correspondent UDP's (and the note field for attributes and entities).

Do not include the UDP-columns for the current language in the exported EXCEL.

Adding automated translation

Currently we support automated translation via DeepL.

All you have to do is to add a DeepL-Authorization key.

Add the following line to the translation-properties in your model properties (see (4) above):

DEEPLAuthKey=<your authorization key here>

If the key is valid, automatic translation takes place every time you change to another language. If you change from e.g. German to English, all new entries, still empty in any language other than German, will be translated via a call to the DeepL Web interface. In other words: changing the display language translates all (so far untranslated values) immediately. You can stop automatic translation only by removing the key in the translation properties.

Adding a language

See Installation above:

Add the new language to the languages in the model-comment.

Add the new UDP into translation.udposdm.

Change to the new language to initialize all UDP with a copy of the current language.

Versions

A new installation might need some changes to the data in the modeler. Find here the list of Versions and the steps that have to be done.

Version	Released	Remarks
1.0	2019-11-8	First production release. Install and initialize as described above
1.1	2019-11-10	Corrected bug in replacing language-content Run upgradeTranslation
1.2	2020-02-25	Moved the UDP for Relations from dynamic properties to translation.udposdm. CAUTION: requires ODM 19.4 Add the relationship UDP to translation.udposdm (see Adding a language above). Close and reopen the model. Run upgradeTranslation.
1.3	2020-03-23	Separated manual from installation manual
1.4	2020-06-05	Added automatic translation via DEEPL. Improvements in the treatment of multiline comments in the notes field.