

This manual describes the usage of the **foryouandyo** **urcustomers mapping manager** AddOn, improving the Oracle Data Modeler.

General

Before you can use the mapping manager, it has to be installed into your Oracle Data Modeler (ODM) environment. See [ODM-Scripting-Installation.pdf](#) for the installation process.


Mapping manager

Usage - short description

The mapping-manager are a few script allowing you:


- to export the ODM mapping between entities/attributes and tables/columns
- to import changes in the mapping from the exported files.

Start a script via right-click on logical model, choose Apply Custom Transformation Scripts




Select on of

importMapping	Import changed mapping information from a csv-file
print1Mapping	print the mapping for one relational model into an csv-file
printXMapping	print the existence of a mapping for all entities to all relational models
printNameMapping	print the mapping of all entities, m:n Relationships, attributes to tables and columns for all relational models.



Source of Information

When developping the logical model to relational models (1), ODM keeps track of the mapping of source (entity/relationships/attribute) and target (table/column). (2). The same information is managed by the modeler when reverse engineering a relational model to the logical model.



Functionality

printXMapping	print the existence of a mapping for all entities to all relational models into an csv-File.
printNameMapping	print the mapping of all entities, m:n Relationships and attributes to tables and columns for all relational models into one csv-file
print1Mapping	prints the mapping for all tables/columns from one relational model into a csv-file
importMapping	Import changed mapping information from csv-file generated by print1Mapping.

All generated csv-files are in UTF-8 character code. Elements are separated by ";". Make sure, when importing csv into Excel oder Number (mac) to set the correct parameters.Importing mappings

Importing

The name in the first column/row is the name of the relational model in ODM. It must be identical or it will lead to an error.

To import a new mapping, add the entity-name into the column *entityName* and the attrName into the column *attrName*, the table name into *tableName* and column name into *columnName*.

The names must be exactly as defined in the modeler. No unprintable characters are allowed. Beware of trailing blanks!

If an entity or attribute name is not found, it is ignored during importing.

If a table or column name ist not found, the table or column is inserted into the modeler.
(Nice possibility to import tables and columns, isn't it?)

A1	B	C	D	E	F
Test des Mapping					
entityName	attrName	tableName	columnName		
IsA Entity 2		IsA_Entity_2			
IsA Entity 2	deleteMapping	IsA_Entity_2	delMap		
		IsA_Entity_2	IsA_Entity_2_ID		
		StandaloneTablemitCol	standaloneCol1		
		StandaloneTablemitCol	standaloneCol2		
Subentit 1-2		TABLE_1			
		TABLE_1	Column_1		

Deleting mappings

We haven't found yet a way to delete mappings programmatically in the modeler. The only way we found is:

- print a mappinglist with print1Mapping
- copy an element in the ODM,
delete the original element and
rename the copy to the old element.
- delete the mappings in the csv-file (e.g. the entity - attribut-names)
- import the changed csv file.

This will work because the scripts rely on the names, not on ID's.

Versions

Version	Released	Remarks
1.0	2020-03-21	First Version released beta
1.1	2020-03-23	Separated manual from installation manual