Scope / When to use this article

Use this article when a user reports issues within the Mobile Editor itself, including problems with menus, hidden elements, headers, backgrounds, galleries, slideshows, or elements that only appear on mobile.

Before you start

Always ask the user for their mobile device model, OS version, and browser version before troubleshooting. Do not perform changes on a user's site on their behalf, even with consent. Guide them through steps instead. First try to reproduce on a duplicated or cloned site before accessing the user's account.
Note: *We do not support old menu issues. Before escalating any menu-related issue, always confirm the menu is set to Advanced.*


Troubleshooting Steps

Unable to locate an element in the Mobile Editor

1. Some elements may be automatically hidden by the mobile algorithm. Common causes: content not needed on mobile, heavy elements like Pro Galleries, non-mobile-friendly elements, or elements outside the Mobile Editor frame.
2. Use the Layers Panel to locate the element and check its position. Use the Component Finder for harder to reach elements.
3. Refer to Hidden Elements in the Mobile Editor for additional steps.

Header is too large and cannot be resized

1. If the header cannot be resized, the mobile menu is likely frozen in the header.
2. Open the Layers Panel, select the mobile menu icon, and toggle off the freeze option in the toolbar. The user will then be able to adjust the header height.




Menu issues in the Mobile Editor

1. Confirm the menu is set to **Advanced** before troubleshooting. If you see a **Set to Advanced** button in Settings, ask the user to click it first.
2. If the menu cannot be found, check for: hidden menu, menu color matching the header background, overlapping elements, menu outside the mobile frame, or page set to no header and footer.
3. If the mobile menu appears empty, follow these steps: open the Layers Panel, select the menu container arrow, select the expandable menu, press **Delete**, then unhide the element from hidden elements.
4. Anchor menus will not appear or function on mobile. Anchors must appear in the main menu or have a linked button.
5. Vertical, lightbox, and horizontal menus are not supported on mobile. Only the default hamburger menu is available.
6. If the page layout has no header and footer, the mobile menu will not appear. The user must use linked elements like buttons or text for navigation.

If unresolved, escalate to **Escalations - Editor & Mobile** via the Escalation Wizard.

Elements shifting towards the bottom on the live site

1. This is usually caused by placing a static element such as a social bar on top of a dynamic gallery like a Pro Gallery. This behaviour is expected and is not a bug.



Characters misplaced on mobile menu layout

1. If page names appear in the wrong order on mobile, apply the workaround in Characters Misplaced on Mobile Menu Layout.

After applying the workaround, escalate for visibility and reference **ECL-3858** in the escalation note.

Quick Action Bar covering mobile site content

1. This is expected behaviour. The bar is fixed at the bottom of the page. Guide the user to increase the footer height by approximately 50px using the Editor Toolbar.

Mobile page background issues

1. By default, the desktop background also appears on mobile. The user can set a different background image specifically for mobile.
2. If a video background is not playing on mobile, guide the user to enable it via the background settings on strips, columns, hover boxes, lightboxes, or slideshows. Refer to Wix Editor: Using Video Backgrounds on Your Mobile Site.
3. If a background image appears distorted or cut off, enable the **Freeze** scroll effect or adjust scaling in Background Settings. For best results, crop images specifically for mobile.

Note: *Data Saver in Chrome or Low Power Mode on iOS will prevent video backgrounds from auto-playing.*

Slideshow issues on mobile

1. If slide order updated on desktop does not reflect on mobile, hide and unhide the slideshow to reset it.
2. If a slideshow background is not displaying correctly, adjust the slideshow height on mobile to match the desktop aspect ratio.
3. If the user cannot make a slideshow shorter, check other slides — an element on another slide may be preventing it from shrinking.

Elements only appearing on mobile

1. Elements that appear only on mobile and are not updated like their desktop counterparts are likely **Mobile Only** elements. Refer to Wix Editor: Adding and Customizing Mobile-Only Elements for full details.

Resolution Confirmation

Confirm the Mobile Editor issue has been identified and resolved. If the issue was a known bug with a workaround applied, confirm the case has been escalated with the relevant reference included. If the issue involved an unsupported feature, confirm the user was informed. If unresolved, confirm all troubleshooting steps and device information have been documented before escalating to **Escalations - Editor & Mobile**.