# **HDFS File System Shell Guide**

# **Table of contents**

1	Overview	. 3
	1.1 cat	3
	1.2 chgrp	3
	1.3 chmod	. 3
	1.4 chown	3
	1.5 copyFromLocal	. 4
	1.6 copyToLocal	. 4
	1.7 count	. 4
	1.8 cp	. 4
	1.9 du	5
	1.10 dus	5
	1.11 expunge	5
	1.12 get	. 5
	1.13 getmerge	5
	1.14 ls	6
	1.15 lsr	6
	1.16 mkdir	6
	1.17 moveFromLocal	6
	1.18 moveToLocal	7
	1.19 mv	. 7
	1.20 put	. 7
	1.21 rm	
	1.22 rmr	8

1.23 setrep	8
1.24 stat	
1.25 tail	
1.26 test	
1.27 text	
1.28 touchz	
1.28 fouchz	9

### 1 Overview

The FileSystem (FS) shell is invoked by bin/hadoop fs <args>. All FS shell commands take path URIs as arguments. The URI format is *scheme://autority/path*. For HDFS the scheme is *hdfs*, and for the local filesystem the scheme is *file*. The scheme and authority are optional. If not specified, the default scheme specified in the configuration is used. An HDFS file or directory such as */parent/child* can be specified as *hdfs://namenodehost/parent/child* or simply as */parent/child* (given that your configuration is set to point to *hdfs://namenodehost*). Most of the commands in FS shell behave like corresponding Unix commands. Differences are described with each of the commands. Error information is sent to *stderr* and the output is sent to *stdout*.

#### 1.1 cat

```
Usage: hadoop fs -cat URI [URI ...]
Copies source paths to stdout.
```

# Example:

- hadoop fs -cat hdfs://nn1.example.com/file1 hdfs:// nn2.example.com/file2
- hadoop fs -cat file:///file3 /user/hadoop/file4

#### Exit Code:

Returns 0 on success and -1 on error.

# 1.2 chgrp

```
Usage: hadoop fs -chgrp [-R] GROUP URI [URI ...]
```

Change group association of files. With -R, make the change recursively through the directory structure. The user must be the owner of files, or else a super-user. Additional information is in the HDFS Admin Guide: Permissions.

#### 1.3 chmod

```
Usage: hadoop fs -chmod [-R] <MODE[,MODE]... | OCTALMODE> URI
[URI ...]
```

Change the permissions of files. With -R, make the change recursively through the directory structure. The user must be the owner of the file, or else a super-user. Additional information is in the HDFS Admin Guide: Permissions.

#### 1.4 chown

```
Usage: hadoop fs -chown [-R] [OWNER][:[GROUP]] URI [URI ]
```

Change the owner of files. With -R, make the change recursively through the directory structure. The user must be a super-user. Additional information is in the <u>HDFS Admin</u> Guide: Permissions.

# 1.5 copyFromLocal

Usage: hadoop fs -copyFromLocal <localsrc> URI Similar to put command, except that the source is restricted to a local file reference.

# 1.6 copyToLocal

```
Usage: hadoop fs -copyToLocal [-ignorecrc] [-crc] URI
<localdst>
```

Similar to **get** command, except that the destination is restricted to a local file reference.

#### 1.7 count

```
Usage: hadoop fs -count [-q] <paths>
```

Count the number of directories, files and bytes under the paths that match the specified file pattern. The output columns are:

```
DIR_COUNT, FILE_COUNT, CONTENT_SIZE FILE_NAME.
```

The output columns with -q are:

QUOTA, REMAINING\_QUATA, SPACE\_QUOTA, REMAINING\_SPACE\_QUOTA, DIR\_COUNT, FILE\_COUNT, CONTENT\_SIZE, FILE\_NAME.

## Example:

- hadoop fs -count hdfs://nn1.example.com/file1 hdfs:// nn2.example.com/file2
- hadoop fs -count -q hdfs://nnl.example.com/file1

# Exit Code:

Returns 0 on success and -1 on error.

## 1.8 cp

```
Usage: hadoop fs -cp URI [URI ...] <dest>
```

Copy files from source to destination. This command allows multiple sources as well in which case the destination must be a directory.

# Example:

- hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2
- hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2 /user/hadoop/dir

#### Exit Code:

Returns 0 on success and -1 on error.

#### 1.9 du

Usage: hadoop fs -du URI [URI ...]

Displays aggregate length of files contained in the directory or the length of a file in case its just a file.

## Example:

hadoop fs -du /user/hadoop/dir1 /user/hadoop/file1 hdfs://
nn.example.com/user/hadoop/dir1

Exit Code:

Returns 0 on success and -1 on error.

#### 1.10 dus

Usage: hadoop fs -dus <args>

Displays a summary of file lengths.

# 1.11 expunge

Usage: hadoop fs -expunge

Empty the Trash. Refer to HDFS Architecture for more information on Trash feature.

## 1.12 get

Usage: hadoop fs -get [-ignorecrc] [-crc] <src> <localdst>

Copy files to the local file system. Files that fail the CRC check may be copied with the - ignorecre option. Files and CRCs may be copied using the -cre option.

## Example:

- hadoop fs -get /user/hadoop/file localfile
- hadoop fs -get hdfs://nn.example.com/user/hadoop/file localfile

## Exit Code:

Returns 0 on success and -1 on error.

## 1.13 getmerge

Usage: hadoop fs -getmerge <src> <localdst> [addnl]

Takes a source directory and a destination file as input and concatenates files in src into the destination local file. Optionally addnl can be set to enable adding a newline character at the end of each file.

#### 1.14 Is

Usage: hadoop fs -ls <args>

For a file returns stat on the file with the following format:

permissions number\_of\_replicas userid groupid filesize modification\_date modification\_time filename

For a directory it returns list of its direct children as in unix. A directory is listed as:

permissions userid groupid modification\_date modification\_time dirname

# Example:

hadoop fs -ls /user/hadoop/file1

Exit Code:

Returns 0 on success and -1 on error.

## 1.15 Isr

Usage: hadoop fs -lsr <args>
Recursive version of ls. Similar to Unix ls -R.

## 1.16 mkdir

Usage: hadoop fs -mkdir <paths>

Takes path uri's as argument and creates directories. The behavior is much like unix mkdir -p creating parent directories along the path.

# Example:

- hadoop fs -mkdir /user/hadoop/dir1 /user/hadoop/dir2
- hadoop fs -mkdir hdfs://nn1.example.com/user/hadoop/dir hdfs://nn2.example.com/user/hadoop/dir

## Exit Code:

Returns 0 on success and -1 on error.

## 1.17 moveFromLocal

Usage: dfs -moveFromLocal <localsrc> <dst>

Similar to **put** command, except that the source localsrc is deleted after it's copied.

## 1.18 moveToLocal

Usage: hadoop fs -moveToLocal [-crc] <src> <dst> Displays a "Not implemented yet" message.

#### 1.19 mv

Usage: hadoop fs -mv URI [URI ...] <dest>

Moves files from source to destination. This command allows multiple sources as well in which case the destination needs to be a directory. Moving files across filesystems is not permitted.

## Example:

- hadoop fs -mv /user/hadoop/file1 /user/hadoop/file2
- hadoop fs -mv hdfs://nn.example.com/file1 hdfs:// nn.example.com/file2 hdfs://nn.example.com/file3 hdfs:// nn.example.com/dir1

### Exit Code:

Returns 0 on success and -1 on error.

## 1.20 put

Usage: hadoop fs -put <localsrc> ... <dst>

Copy single src, or multiple srcs from local file system to the destination filesystem. Also reads input from stdin and writes to destination filesystem.

- hadoop fs -put localfile /user/hadoop/hadoopfile
- hadoop fs -put localfile1 localfile2 /user/hadoop/hadoopdir
- hadoop fs -put localfile hdfs://nn.example.com/hadoop/ hadoopfile
- hadoop fs -put hdfs://nn.example.com/hadoop/hadoopfile Reads the input from stdin.

## Exit Code:

Returns 0 on success and -1 on error.

## 1.21 rm

Usage: hadoop fs -rm [-skipTrash] URI [URI ...]

Delete files specified as args. Only deletes non empty directory and files. If the -skipTrash option is specified, the trash, if enabled, will be bypassed and the specified file(s) deleted immediately. This can be useful when it is necessary to delete files from an over-quota directory. Refer to rmr for recursive deletes.

 hadoop fs -rm hdfs://nn.example.com/file /user/hadoop/ emptydir

## Exit Code:

Example:

Returns 0 on success and -1 on error.

## 1.22 rmr

```
Usage: hadoop fs -rmr [-skipTrash] URI [URI ...]
```

Recursive version of delete. If the <code>-skipTrash</code> option is specified, the trash, if enabled, will be bypassed and the specified file(s) deleted immediately. This can be useful when it is necessary to delete files from an over-quota directory.

# Example:

- hadoop fs -rmr /user/hadoop/dir
- hadoop fs -rmr hdfs://nn.example.com/user/hadoop/dir

## Exit Code:

Returns 0 on success and -1 on error.

# 1.23 setrep

```
Usage: hadoop fs -setrep [-R] <path>
```

Changes the replication factor of a file. -R option is for recursively increasing the replication factor of files within a directory.

## Example:

• hadoop fs -setrep -w 3 -R /user/hadoop/dir1

## Exit Code:

Returns 0 on success and -1 on error.

## 1.24 stat

Usage: hadoop fs -stat URI [URI ...]

Returns the stat information on the path.

Example:

• hadoop fs -stat path

## Exit Code:

Returns 0 on success and -1 on error.

#### 1.25 tail

Usage: hadoop fs -tail [-f] URI

Displays last kilobyte of the file to stdout. -f option can be used as in Unix.

# Example:

• hadoop fs -tail pathname

#### Exit Code:

Returns 0 on success and -1 on error.

#### 1.26 test

Usage: hadoop fs -test -[ezd] URI

# Options:

- -e check to see if the file exists. Return 0 if true.
- -z check to see if the file is zero length. Return 0 if true.
- -d check to see if the path is directory. Return 0 if true.

## Example:

• hadoop fs -test -e filename

## 1.27 text

Usage: hadoop fs -text <src>

Takes a source file and outputs the file in text format. The allowed formats are zip and TextRecordInputStream.

## 1.28 touchz

Usage: hadoop fs -touchz URI [URI ...]

Create a file of zero length.

## Example:

• hadoop -touchz pathname

# Exit Code:

Returns 0 on success and -1 on error.