

SVM MANAGEMENT:

Create a new SVM.

```
P90-C::> vservers create -vservers vnas -subtype default -rootvolume root_vnas -aggregate aggr1 -rootvolume-security-style unix -language C.UTF-8 -snapshot-policy default -is-repository false -foreground true
[Job 23] Job succeeded:
Vserver creation completed

P90-C::> vservers show
```

Vserver	Type	Subtype	Admin State	Operational State	Root Volume	Aggregate
P90-C	admin	-	-	-	-	-
P90-C-01	node	-	-	-	-	-
vnas	data	default	running	running	root_vnas	aggr1

```
3 entries were displayed.

P90-C::>
```

NetApp OnCommand System Manager

Help | Administration | admin | Sign Out

Dashboard | Volumes | **SVMs** | Network | Hardware and Diagnostics | Protection | Configurations

All Search

SVMs

Create Edit Delete Start Stop Manage Refresh

Name	State	Subtype	Allowed Protocols	IPspace	Volume Type	Configuration State
vnas	running	default	NFS, CIFS, FC/FCoE, iSCSI	Default	FlexVol Volume	Unlocked

Details

Protocols: [NFS](#) [CIFS](#) [FC/FCoE](#) [iSCSI](#)

Administrative User: vsadmin(Locked)

Management Interface: [Add Interface](#)

Snapshot policy: default

NIS domain: -NA-

LDAP client: -NA-

Language: C.UTF-8

Peer Storage Virtual Machines

Name	Cluster	Status	Applications
------	---------	--------	--------------

Create SVM using System Manager.

Storage Virtual Machine (SVM) Setup

1
Enter SVM basic details

SVM Details

? Specify a unique name and the data protocols for the SVM

SVM Name:

? IPspace:

? Volume Type: ☒ FlexVol volumes ☐ Infinite Volume

An SVM can contain either multiple FlexVol volumes or a single Infinite Volume.
You cannot change the volume type of the SVM after you set it.

? Default Language:

The language of the SVM specifies the default language encoding setting for the SVM and its volumes. Using a setting that incorporates UTF-8 character encoding is recommended.

? Security Style:

? Root Aggregate:

DNS Configuration

Specify the DNS domain and name servers. DNS details are required to configure the CIFS protocol.

? Search Domains:

? Name Servers:

Submit & Continue Cancel

Storage Virtual Machine (SVM) Setup

1

2

Enter SVM basic details

Enter SVM administrator details

SVM Administration (optional)

? Specify the following details to enable host side applications such as SnapDrive and SnapManager

? To enable the SVM administrator to create volumes, you must assign aggregates to the SVM by using Edit SVM dialog

Administrator Details

User Name: vsadmin

Password:

Confirm Password:

Management Interface (LIF) Configuration for SVM

☒ Create a new LIF for SVM management

For CIFS and NFS protocols, data LIFs have management access enabled by default; therefore, create a new management LIF only if required. However, for iSCSI and FC/FCoE protocols, create a dedicated management LIF because data LIFs cannot be used for SVM management.

Assign IP Address: Without a subnet

IP Address: 10.2.2.30 [Change](#)

? Port: P90-C-01:e0d [Browse...](#)


Skip

Submit & Continue

Cancel

<http://senthil-it-infrastructure.blogspot.com/>

Senthilkumar Muthusamy



Listing, Adding and removing the VServer Protocols.

```
P90-C::>
P90-C::>
P90-C::> vserver show-protocols -vserver vnas

  Vserver: vnas
Protocols: nfs, cifs, fcp, iscsi, ndmp

P90-C::>
P90-C::> vserver show-protocols -vserver vsan

  Vserver: vsan
Protocols: ndmp

P90-C::> 
```

```
P90-C::> vserver add-protocols -vserver vsan nfs,cifs,fc,iscsi,ndmp

P90-C::> vserver show-protocols -vserver vsan

Vserver: vsan
Protocols: nfs, cifs, fc, iscsi, ndmp

P90-C::>
```

Stop and Start the SVMs.

```
P90-C::> vserver stop -vserver vsan
[Job 26] Job succeeded: DONE

P90-C::>
P90-C::> vserver show
```

Vserver	Type	Subtype	Admin State	Operational State	Root Volume	Aggregate
P90-C	admin	-	-	-	-	-
P90-C-01	node	-	-	-	-	-
vnas	data	default	running	running	root_vnas	aggr1
vsan	data	default	stopped	stopped	vsan_root	aggr2

4 entries were displayed.

```
P90-C::>
```

NetApp OnCommand System Manager							Help	Administration	admin	Sign Out
Dashboard	Volumes	SVMs	Network	Hardware and Diagnostics	Protection	Configurations	All	Search	+	-
SVMs										
Create Edit Delete Start Stop Manage Refresh										
Name	State	Subtype	Allowed Protocols	IPspace	Volume Type	Configuration State				
vnas	running	default	NFS, CIFS, FC/FCoE, iSCSI	Default	FlexVol Volume	Unlocked				
vsan	stopped	default	NFS, CIFS, FC/FCoE, iSCSI	Default	FlexVol Volume	Unlocked				