回到首页

Q

我是一段不羁的公告!

记得给艿艿这 3 个项目加油,添加一个 STAR 噢。 https://github.com/YunaiV/SpringBoot-Labs https://github.com/YunaiV/onemall https://github.com/YunaiV/ruoyi-vue-pro

NETTY

精尽 Netty 源码解析 —— Buffer 之 ByteBufAllocator (三) PooledByteBufAllocator

1. 概述

本文,我们来分享 PooledByteBufAllocator ,基于**内存池**的 ByteBuf 的分配器。而 PooledByteBufAllocator 的内存池,是基于 **Jemalloc** 算法进行分配管理,所以在看本文之前,胖友先跳到 《精尽 Netty 源码解析 —— Buffer 之 Jemalloc (一) 简介》,将 Jemalloc 相关的**几篇**文章看完,在回到此处。

文章目录

- 1. 概述
- 2. PooledByteBufAllocatorMetric
- 3. PooledByteBufAllocator
 - 3.1 静态属性
 - 3.2 validateAndCalculatePageShifts
 - 3.3 validateAndCalculateChunkSize
 - 3.4 构造方法
 - 3.5 newHeapBuffer
 - 3.6 newDirectBuffer
 - 3.6 其它方法
- 4. PoolThreadLocalCache
 - 4.1 构造方法
 - 4.2 leastUsedArena
 - 4.3 initialValue
 - 4.4 onRemoval
- 666. 彩蛋

rMetric

:ric , 实现 ByteBufAllocatorMetric 接口, PooledByteBufAllocator

```
Metric implements ByteBufAllocatorMetric {
```

allocator;

teBufAllocator allocator) {

```
*/
public int numHeapArenas() {
    return allocator.numHeapArenas();
}
/**
    * Return the number of direct arenas.
    */
public int numDirectArenas() {
    return allocator.numDirectArenas();
}

/**
    * Return a {@link List} of all heap {@link PoolArenaMetric}s that are provided by this pool.
    */
```

```
public List<PoolArenaMetric> heapArenas() {
        return allocator.heapArenas();
    }
    /**
     * Return a {@link List} of all direct {@link PoolArenaMetric}s that are provided by this pool.
    public List<PoolArenaMetric> directArenas() {
        return allocator.directArenas();
    }
     * Return the number of thread local caches used by this {@link PooledByteBufAllocator}.
    public int numThreadLocalCaches() {
        return allocator.numThreadLocalCaches();
    }
     * Return the size of the tiny cache.
    public int tinyCacheSize() {
        return allocator.tinyCacheSize();
文章目录
  1. 概述
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
                                          );
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
    4.4 onRemoval
  666. 彩蛋
        return allocator.chunkSize();
    }
    @Override
    public long usedHeapMemory() {
        return allocator.usedHeapMemory();
    }
    @Override
    public long usedDirectMemory() {
        return allocator.usedDirectMemory();
    @Override
    public String toString() {
```

无

• 每个实现方法,都是调用 allocator 对应的方法。通过 PooledByteBufAllocatorMetric 的封装,可以统一获得 PooledByteBufAllocator Metric 相关的信息。

3. PooledByteBufAllocator

```
文章目录
                                         实现 ByteBufAllocatorMetricProvider 接口,实现
  1. 概述
                                        teBuf 的分配器。
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
                                         ARENA;
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
                                        CT ARENA;
    4.3 initialValue
    4.4 onRemoval
  666. 彩蛋
 * 默认配置, 8192 B = 8 KB
private static final int DEFAULT_PAGE_SIZE;
 * {@link PoolChunk} 满二叉树的高度,默认为 11 。
private static final int DEFAULT_MAX_ORDER; // 8192 << 11 = 16 MiB per chunk
 * 默认 {@link PoolThreadCache} 的 tiny 类型的内存块的缓存数量。默认为 512 。
 * @see #tinyCacheSize
private static final int DEFAULT_TINY_CACHE_SIZE;
```

```
* 默认 {@link PoolThreadCache} 的 small 类型的内存块的缓存数量。默认为 256 。
 * @see #smallCacheSize
private static final int DEFAULT SMALL CACHE SIZE;
 * 默认 {@link PoolThreadCache} 的 normal 类型的内存块的缓存数量。默认为 64 。
 * @see #normalCacheSize
private static final int DEFAULT NORMAL CACHE SIZE;
 * 默认 {@link PoolThreadCache} 缓存的内存块的最大字节数
private static final int DEFAULT MAX CACHED BUFFER CAPACITY;
 * 默认 {@link PoolThreadCache}
private static final int DEFAULT_CACHE_TRIM_INTERVAL;
/**
 * 默认是否使用 {@link PoolThreadCache}
文章目录
                                         CACHE FOR ALL THREADS;
  1. 概述
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
                                        EMORY CACHE ALIGNMENT;
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
                                         4096;
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
                                         (int) (((long) Integer.MAX VALUE + 1) / 2);
    4.4 onRemoval
  666. 彩蛋
    // 初始化 DEFAULT PAGE SIZE
    int defaultPageSize = SystemPropertyUtil.getInt("io.netty.allocator.pageSize", 8192);
    Throwable pageSizeFallbackCause = null;
    try {
        validateAndCalculatePageShifts(defaultPageSize);
    } catch (Throwable t) {
        pageSizeFallbackCause = t;
        defaultPageSize = 8192;
    DEFAULT_PAGE_SIZE = defaultPageSize;
    // 初始化 DEFAULT MAX ORDER
    int defaultMaxOrder = SystemPropertyUtil.getInt("io.netty.allocator.maxOrder", 11);
    Throwable maxOrderFallbackCause = null;
```

```
trv {
        validateAndCalculateChunkSize(DEFAULT_PAGE_SIZE, defaultMaxOrder);
    } catch (Throwable t) {
        maxOrderFallbackCause = t;
        defaultMaxOrder = 11;
    DEFAULT MAX ORDER = defaultMaxOrder;
    // Determine reasonable default for nHeapArena and nDirectArena.
    // Assuming each arena has 3 chunks, the pool should not consume more than 50% of max memory.
    final Runtime runtime = Runtime.getRuntime();
     * We use 2 * available processors by default to reduce contention as we use 2 * available process
     * number of EventLoops in NIO and EPOLL as well. If we choose a smaller number we will run into h
     * allocation and de-allocation needs to be synchronized on the PoolArena.
     * See https://github.com/netty/netty/issues/3888.
    // 默认最小 Arena 个数。为什么这样计算,见上面的英文注释,大体的思路是,一个 EventLoop 一个 Arena ,避免多
    final int defaultMinNumArena = NettyRuntime.availableProcessors() * 2;
    // 初始化默认 Chunk 的内存大小。默认值为 8192 << 11 = 16 MiB per chunk
                                         PAGE SIZE << DEFAULT MAX ORDER;
東目章文
  1. 概述
  2. PooledByteBufAllocatorMetric
                                         umHeapArenas",
  3. PooledByteBufAllocator
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
                                         Arena,
                                         nory() / defaultChunkSize / 2 / 3))); // `/ 2` 是为了不超过内存
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
                                         umDirectArenas",
  4. PoolThreadLocalCache
    4.1 构造方法
                                         Arena.
    4.2 leastUsedArena
                                         dent.maxDirectMemory() / defaultChunkSize / 2 / 3)));
    4.3 initialValue
    4.4 onRemoval
  666. 彩蛋
    DEFAULT TINY CACHE SIZE = SystemPropertyUtil.getInt("io.netty.allocator.tinyCacheSize", 512);
    // 初始化 DEFAULT SMALL CACHE SIZE
    DEFAULT_SMALL_CACHE_SIZE = SystemPropertyUtil.getInt("io.netty.allocator.smallCacheSize", 256);
    // 初始化 DEFAULT NORMAL CACHE SIZE
    DEFAULT_NORMAL_CACHE_SIZE = SystemPropertyUtil.getInt("io.netty.allocator.normalCacheSize", 64);
    // 初始化 DEFAULT_MAX_CACHED_BUFFER_CAPACITY
    // 32 kb is the default maximum capacity of the cached buffer. Similar to what is explained in
    // 'Scalable memory allocation using jemalloc'
    DEFAULT_MAX_CACHED_BUFFER_CAPACITY = SystemPropertyUtil.getInt("io.netty.allocator.maxCachedBuffer")
    // 初始化 DEFAULT CACHE TRIM INTERVAL
    // the number of threshold of allocations when cached entries will be freed up if not frequently u
    DEFAULT_CACHE_TRIM_INTERVAL = SystemPropertyUtil.getInt("io.netty.allocator.cacheTrimInterval", 81
```

```
// 初始化 DEFAULT_USE_CACHE_FOR_ALL_THREADS
DEFAULT_USE_CACHE_FOR_ALL_THREADS = SystemPropertyUtil.getBoolean("io.netty.allocator.useCacheForA

// 初始化 DEFAULT_DIRECT_MEMORY_CACHE_ALIGNMENT
DEFAULT_DIRECT_MEMORY_CACHE_ALIGNMENT = SystemPropertyUtil.getInt("io.netty.allocator.directMemory

// 打印调试日志(省略...)
}
```

- 静态变量有点多,主要是为 PoolThreadCache 做的**默认**配置项。读过《精尽 Netty 源码解析 —— Buffer 之 Jemalloc (六) PoolThreadCache》的胖友,是不是灰常熟悉。
- 比较有意思的是, DEFAULT NUM HEAP ARENA 和 DEFAULT NUM DIRECT ARENA 变量的初始化,在 <1> 处。
 - 默认情况下,最小值是 NettyRuntime.availableProcessors() * 2 ,也就是 CPU 线程数。这样的好处是, 一个 EventLoop 一个 Arena, 避免多线程竞争。更多的讨论,胖友可以看看 https://github.com/netty/netty/issues/3888。
 - 比较有趣的一段是 runtime.maxMemory() / defaultChunkSize / 2 / 3 代码块。其中, / 2 是为了保证 Arena 不超过内存的一半,而 / 3 是为了每个 Arena 有三个 Chunk 。
 - 当然最终取值是上述两值的最小值。所以在推荐上,尽可能配置的内存,能够保证 defaultMinNumArena 。因为要避免多线程竞争。

```
文章目录
                                         ts
  1. 概述
                                         ize) 方法,校验 pageSize 参数,并计算 pageShift 值。代码如
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
                                         geShifts(int pageSize) {
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
                                         n("pageSize: " + pageSize + " (expected: " + MIN_PAGE_SIZE +
    3.5 newHeapBuffer
    3.6 newDirectBuffer
                                         级
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
                                         n("pageSize: " + pageSize + " (expected: power of 2)");
    4.2 leastUsedArena
    4.3 initialValue
    4.4 onRemoval
  666. 彩蛋
                                          know that pageSize is a power of two.
                                         berOfLeadingZeros(pageSize);
}
```

• 默认情况下, pageSize = 8KB = 8 * 1024= 8096 , pageShift = 8192 。

3.3 validateAndCalculateChunkSize

#validateAndCalculateChunkSize(int pageSize, int maxOrder) 方法, 校验 maxOrder 参数, 并计算 chunkSize 值。代码如下:

```
private static int validateAndCalculateChunkSize(int pageSize, int maxOrder) {
   if (maxOrder > 14) {
     throw new IllegalArgumentException("maxOrder: " + maxOrder + " (expected: 0-14)");
```

无

3.4 构造方法

```
/**
 * 单例
 */
                                        DEFAULT = new PooledByteBufAllocator(PlatformDependent.dire
文章目录
  1. 概述
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
                                        nas;
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
                                        ectArenas;
    3.6 newDirectBuffer
    3.6 其它方法
                                        爰存数组的大小
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
                                        缓存数组的大小
    4.4 onRemoval
  666. 彩蛋
/**
 * {@link PoolThreadCache} 的 normal 内存块缓存数组的大小
private final int normalCacheSize;
 * PoolArenaMetric 数组
private final List<PoolArenaMetric> heapArenaMetrics;
/**
 * PoolArenaMetric 数组
private final List<PoolArenaMetric> directArenaMetrics;
 * 线程变量,用于获得 PoolThreadCache 对象。
```

```
private final PoolThreadLocalCache threadCache;
 * Chunk 大小
 */
private final int chunkSize;
/**
 * PooledByteBufAllocatorMetric 对象
private final PooledByteBufAllocatorMetric metric;
public PooledByteBufAllocator() {
    this(false);
}
@SuppressWarnings("deprecation")
public PooledByteBufAllocator(boolean preferDirect) {
    this(preferDirect, DEFAULT_NUM_HEAP_ARENA, DEFAULT_NUM_DIRECT_ARENA, DEFAULT_PAGE_SIZE, DEFAULT_MA
}
@SuppressWarnings("deprecation")
public PooledByteBufAllocator(int nHeapArena, int nDirectArena, int pageSize, int maxOrder) {
                                          pageSize, maxOrder);
文章目录
  1. 概述
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
                                          teBufAllocator(boolean, int, int, int, int, int, int, bo
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
                                          ferDirect, int nHeapArena, int nDirectArena, int pageSize, in
    3.5 newHeapBuffer
                                          tArena, pageSize, maxOrder,
    3.6 newDirectBuffer
                                          JLT SMALL CACHE SIZE, DEFAULT NORMAL CACHE SIZE);
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
                                          teBufAllocator(boolean, int, int, int, int, int, int, bo
    4.4 onRemoval
  666. 彩蛋
public PooledByteButAllocator(boolean preferDirect, int nHeapArena, int nDirectArena, int pageSize, in
                              int tinyCacheSize, int smallCacheSize, int normalCacheSize) {
    this(preferDirect, nHeapArena, nDirectArena, pageSize, maxOrder, tinyCacheSize, smallCacheSize,
            normalCacheSize, DEFAULT USE CACHE FOR ALL THREADS, DEFAULT DIRECT MEMORY CACHE ALIGNMENT)
}
public PooledByteBufAllocator(boolean preferDirect, int nHeapArena,
                              int nDirectArena, int pageSize, int maxOrder, int tinyCacheSize,
                              int smallCacheSize, int normalCacheSize,
                              boolean useCacheForAllThreads) {
    this(preferDirect, nHeapArena, nDirectArena, pageSize, maxOrder,
            tinyCacheSize, smallCacheSize, normalCacheSize,
            useCacheForAllThreads, DEFAULT_DIRECT_MEMORY_CACHE_ALIGNMENT);
}
```

2023/10/27 17:50

```
public PooledByteBufAllocator(boolean preferDirect, int nHeapArena, int nDirectArena, int pageSize, in
                               int tinyCacheSize, int smallCacheSize, int normalCacheSize,
                               boolean useCacheForAllThreads, int directMemoryCacheAlignment) {
    super(preferDirect);
    // 创建 PoolThreadLocalCache 对象
    threadCache = new PoolThreadLocalCache(useCacheForAllThreads);
    this.tinyCacheSize = tinyCacheSize;
    this.smallCacheSize = smallCacheSize;
    this.normalCacheSize = normalCacheSize;
    // 计算 chunkSize
    chunkSize = validateAndCalculateChunkSize(pageSize, maxOrder);
    if (nHeapArena < 0) {
        throw new IllegalArgumentException("nHeapArena: " + nHeapArena + " (expected: >= 0)");
    }
    if (nDirectArena < 0) {</pre>
        throw new IllegalArgumentException("nDirectArea: " + nDirectArena + " (expected: >= 0)");
    }
    if (directMemoryCacheAlignment < 0) {</pre>
        throw new IllegalArgumentException("directMemoryCacheAlignment: "
                                          ent + " (expected: >= 0)");
東目章文
                                           !isDirectMemoryCacheAlignmentSupported()) {
  1. 概述
                                          n("directMemoryCacheAlignment is not supported");
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
                                          rectMemoryCacheAlignment) != directMemoryCacheAlignment) {
    3.2 validateAndCalculatePageShifts
                                          n("directMemoryCacheAlignment: "
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
                                          ent + " (expected: power of two)");
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
                                          PageShifts(pageSize);
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
                                          rena);
    4.4 onRemoval
  666. 彩蛋
                                          ew ArrayList<PoolArenaMetric>(heapArenas.length);
        // 初始化 heapArenas 和 metrics 数组
        for (int i = 0; i < heapArenas.length; i ++) {
            // 创建 HeapArena 对象
            PoolArena.HeapArena arena = new PoolArena.HeapArena(this,
                    pageSize, maxOrder, pageShifts, chunkSize,
                    directMemoryCacheAlignment);
            heapArenas[i] = arena;
            metrics.add(arena);
        heapArenaMetrics = Collections.unmodifiableList(metrics);
    } else {
        heapArenas = null;
        heapArenaMetrics = Collections.emptyList();
    }
```

```
    orz 代码比较长,主要是构造方法和校验代码比较长。胖友自己耐心看下。笔者下面只重点讲几个属性。

▲ DEFAULT 輪木居性 Pooled Ryte Ruf Allocator 单例。绝绝绝大多数情况下,我们不需要自己创建
                                      即可。
文章目录
                                      ThreadCache 对象。通过该属性,不同线程虽然使用相同的
  1. 概述
                                      adCache 对象。关于 PoolThreadLocalCache 的详细解析,见「4.
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
                                      Arena 数组。代码如下:
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
                                      enaArray(int size) {
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
                                      laxCapacity) 方法,创建 Heap ByteBuf 对象。代码如下:
    4.3 initialValue
    4.4 onRemoval
  666. 彩蛋
                                      alCapacity, int maxCapacity) {
    // <1> 获得线程的 PoolThreadCache 对象
    PoolThreadCache cache = threadCache.get();
    PoolArena<byte[]> heapArena = cache.heapArena;
    // <2.1> 从 heapArena 中,分配 Heap PooledByteBuf 对象,基于池化
    final ByteBuf buf;
    if (heapArena != null) {
       buf = heapArena.allocate(cache, initialCapacity, maxCapacity);
    // <2.2> 直接创建 Heap ByteBuf 对象,基于非池化
    } else {
```

new UnpooledUnsafeHeapByteBuf(this, initialCapacity, maxCapacity) :

new UnpooledHeapByteBuf(this, initialCapacity, maxCapacity);

}

buf = PlatformDependent.hasUnsafe() ?

```
// <3> 将 ByteBuf 装饰成 LeakAware ( 可检测内存泄露 )的 ByteBuf 对象 return toLeakAwareBuffer(buf);
}
```

• 代码比较易懂, 胖友自己看代码注释。

3.6 newDirectBuffer

#newDirectBuffer(int initialCapacity, int maxCapacity) 方法, 创建 Direct ByteBuf 对象。代码如下:

```
@Override
protected ByteBuf newDirectBuffer(int initialCapacity, int maxCapacity) {
    // <1> 获得线程的 PoolThreadCache 对象
    PoolThreadCache cache = threadCache.get();
    PoolArena<ByteBuffer> directArena = cache.directArena;
    final ByteBuf buf;
    // <2.1> 从 directArena 中, 分配 Direct PooledByteBuf 对象,基于池化
    if (directArena != null) {
                                         initialCapacity, maxCapacity);
文章目录
                                         基于非池化
  1. 概述
                                        () ?
  2. PooledByteBufAllocatorMetric
                                        feDirectByteBuf(this, initialCapacity, maxCapacity) :
  3. PooledByteBufAllocator
                                        (this, initialCapacity, maxCapacity);
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
                                        「检测内存泄露 )的 ByteBuf 对象
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
    4.3 initialValue
    4.4 onRemoval
                                        事多做哔哔啦,胖友自己感兴趣的话,可以翻翻噢。
  666. 彩蛋
```

4. PoolThreadLocalCache

PoolThreadLocalCache ,是 PooledByteBufAllocator 的内部类。继承 FastThreadLocal 抽象类,PoolThreadCache **ThreadLocal** 类。

4.1 构造方法

```
/**
 * 是否使用缓存
 */
private final boolean useCacheForAllThreads;
```

```
PoolThreadLocalCache(boolean useCacheForAllThreads) {
   this.useCacheForAllThreads = useCacheForAllThreads;
}
```

4.2 leastUsedArena

#leastUsedArena(PoolArena<T>[] arenas) 方法,从 PoolArena 数组中,获取线程使用最少的 PoolArena 对象,基于 PoolArena.numThreadCaches 属性。通过这样的方式,尽可能让 PoolArena 平均分布在不同线程,从而尽肯能避免线程的**同步和竞争**问题。代码如下:

```
private <T> PoolArena<T> leastUsedArena(PoolArena<T>[] arenas) {
    // 一个都没有,返回 null
    if (arenas == null || arenas.length == 0) {
        return null;
    }
    // 获得第零个 PoolArena 对象
    PoolArena<T> minArena = arenas[0];
    // 比较后面的 PoolArena 对象,选择线程使用最少的
    for (int i = 1; i < arenas.length; i++) {</pre>
        PoolArena<T> arena = arenas[i];
                                         minArena.numThreadCaches.get()) {
文章目录
  1. 概述
  2. PooledByteBufAllocatorMetric
  3. PooledByteBufAllocator
    3.1 静态属性
    3.2 validateAndCalculatePageShifts
    3.3 validateAndCalculateChunkSize
    3.4 构造方法
    3.5 newHeapBuffer
    3.6 newDirectBuffer
                                         adCache 对象。代码如下:
    3.6 其它方法
  4. PoolThreadLocalCache
    4.1 构造方法
    4.2 leastUsedArena
                                         itialValue() {
    4.3 initialValue
                                         firectArena 对象,基于 `PoolArena.numThreadCaches` 属性。
    4.4 onRemoval
                                         eastUsedArena(heapArenas);
  666. 彩蛋
                                         na = leastUsedArena(directArenas);
    // 创建开启缓存的 PoolThreadCache 对象
    Thread current = Thread.currentThread();
    if (useCacheForAllThreads || current instanceof FastThreadLocalThread) {
        return new PoolThreadCache(
                heapArena, directArena, tinyCacheSize, smallCacheSize, normalCacheSize,
                DEFAULT_MAX_CACHED_BUFFER_CAPACITY, DEFAULT_CACHE_TRIM_INTERVAL);
    }
    // 创建不进行缓存的 PoolThreadCache 对象
    // No caching so just use 0 as sizes.
    return new PoolThreadCache(heapArena, directArena, 0, 0, 0, 0, 0);
}
```

2023/10/27 17:50

4.4 onRemoval

#onRemoval(PoolThreadCache threadCache) 方法,释放 PoolThreadCache 对象的缓存。代码如下:

```
@Override
protected void onRemoval(PoolThreadCache threadCache) {
    // 释放缓存
    threadCache.free();
}
```

无

666. 彩蛋

推荐阅读文章:

- 杨武兵 《netty源码分析系列——PooledByteBuf&PooledByteBufAllocator》
- wojiushimogui 《Netty源码分析: PooledByteBufAllocator》
- RobertoHuang 《死磕Netty源码之内存分配详解(一)(PooledByteBufAllocator)》

文章目录

- 1. 概述
- 2. PooledByteBufAllocatorMetric
- 3. PooledByteBufAllocator
 - 3.1 静态属性
 - 3.2 validateAndCalculatePageShifts
 - 3.3 validateAndCalculateChunkSize
 - 3.4 构造方法
 - 3.5 newHeapBuffer
 - 3.6 newDirectBuffer
 - 3.6 其它方法
- 4. PoolThreadLocalCache
 - 4.1 构造方法
 - 4.2 leastUsedArena
 - 4.3 initialValue
 - 4.4 onRemoval
- 666. 彩蛋

量 6319095 次