


Step 1: Create the VPC

In this step, you'll use the Amazon VPC wizard in the Amazon VPC console to create a VPC. The wizard performs the following steps for you:

- Creates a VPC with a /16 CIDR block (a network with 65,536 private IP addresses). For more information about CIDR notation and the sizing of a VPC, see [Your VPC](#).
- Attaches an Internet gateway to the VPC. For more information about Internet gateways, see [Internet Gateways](#).
- Creates a size /24 subnet (a range of 256 private IP addresses) in the VPC.
- Creates a custom route table, and associates it with your subnet, so that traffic can flow between the subnet and the Internet gateway. For more information about route tables, see [Route Tables](#).

The following diagram represents the architecture of your VPC after you've completed this step.




Note

This exercise covers the first scenario in the VPC wizard. For more information about the other scenarios, see [Scenarios for Amazon VPC](#).

To create a VPC using the Amazon VPC Wizard

1. Open the Amazon VPC console at <https://console.aws.amazon.com/vpc/>.

2. In the navigation bar, on the top-right, take note of the region in which you'll be creating the VPC. Ensure that you continue working in the same region for the rest of this exercise, as you cannot launch an instance into your VPC from a different region. For more information about regions, see [Regions and Availability Zones](#).
3. In the navigation pane, choose **VPC dashboard**, and then choose **Start VPC Wizard**.



Note

Do not choose **Your VPCs** in the navigation pane; you cannot access the VPC wizard from this page.

4. Choose the first option, **VPC with a Single Public Subnet**, and then choose **Select**.
5. On the configuration page, enter a name for your VPC in the **VPC name** field; for example, `my-vpc`, and enter a name for your subnet in the **Subnet name** field. This helps you to identify the VPC and subnet in the Amazon VPC console after you've created them. For this exercise, you can leave the rest of the configuration settings on the page, and choose **Create VPC**.

(Optional) If you prefer, you can modify the configuration settings as follows, and then choose **Create VPC**.

- The **IP CIDR block** displays the IP address range that you'll use for your VPC (10.0.0.0/16), and the **Public subnet** field displays the IP address range you'll use for the subnet (10.0.0.0/24). If you don't want to use the default CIDR ranges, you can specify your own. For more information, see [VPC Sizing](#) and [Subnet Sizing](#).
- The **Availability Zone** list enables you to select the Availability Zone in which to create the subnet. You can leave **No Preference** to let AWS choose an Availability Zone for you. For more information, see [Regions and Availability Zones](#).
- In the **Add endpoints for S3 to your subnets** section, you can select a subnet in which to create a VPC endpoint to Amazon S3 in the same region. For more information, see [VPC Endpoints](#).
- The **Enable DNS hostnames** option, when set to **Yes**, ensures that instances that are launched into your VPC receive a DNS hostname. For more information, see [Using DNS with Your VPC](#).

more information, see [USING DNS WITH YOUR VPC](#).

- The **Hardware tenancy** option enables you to select whether instances launched into your VPC are run on shared or dedicated hardware. Selecting a dedicated tenancy incurs additional costs. For more information about hardware tenancy, see [Dedicated Instances](#).

6. A status window shows the work in progress. When the work completes, choose **OK** to close the status window.
7. The **Your VPCs** page displays your default VPC and the VPC that you just created. The VPC that you created is a nondefault VPC, therefore the **Default VPC** column displays **No**.



Viewing Information About Your VPC

After you've created the VPC, you can view information about the subnet, the Internet gateway, and the route tables. The VPC that you created has two route tables — a main route table that all VPCs have by default, and a custom route table that was created by the wizard. The custom route table is associated with your subnet, which means that the routes in that table determine how the traffic for the subnet flows. If you add a new subnet to your VPC, it uses the main route table by default.

To view information about your VPC

1. Open the Amazon VPC console at <https://console.aws.amazon.com/vpc/>.
2. In the navigation pane, choose **Your VPCs**. Take note of the name and the ID of the VPC that you created (look in the **Name** and **VPC ID** columns). You will use this information to identify the components that are associated with your VPC.
3. In the navigation pane, choose **Subnets**. The console displays the subnet that was created when you created your VPC. You can identify the subnet by its name in **Name** column, or you can use the VPC information that you obtained in the previous step and look in the **VPC** column.
4. In the navigation pane, choose **Internet Gateways**. You can find the Internet gateway that's attached to your VPC by looking at the **VPC** column, which displays the ID and the name (if applicable) of the VPC.

5. In the navigation pane, choose **Route Tables**. There are two route tables associated with the VPC. Select the custom route table (the **Main** column displays **No**), and then choose the **Routes** tab to display the route information in the details pane:

- The first row in the table is the local route, which enables instances within the VPC to communicate. This route is present in every route table by default, and you can't remove it.
- The second row shows the route that the Amazon VPC wizard added to enable traffic destined for an IP address outside the VPC (0.0.0.0/0) to flow from the subnet to the Internet gateway.

6. Select the main route table. The main route table has a local route, but no other routes.

[Document Conventions](#)

[« Previous](#) [Next »](#)

▼ [Terms of Use](#) | © 2016, Amazon Web Services, Inc. or its affiliates. All rights reserved.