Scheduler

XCAP allows you to schedule the creation of models on a weekly, monthly, or regular interval, depending on the schedule that you specify, or to proceed with the batch export function.

- Local mode – You can schedule a log in Local Drives.
  - (Single) Today: One time task to be executed today
  - (Single) Tomorrow: One time task to be executed tomorrow
  - (Repeat) Daily: Task to be repeated everyday
  - (Repeat) Weekly: Task to be repeated on specified day of a week

- FTP Mode – You can download the logs uploaded to the FTP server and schedule them to proceed.
  - (FTP) Realtime monitoring: FTP directory to be continuously accessed & monitored for logfiles. File naming convention is checked before downloading logfile.
  - (FTP) Specified time: FTP directory is accessed only one time to download all available logfiles.

Task	Real-Time Monitoring	Specific Time
FTP Access cycle	Continuous	1 Time
File naming convention check	If you want to use the model merge option, you need the file "Allfileuploadcompleted.txt" which is an identifier that all files have been uploaded.	Not mandatory
After download Logfile management	Moved to a sub directory named "_Comp_"	No movement
Retry	6 times (every 5 minutes)	No
Supported file format	*.drm, *.drx, *.scn, *scx, *.aof, *.aox, *.zip Compressed files (e.g. *.drx, *.scx, *.aox) recompressed in zip format are not supported.	


© Innowireless Co., Ltd. All rights reserved.

Management after downloading log files	When the model generation is completed normally, That log file is moved to the Completed folder. If the model generation is not completed normally, That log file is moved to the Quarantine folder

Local Mode

Procedure for using Local mode is as follows.

1. Select **[Tools] – [Scheduler]** from the menu bar.
2. The **[Scheduler]** screen will appear.



3. Set schedule options, model settings options, log file conditions and paths, and export options to Favorites.
4. Select the **[OK]** to finish the setting.

© Innowireless Co., Ltd. All rights reserved.


Example of setting the Local mode option

This section describes how to set the option to automatically create models every Monday, Wednesday, and Friday at 12:00 p.m. from October 16, 2015 to October 30, 2015.


1. Under Job Type, select [**(Repeat) Weekly**].

Job Type	Description	Sub Menu
None	Disable the Scheduler function	N/A
(Single) Today	Create a model at a fixed time today.	Time
(Single) Tomorrow	Create a model at a fixed time tomorrow.	Time
(Repeat) Daily	Create a model at a fixed time every day.	Time Start/End Date
(Repeat) Weekly	Create a model on a given day of the week, at a fixed time.	Date (day of the week) Time (time) Start/End Date (Start/End date)

2. Select a day of the week **[Select Date]** by clicking the Monday, Wednesday, and Friday buttons.



3. Select the time and start/end date.



4. [**From Local Drives**] Click the button to select the path where the log files for model creation are stored.

   Because the model is created using a log file located in the same path that you specify, the log file must be updated before the scheduler is operated. If you did not update, you can create the same model on Monday, Wednesday, and Friday using the same log file.


5. Set model generation options, such as [**Sampling Rate**], [**Separate**], [**Merge**].

   The default value is set to Sampling Rate 1 and Merge.

- [**Sampling Rate**]: Sorts log data based on the Sampling Interval value and plots the average value of that data.
- [**Separate**]: Models are created for each log file. Parameters in log files are sorted in file order, not in time order.
- [**Merge**]: Create a model using multiple log files. Data in the log file is sorted by file, not by time.

© Innowireless Co., Ltd. All rights reserved.

- [**Port Merge**]: The processing is the same as Merge, which uses measuring port information to categorize the logging files, collect files corresponding to the same port number, and create a model.
- [**PAF**]: When measuring, select the option if the log file is split (for example, Call by call or by file size).
- [**MtoM**]: For Mobile to Mobile measurement logs, set to Yes and set [Method] to Port Merge.
- [**Filter**]: You can set the Filter function to handle only files that meet certain conditions.



6. Sets the storage path for the model generated by [**Output Path (Models)**].
   - Click on the **...** button and the Open screen will appear.
   - Use the **[Add a date path]** option on the **[Open]** screen to create a date folder in the specified path and create a model in its subdirectory.
7. Select **[Extra Job (To Excel)]** and select the **[Batch Export Manager]** button to set the Batch Export option.


   For details, refer to **Chapter 4_Exporting Batch using Batch Export Feature.pdf**.
8. Click the **[OK]** button to complete the setting.

© Innowireless Co., Ltd. All rights reserved.


FTP Mode


FTP Mode has the following features:

- File management - Files (logs, models, exports) are stored in the "Backup files" folder when operating in FTP mode.



- Uploading - You can create an FTP subdirectory with a date or the original folder name.






© Innowireless Co., Ltd. All rights reserved.


Procedure for using FTP Mode is as follows.

1. Select [**Tools**] – [**Scheduler**] from the menu bar.
2. [**Scheduler**] screen will appear.



3. Set the time to connect to the FTP server. If you set up a schedule, you proceed with the task set at the same time within the time period.
4. Click the From FTP Server button to enter the information of the server you want to connect to.
5. If you want to process logs from different folders with different paths, use the Duplicate button to add server information and change Path.
6. You can set the priority using the Top, Up, Down, Bottom buttons below. The set priority can be found in Priority.
7. Once the Upload server is set up, you can upload the output file that you created using the Batch Export feature to a specific server.
8. Set model settings options and click the OK button.
9. Upon pressing the OK button, check whether the information on the set server is valid and provide the information in a separate notification window if the server is not connected or unknown.

© Innowireless Co., Ltd. All rights reserved.




10. Sets the path where the model generated by [**Output Path (Models)**] will be stored.
    - Click on the **...** button and the Open screen will appear.
    - Use the **[Add a date path]** option on the **[Open]** screen to create a date folder in the specified path and create a model in its subdirectory.
11. Select **[Extra Job (To Excel)]** and select the **[Batch Export Manager]** button to set the Batch Export option.
12. For details, refer to Chapter 4_Exporting Batch using Batch Export Feature.pdf.
13. Click the **[OK]** button to complete the setting.

© Innowireless Co., Ltd. All rights reserved.


Example of setting FTP Mode options

Examples include the procedure for extracting M to M call statistics by downloading logs from A server or uploading Favorite export results by Log File to B server.


1. Select [**Tools**] – [**Scheduler**] from the menu bar.
2. Select Job type as [**(FTP)Specific Time]**.
3. Click the **[From FTP Server]** button to enter the A server information in Download Server information, and in Upload Server information, enter the B server information as follows:



4. To extract M to M Statistics, set it as follows:



5. If you set M to M to M to Yes in the above window, the Model creation option is automatically set to Port Merge. The pair of M to M is set at Setting. The user must check the pair before M to M, and if it differs from the basic information, press Setting to change the setting.




6. Check **[Extra Jab(To Excel)]**, then click the Batch Export Manager button.
7. Check Call Statistics and click the Setting button to select **Voice/Video Call Statistics** and click the **[OK]** button to exit the setup.


© Innowireless Co., Ltd. All rights reserved.

8. Set the time [Time] for the scheduler.
9. Click the OK button to complete the setting.

B server Result-MtoM Statistics



B server Result-Favorite, Call Statistics




© Innowireless Co., Ltd. All rights reserved.

Example of FTP Mode Alarm options


In FTP Mode (Specific Time-ONLY), you can view and receive the results by e-mail.

In addition to report results, you can receive status reports by e-mail even if you cannot connect to the FTP server or cannot download logging files. Usage is as follows:

1. In the FTP Server setting window, select **[Alarm]**.




2. Select the item that requires an e-mail alarm and select the Setting icon.



3. Enter the recipient email address. If you want to send it to more than one person, enter the separator (;) and add it.

© Innowireless Co., Ltd. All rights reserved.



4. After entering SMTP Server and Secure connection information, click the "Send a test e-mail" button to check if the settings are normal.
5. The email will be sent in the following form.



© Innowireless Co., Ltd. All rights reserved.




Recommendation: We recommend using internal mail.

© Innowireless Co., Ltd. All rights reserved.


Example setup for using a network drive

You can process logs shared on Network Drive. the usage is as follows:

1. Select [**local]** type in the FTP Server setting window.



2. Enter User/Password.
3. Enter the path.
4. If the Delete log files in temporary folder option is set to yes, the copied logging files are deleted after extracting the output.



© Innowireless Co., Ltd. All rights reserved.