



USER GUIDE · V1.0.0

Tatanka AMT Toolkit

Auction Market Theory on one chart

TradingView & NinjaTrader 8 · October 2026 ·
tatankatrading.com

The Tatanka AMT Toolkit puts a complete Auction Market Theory read on one chart: where value is, whether the day is balanced or trending, who is trapped, what is unfinished and where your levels are. This guide explains everything it draws, how each piece is calculated and what every setting does, on both TradingView and NinjaTrader 8.

New to the Toolkit? Install it with the **Tatanka Indicators Setup Guide** first, then come back here.

IN THIS GUIDE

01 Overview

Page 2

02 Before you start

Page 2

03 The chart at a glance

Page 3

04 A trading day

Page 4

05 The dashboard

Page 5

06 Where is value?

Page 6

07 Balanced or trending?

Page 7

08 Who is trapped?

Page 10

09 What is unfinished?

Page 11

10 Reference prices

Page 12

11 Your daily levels

Page 13

12 Alerts

Page 14

13 Display & performance

Page 16

14 TradingView vs NinjaTrader

Page 17

15 Settings reference

Page 18

16 Glossary & help

Page 25

01 • OVERVIEW

How the Toolkit is organized

Every session, an auction read asks the same six questions. The Toolkit answers each one with a set of tools; it gives no buy or sell signals. Its settings and this guide follow the same order.

QUESTION 1

Where is value?

Developing volume profile (session, week, month or year), prior-day value, prior-month value, RTH VWAP.

QUESTION 2

Balanced or trending?

Initial balance, live day type, open location against prior value, the 80% Rule.

QUESTION 3

Who is trapped?

Overnight inventory against settlement, the trap flag, the late-day spike base.

QUESTION 4

What is unfinished?

Naked POCs (daily, weekly, monthly), single prints, poor highs and lows.

QUESTION 5

Which reference prices matter?

Overnight high and low, prior day, week and month highs and lows, weekly open, RTH open.

QUESTION 6

Where are my levels?

Paste one line of levels and get zones, flip coloring, a pivot bias and alerts.

02 • BEFORE YOU START


Chart requirements

REQUIREMENT	TRADINGVIEW	NINJATRADER 8
Chart	1 to 30 minute bars. Above 30 minutes a warning says IB, OVN and TPO readings degrade.	1 to 30 minute bars. Other bar types stop the indicator with an error.
Setup	B-ADJ off (the default), so levels sit at the prices that actually traded.	ETH trading hours, Tick Replay off, Calculate on each tick (the default), merge policy non back adjusted.
History	No minimum: the ATR and prior week and month come from daily, weekly, monthly and 30-minute data. More history shows more past profiles and nPOCs.	90 days (400 for the yearly profile). Until the ATR and the prior month are loaded, a notice shows on the chart.
Data used	1-minute intrabar data. On ES1! and other continuous symbols, profiles follow the new contract once it out-trades the old one.	Its own 1-minute, 30-minute and daily series, added automatically.

Every time is Central (CME exchange) time. Leave the session fields at their defaults; to see your own clock, change the chart's time zone instead.

03 · THE CHART AT A GLANCE

What you see on the chart




ES on TradingView, default settings with a pasted levels line. NinjaTrader draws the same items.

- | | | |
|--|--|---|
| <p>1 Dashboard: session, day type, pivot bias, inventory, open, ATR, 80% Rule</p> <p>4 Volume profile: developing weekly profile with POC, VAH, VAL</p> <p>7 Weekly open and prior month: wkOpen, pmVAH, pmPOC, pmVAL</p> <p>10 80% Rule fill: prior-day value shaded after an open outside it</p> | <p>2 Daily levels: RES, PIVOT and SUPP zones from your paste line</p> <p>5 Initial balance: IB high and low (08:30–09:30)</p> <p>8 Prior day: pdHigh, pdLow and prior-day value</p> <p>11 Settlement: the 15:00 settle, TRAP ACTIVE when trapped</p> | <p>3 Flipped level: support closed through, now red and marked FLIPPED</p> <p>6 Overnight: OVN high and low, removed at 15:00</p> <p>9 Single prints: orange boxes traded in only one TPO period</p> <p>12 Prior week: pwHigh and pwLow</p> |
|--|--|---|

When each piece updates

The Toolkit's day runs from the 17:00 CT Globex open to the next afternoon. These are the moments that change what you see.



05 • THE DASHBOARD

The dashboard

Eight rows in the top-right corner summarize the session. Outside 08:30–15:00 CT every row except SESSION and OVN INVENTORY shows ---.

Tatanka AMT	v1.0.0
SESSION	RTH
DAY TYPE	Neutral Extreme (Down)
PIVOT	BULLISH
OVN INVENTORY	LONG (95%)
OPEN	Above pdHigh
ATR(14)	78.14
ATR USED	56.25 (72%)
80% RULE	ACTIVE

The example is the chart in section 03: an open above yesterday's high, mostly long overnight inventory, price above the pivot, and a day that broke both IB extremes and sits near its low. The 80% Rule is active because the open was outside prior value.

ROW	VALUES	HOW IT IS WORKED OUT
SESSION	RTH OVN CLOSED	RTH 08:30–15:00, OVN 17:00–08:30, CLOSED in between.
DAY TYPE	Dalton day types, TRAP, GAP UP/DOWN, DEVELOPING	Reclassified on every RTH bar. See section 07.
PIVOT	BULLISH BEARISH AT PIVOT	Close against your pasted pivot, with a band of 0.5% of the daily ATR. Calculated from 08:15, shown 08:30–15:00.
OVN INVENTORY	LONG (x%) SHORT (x%) BALANCED TRAP LONG TRAP SHORT	Share of overnight bars entirely above or below settlement: over 60% reads LONG or SHORT, 100% reads TRAP. During RTH it shows the reading as of 08:15. See section 08.
OPEN	Above pdHigh, Above pdVAH, Inside Value, Below pdVAL, Below pdLow	The 08:30 open against yesterday's range and value. See section 07.
ATR(14)	points	Wilder daily ATR over 14 days, with today's range so far counted in.
ATR USED	points (percent)	Today's range since 08:30 divided by the ATR. Orange at 75%, red at 100%.
80% RULE	ACTIVE CONFIRMED	Open outside prior value, then 60 minutes of closes back inside. See section 07.



Where is value?

Value is where the market did most of its business. The Toolkit builds volume profiles from 1-minute data and marks the POC, value area high (VAH) and value area low (VAL) for the developing period, the prior day and the prior month.

A Volume profile

- **Built from 1-minute data.** Each 1-minute bar's volume is spread evenly across the price rows between its low and high, so the profile is the same on a 5-minute or a 15-minute chart.
- **Profile Period** sets how long one profile runs: **Session**, **Weekly** (default), **Monthly** or **Yearly**. Weekly starts at the Sunday 17:00 CT open and Monthly at the first session of the month. Session uses only bars inside Session Time (08:30–15:00).
- **POC** is the row with the most volume. The **value area** holds 68% of the period's volume: starting at the POC, the Toolkit adds the next row above or below, whichever has more volume, until 68% is reached.
- **Developing profile:** drawn just right of the current bar (Profile Offset, 50 bars) with Developing POC, VAH and VAL lines and labels. It updates on every bar.
- **Completed profiles** stay on the chart as histograms without lines: up to 12 of them, as long as they ended within the last 4,500 bars.
- **Profile Row Scale** (Global Settings) sets the row height. **Auto** keeps rows near 0.0035% of price: 1x on ES, RTY, CL and GC, 2x on YM, 5x on NQ. Row Size (0.25) is the minimum. A fixed scale (1x to 100x) helps if a symbol loads slowly.
- **Alerts:** crosses of the Developing POC, VAH and VAL between 08:30 and 15:00 (on by default).

Prior-day value (pdPOC, pdVAH, pdVAL)

A profile of the previous day's RTH session (08:30–15:00 CT, set by RTH Session for VA) with a 68% value area, the Dalton convention. Set at 17:00 and fixed for the next day. pdPOC is white, pdVAH and pdVAL purple.

It also drives the OPEN row, the 80% Rule and the day type. Cross alerts are off by default.

Prior-month value (pmPOC, pmVAH, pmVAL)

A profile of the entire previous month built from 30-minute bars, with the 68% value area, plus the month's high and low (pmHigh, pmLow). Thick white lines with price-axis tags, drawn from the first bar of the current month.

Cross alerts are on by default. NinjaTrader needs the whole prior month loaded.

RTH VWAP (off by default)

Volume-weighted average of the typical price (high + low + close) / 3, restarting each day at 08:30 and ending at 15:00. One white line (50% transparent on TradingView), no bands. Optional cross alert.

Volume profile walls (off by default)

Amber lines at the edges of high-volume areas in the developing profile: where the smoothed row volume crosses the average row volume times a multiplier. The multiplier eases from 2.0 to 1.5 as the period goes on. No labels or alerts.

07 • BALANCED OR TRENDING?

Balanced or trending?

The first hour sets the reference range. The Toolkit tracks the initial balance, compares the open with yesterday's value, classifies the day as it develops and runs the 80% Rule.

A Initial balance

- The high and low of bars from 08:30 to 09:30 CT (IB Calc Period). Lines appear at 09:30 and reset the next morning.
- Labeled **IB High** and **IB Low**, in light orange. The midpoint (IB Midpoint) is optional and off by default.
- Lines follow the current bar until 15:15 (Stop Time), or extend to the chart edge with Extend IB Levels.
- Alerts on IB High and IB Low crosses from 09:30 to 15:00 (on by default).
- There are no IB extension lines. How far the day extends past the IB is measured inside the day type.

B Open location

The OPEN row compares the 08:30 open with yesterday's range and value. It is checked in this order, so a range break wins over a value break.

OPEN READS	WHEN THE 08:30 OPEN IS
Above pdHigh	above yesterday's RTH high
Below pdLow	below yesterday's RTH low
Above pdVAH	above yesterday's value area, inside the range
Below pdVAL	below yesterday's value area, inside the range
Inside Value	between pdVAL and pdVAH

The same open decides the gap test: above pdHigh is GAP UP and below pdLow is GAP DOWN until the day type has enough to classify.

C Day type

The day type follows Dalton's classification and is recalculated on every RTH bar, so it can change during the session. It uses these measurements:

- **Reference range:** the IB once it is set at 09:30; before that, the overnight range.
- **Extension:** today's RTH range divided by the reference range.
- **Position:** where the close sits in today's RTH range, from 0 (low) to 1 (high).
- **Initiative up:** trading above pdHigh, or above the overnight high with a close above pdVAH. Initiative down is the mirror.
- **One-timeframing:** 5 bars in a row each making a higher low (up) or a lower high (down).

The tests run in this order and the first match wins:

#	DAY TYPE	CONDITION
1	TRAP	At the open, 100% of overnight bars were on one side of settlement. Holds for the whole session.
2	Trend Day (Down)	Broke below the reference range, close in the bottom 25% of the range, the day's VWAP (not the RTH VWAP line) below the reference midpoint, one-timeframing down or initiative selling, and extension over 1.5. Or: initiative selling, close in the bottom 20% and extension over 2.
3	Trend Day (Up)	The mirror of Trend Day (Down): top 25%, VWAP above the midpoint, extension over 1.5. Or initiative buying, top 20%, extension over 2.
4	Neutral Extreme (Up) Neutral Day (Center) Neutral Extreme (Down)	Both sides of the reference range broken. Close in the top 35% of the range is Neutral Extreme (Up), bottom 35% is Neutral Extreme (Down), anything else is Neutral Day (Center).
5	Normal Day	Neither side broken and the reference range is wider than half the daily ATR.
6	Normal Variation (Up) Normal Day (Balance)	Only the top broken, with initiative buying, extension over 1.2 or a close above pdVAH. Otherwise Normal Day (Balance).
7	Normal Variation (Down) Normal Day (Balance)	Only the bottom broken, with initiative selling, extension over 1.2 or a close below pdVAL. Otherwise Normal Day (Balance).
8	Non-Trend Day	No break and a narrow reference range, once the IB is set.

Until the first classification the row reads **GAP UP**, **GAP DOWN** or **DEVELOPING**. A bar that fits no test keeps the last day type. The value at 15:00 is the day's final read, but the dashboard shows --- after 15:00.

D The 80% Rule

Dalton's 80% Rule: when the market opens outside yesterday's value area and is then accepted back inside it, the other side of value becomes the next reference. The Toolkit tracks it in three steps:

- 1 **Setup:** the 08:30 open is above pdVAH or below pdVAL. The prior-day value area is shaded purple and the row reads **ACTIVE**.
- 2 **Acceptance:** the first bar that closes inside value (between pdVAL and pdVAH) starts a 60-minute timer. A close back outside value resets it. Only bars from 08:30 to 15:00 count.
- 3 **Confirmation:** a close inside value 60 minutes after the timer started confirms the rule. The shading turns pink, the row reads **CONFIRMED** for the rest of RTH and the alert fires once at that bar's close. The rule resets at 17:00.

The fill is display only. Turning off "Show 80% Rule Fill" hides the shading; the rule, the 80% RULE row and the alert keep working.

Example on a 5-minute chart: the first close back inside value is the 09:00 bar. If every bar from 09:00 to 10:00 closes inside value, the rule confirms when the 10:00 bar closes.

Who is trapped?

Overnight inventory shows which side carried positions into the open. When the whole overnight session held one side of settlement, those traders are trapped until price trades back to it.

A Settlement and overnight inventory

- **Settlement** is the close of the last RTH bar before 15:00 CT, captured at 15:00. It is drawn as a gray dashed line labeled **SETTLE**, extended to the right. It is the Toolkit's own settlement, not the exchange's official settle.
- **Inventory** counts the overnight bars from 17:00 to 08:30: a bar whose low is at or above settlement counts as long, a bar whose high is at or below it counts as short, and a bar that straddles it counts toward neither side.
- The dashboard shows the share of all counted bars: **LONG (x%)** or **SHORT (x%)** above 60%, **BALANCED** otherwise. During RTH the row shows the reading as of 08:15; outside RTH it shows the live count.
- It counts bars, not volume or time, so the percentage can differ a little between a 5-minute and a 15-minute chart.

The trap

When 100% of the overnight bars sat on one side of settlement:

- The dashboard reads **TRAP LONG (100%)** or **TRAP SHORT (100%)**.
- The settlement line turns bright green and reads **TRAP ACTIVE** until a bar trades back to settlement.
- The day type shows **TRAP** for the whole session.
- The Trap alert fires once between 08:30 and 09:00 if price hasn't traded back to settlement.

B Late spike

A late spike is a break of the day's range in the last 30 minutes of RTH. At 15:00 the Toolkit compares the 15:00 close with the RTH high and low made before 14:30:

- Close above the earlier high: that high becomes **Spike Base (Supp)**, a green line.
- Close below the earlier low: that low becomes **Spike Base (Res)**, a red line.
- The line starts at 14:30. It is removed the first time price trades back to it, which fires the Spike Base Touch alert, or cleared at the next day's 15:00 check (replaced if there is a new spike).

What is unfinished?

Unfinished business is what the auction left behind: a POC that was never revisited, prices that traded in only one period, and extremes that were not cleanly finished.

A Naked POCs

- The POC of every completed day, week and month, from a full-session profile (overnight included) built from 1-minute data. Week = Sunday 17:00 to Friday.
- Drawn in pink from the start of the next period and extended right: **Daily nPOC** (width 1), **Weekly nPOC** (2) and **Monthly nPOC** (3).
- Removed the first time any bar touches the price, which fires the nPOC Touch alert. A POC touched on the new period's first bar is never shown.
- The first, partial period on the chart never produces one.

B Single prints

- Built from a TPO count of RTH (08:30–15:00) in 30-minute periods. A **single print** is a price block that traded in only one period.
- Single-print blocks no more than one block apart form a cluster. A cluster shows if it spans at least 1 tick from its first to its last block, so it needs at least two blocks: the Market Profile convention that a single print takes at least two TPO prices.
- **Filter Tails** (on) hides a cluster that touches the session high or low and is shorter than 15 ticks, the normal buying or selling tail.
- Drawn as orange boxes from where they formed to just past the current bar. Each block is removed when price trades back into it, and any left are removed after 10 days.

C Poor highs and lows

- A **poor high** is a session high whose top price block traded in 2 or more TPO periods: a flat top with no tail. A poor low is the same at the session low.
- Red dotted line (Poor High) or green dotted line (Poor Low), labeled with the price. The poor-high line sits at the top edge of the high block, one tick above the high with 1-tick blocks.
- Removed when price trades beyond it, or after 10 days. There is no poor high/low alert.

Which reference prices matter?

The Toolkit maps the reference prices every auction trader watches. Each has its own group in the settings.

LINE	WHAT IT IS	ON BY DEFAULT	ALERT
OVN High / Low	The overnight (17:00–08:30) high and low. Drawn from 08:30, removed at 15:00.	Yes	OVN Break (on), outside the overnight session
pdHigh / pdLow	Yesterday's RTH (08:30–15:00) high and low. At 15:00 they switch to the session that just closed.	Yes	High/Low Break (on)
pdOpen	Yesterday's 08:30 open.	No	None
pwHigh / pwLow	Last week's high and low (weeks start Sunday 17:00).	Yes	High/Low Break (on)
pmHigh / pmLow	Last month's high and low, with the prior-month value lines.	Yes	Prev Month Cross (on)
wkOpen	The weekly open: the first bar of the Sunday 17:00 Globex session.	Yes	Weekly Open Cross (on)
dOpen	Today's 08:30 RTH open.	No	None

- Turn off **Use Custom Session for High/Low** (group 3) to use the full trading day's high and low for pdHigh and pdLow instead of RTH.
- The pdHigh/pdLow, prior-week, prior-month and weekly-open alerts keep working when their lines are hidden. Turn the alert switch off to stop them.
- On TradingView, prior-week and prior-month highs and lows come from TradingView's weekly and monthly bars, so they appear even with short history.

11 · YOUR DAILY LEVELS

Where are my levels?

Paste one line of levels into **2. Daily Levels → Paste Levels Here** and the Toolkit draws each one as a zone, flips its color when price closes through it and can alert on it. Anyone can paste their own; Tatanka members paste the daily ML levels.

A The paste line

```
2026-10-05, 7745.25, 7758.25, 7772.00, 7786.50, 7801.25, 7818.00, 7730.25, 7718.25, 7707.25,
7690.50, 7672.75
```

■ Date ■ Pivot ■ Resistance (above the pivot) ■ Support (below the pivot)

- The date, the pivot, then the levels: at least one above and one below the pivot (up to 50 on each side on NinjaTrader). Prices above the pivot become resistance, numbered outward from RES1 (nearest); prices below become support, from SUPP1. The order after the pivot doesn't matter.
- The labeled block also works if all three lines are there: **Pivot Level:**, **Resistance Levels:** and **Support Levels:**. Its levels are numbered in the order written, so list them nearest first. If both are pasted, the paste line wins.
- You can paste a whole Discord levels post: titles, code-block marks and bold marks are skipped. Paste one symbol at a time.
- Write prices without thousands separators (7745.25, not 7,745.25).

B Zones, flips and labels

- **Zones:** a shaded band around each level. In **ATR %** mode (default) it extends 2% of the daily ATR(14) above and below; in **Ticks** mode, 8 ticks.
- **Flips:** when a bar closes through a resistance level by more than the Flip ATR Buffer (5% of the daily ATR), it takes the support color and its label reads **FLIPPED RES1**. A close back through by more than the same buffer flips it back. Support works the same way; the pivot never flips.
- **Colors:** **pivot yellow**, **resistance red**, **support green**; dotted lines with large labels such as **PIVOT: 7745.25** or **RES1: 7758.25**, 40 bars right of price.
- **PIVOT bias:** the dashboard compares the close with the pivot, as described in section 05.

Checks NinjaTrader

STALE LEVELS shows when the line's date is older than the chart's trading date. Levels dated later than the chart, like the 4:45 PM Globex levels, are accepted.

A line is rejected, with the reason at the bottom of the chart, if a price is more than 20% from the pivot (usually a thousands separator) or the pivot is more than 20% from the chart's price (usually another symbol's line).

Levels file NinjaTrader

Instead of pasting, point **Levels File** at a text file with the same line, for example

`%USERPROFILE%\Documents\Tatanka\levels\`

`{root}.txt`. `{root}` becomes the chart's symbol; MES, MNQ, MCL and MGC read the ES, NQ, CL and GC file.

The file is re-read at most every 5 seconds while live data is coming in. If a new file is rejected, the last good levels stay on the chart.

TradingView alerts and new levels. A TradingView alert keeps the levels it was created with. After pasting new levels, delete the alert and create it again.

12 · ALERTS

Alerts

Each alert has its own switch in its section's settings. Most are on by default; alerts on your daily levels are off until you turn on **Enable Level Alerts**.

ALERT	FIRES WHEN	SWITCH (GROUP)	DEFAULT
Daily levels	Price crosses the PIVOT, a RES or a SUPP level	Enable Level Alerts, plus Pivot / Resistance / Support Alerts (2)	Off
IB High / Low	A cross from 09:30 to 15:00	Alert IB High Cross, Alert IB Low Cross (6)	On
OVN High / Low	A cross outside the overnight session	Alert OVN Break (5)	On
pdHigh / pdLow	A cross	Alert High/Low Break (3)	On
pwHigh / pwLow	A cross	Alert High/Low Break (9)	On
Weekly open	A cross	Alert Weekly Open Cross (8)	On

ALERT	FIRES WHEN	SWITCH (GROUP)	DEFAULT
pdPOC / pdVAH / pdVAL	A cross	Alert pdVAH/pdVAL/pdPOC Cross (4)	Off
Developing POC / VAH / VAL	A cross from 08:30 to 15:00	Enable Profile Alerts (11)	On
Prior month	A cross of pmPOC, pmVAH, pmVAL, pmHigh or pmLow	Alert Prev Month Cross (10)	On
RTH VWAP	A cross inside the VWAP window	Alert VWAP Cross, with Enable RTH VWAP (7)	Off
nPOC touch	Price touches a naked POC	Alert nPOC Touch (14)	On
Spike base	Price returns to the spike base	Alert Spike Base Test (16)	On
Inventory trap	Once, 08:30–09:00, while a trap is active	Alert Trap Detected (15)	On
80% Rule	Once, at the close of the confirming bar	Alert 80% Rule Confirmed (4)	On

Alert storm cap (group 18): after 30 alerts within 60 minutes the Toolkit sends one "storm cap reached" warning and drops further alerts until fewer than 30 fall inside the last 60 minutes. Dropped alerts are not sent later. Both numbers can be changed.

On TradingView

TradingView

Turn on the alerts you want in the settings, then **Create Alert** (Alt + A) with the condition **Tatanka AMT** → **Any alert()** function call. One TradingView alert carries every alert you switched on.

Crosses are checked against the previous bar's close and fire at most once per bar; the 80% Rule waits for the bar close. RES crosses on the same bar arrive as one message, and so do SUPP crosses.

The alert keeps the settings it was created with, including pasted levels: re-create it after pasting new levels.

On NinjaTrader

NinjaTrader

Alerts are checked tick by tick on live data and appear in the **Alerts Log** window with a sound (Alert1.wav by default). Enable them on one chart per instrument, or each alert fires twice.

Level Alert Mode (group 18): **Cross**, **Zone Entry** or **Both**. Zone Entry fires when price enters the level's zone; for other lines the zone is 4 ticks each side.

19. Discord Alerts posts each alert, with the price and CT time, to a channel in your own Discord server through a webhook. Live data only.

Display and performance

Global Settings (group 1) control how everything is drawn and how heavy the Toolkit is on your chart.

SETTING	WHAT IT DOES
Force on Top	Draws one line group above everything else. Default: Daily Levels (All). Other choices include the profile POC, VAH or VAL, IB lines, pdPOC, prior-day high or low, OVN high or low, prior-month VAH or VAL and the spike base.
Hide All Labels & Price Tags	One switch that hides every label and price-axis tag. Lines and the dashboard stay.
Show Labels (each group)	Each section has its own label switch, so you can keep the lines and drop the text.
Show Price-Axis Tags	Price tags on the axis for Developing POC, pmPOC, pmVAH, pmVAL, pmHigh, pmLow, pwHigh, pwLow, pdHigh, pdLow, IB High and IB Low.
Auto Tick Size	Sets the base price step used for profile rows, nPOC bins, single-print blocks and tick-mode zones: CL 0.05, GC 0.50, NG 0.005, SI 0.05, HG 0.005, ZB/ZN 1/64, 6E 0.0005, 6J 0.0000005 (MCL, MGC, SIL, M6E and M6J the same). Other symbols use their own tick size, 0.25 on ES and NQ; symbols priced above 1,000 with a tick under 0.1 use 0.25. Turn it off to type your own.
Profile Row Scale	Auto (default) or a fixed 1x to 100x. Higher values mean fewer, taller rows and a faster chart.
Warn if Session Times Were Changed	Shows a warning on the chart when a session field differs from its default.

✓ If the chart is slow

- 1 Raise **Profile Row Scale** (for example to 10x).
- 2 Pick a shorter **Profile Period**.
- 3 Load fewer days of history, keeping enough for the ATR (and, on NinjaTrader, the prior month).

Drawing limits. TradingView allows 500 lines, 500 boxes and 500 labels per script and removes the oldest first. On NinjaTrader, **20. NinjaTrader Limits** caps rows per profile (100,000) and stored nPOCs, poor highs/lows and single prints (2,000 combined); the oldest are removed first and the chart shows a notice.

TradingView vs NinjaTrader

Both versions share the same settings and defaults. These are the differences you will notice.

AREA	TRADINGVIEW	NINJATRADER 8
Install and updates	Public script; updates arrive automatically	Import a zip; re-import each new version
Loading levels	Paste box	Paste box or a levels file that refreshes itself
Level checks	Bad numbers are skipped silently	20% checks, STALE warning and on-chart error messages
Alert checks	Against the previous bar's close, once per bar	Tick by tick; Cross, Zone Entry or Both
Alert delivery	Any TradingView notification: app, email, webhook	Alerts Log and sound; optional Discord webhook
Continuous contracts	On ES1!, profiles follow the new contract once it out-trades the old one; prices follow the chart's B-ADJ setting	Uses the chart instrument as loaded; prices follow your merge policy (non back adjusted recommended)
Prior week and month	Highs and lows from weekly and monthly bars, prior-month value from 30-minute data; available at once	Built from loaded bars; needs the whole prior week or month
Chart rules	Warns above 30 minutes	Requires 1–30 minute bars, ETH, Tick Replay off
Session warning	Red label naming the changed fields	One-line notice at the bottom of the chart
Drawing limits	500 lines, boxes and labels per script	NinjaTrader Limits group
Dashboard header	Tatanka AMT · v1.0.0	Tatanka AMT v1.0.0 · tatankatrading.com

Settings reference

Every setting, in the order it appears in the settings window. Both platforms use the same names and defaults. Groups 19, 20 and About, and settings marked **NT**, exist only on NinjaTrader. Session fields are CME Central time; leave them at their defaults.

1 Global Settings

SETTING	DEFAULT	WHAT IT DOES
Profile Row Scale	Auto	Row height for profiles, nPOC bins and single-print blocks. Auto: about 0.0035% of price (ES 1x, YM 2x, NQ 5x).
Auto Tick Size	On	Picks the base price step for the symbol (see section 13).
Manual Tick Size	0.25	Base price step when Auto Tick Size is off.
Force on Top	Daily Levels (All)	The line group drawn above everything else.
Hide All Labels & Price Tags	Off	Hides every label and price-axis tag; lines and the dashboard stay.
Show Price-Axis Tags	On	Axis tags for 12 key lines while they are drawn.
Warn if Session Times Were Changed	On	Warning on the chart when a session field differs from its default.

2 Daily Levels

SETTING	DEFAULT	WHAT IT DOES
Levels File NT	blank	Full path of a text file to read levels from; {root} becomes the chart's symbol. Blank uses the paste box.
Paste Levels Here	blank	The paste line or the labeled block.
Show Level Lines	On	Off hides the lines; labels and zones stay.
Flip Colors on Break (Res <-> Supp)	On	Changes a level's color after a close through it.
Flip ATR Buffer	0.05	How far past the level the close must be, as a share of the daily ATR.
Show Zones	On	Shaded band around each level.
Zone Size Mode	ATR %	Size zones by ATR % or by ticks. Also the Zone Entry alert band on NinjaTrader.
Zone Width (ATR %)	0.02	Zone half-width as a share of the daily ATR (0.02 = 2%).
Zone Width (ticks above & below)	8	Zone half-width in Ticks mode.
Show Labels	On	Level labels.
Enable Level Alerts	Off	Master switch for daily-level alerts.
Pivot / Resistance / Support Alerts	On	Which levels alert once the master switch is on.
Look: pivot yellow, resistance red, support green; width 1, dotted; zone transparency 85, solid border; labels large, 40 bars right.		

3 Previous Day High/Low/Open

SETTING	DEFAULT	WHAT IT DOES
Enable Prev Day Levels	On	Draws pdHigh, pdLow and pdOpen. Does not affect the alert.
Use Custom Session for High/Low	On	On: high and low of the Custom Session (RTH). Off: of the whole trading day.
Custom Session Time (CT)	0830-1500	Session for pdHigh, pdLow and pdOpen. The 80% Rule only counts bars inside it.
Show pdHigh / Show pdLow	On	Each line on or off.
Show pdOpen	Off	The open of the last completed session.
Show Labels	On	Labels for these lines.
Alert High/Low Break	On	Alerts at pdHigh and pdLow.
Look: pdHigh and pdLow white, pdOpen blue; width 1, solid; labels normal, 2 bars right.		

4 Previous Day Value & 80% Rule

SETTING	DEFAULT	WHAT IT DOES
Enable Prev Day Value & 80% Rule	0n	Builds prior-day value, runs the 80% Rule and fills the 80% RULE row.
Value Area %	0.68	Prior-day value area as a fraction (0.68 = 68%).
RTH Session for VA (CT)	0830-1500:23456	Bars in this session (Monday to Friday) build prior-day value. Its first bar is the RTH open used by OPEN, the gap test and the 80% Rule.
Show pdPOC / pdVAH / pdVAL	0n	Each line on or off.
Show Labels	0n	Labels for these lines.
Show 80% Rule Fill	0n	Shades prior-day value while the rule is active or confirmed. Display only.
Fill: Active (Setup) / Confirmed (80%)	purple / pink	Fill colors before and after confirmation (93% transparent).
Alert pdVAH/pdVAL/pdPOC Cross	0ff	Alerts at the prior-day value lines.
Alert 80% Rule Confirmed	0n	One alert when the rule confirms.
Look: pdPOC white, pdVAH and pdVAL purple at 50%; width 1, solid; labels normal, 2 bars right.		

5 Overnight High/Low

SETTING	DEFAULT	WHAT IT DOES
Enable OVN High/Low	0n	Tracks and draws the overnight high and low. Also needed for the alert.
OVN Session Time (CT)	1700-0830:123456	The overnight window, Sunday to Friday.
Delete OVN Lines At (CT)	1500-1505	OVN lines are removed at 15:00.
Show Labels	0n	OVN labels.
Alert OVN Break	0n	Alerts at OVN High and Low, outside the overnight session.
Look: white, width 1, solid; white labels, 2 bars right.		

6 Initial Balance

SETTING	DEFAULT	WHAT IT DOES
Enable IB	0n	Draws IB High and Low after the IB period. Also needed for the alerts.
IB Calc Period (CT)	0830-0930	The window that forms the IB.
Show IB Midpoint	Off	Adds the midpoint line.
Extend IB Levels	None	Extend the lines Right, Left or Both.
Stop Extension at Time / Stop Time (CT)	0n / 0830-1515	IB lines stop following price at 15:15.
Show Labels / Label Location	0n / Right	IB labels, at the right end or the start of the line.
Alert IB High Cross / IB Low Cross	0n	Alerts at IB High and Low after 09:30.
Alert Window (CT)	0830-1500	IB alerts fire only inside this window.
Look: light orange (#FFCC80), width 1, solid; midpoint dotted; labels normal.		

7 RTH VWAP

SETTING	DEFAULT
Enable RTH VWAP	Off
Start Hour / Minute (CT)	8 / 30
End Hour / Minute (CT)	15 / 0
Alert VWAP Cross	Off
Look: white, width 2, solid (50% transparent on TradingView).	

8 Daily & Weekly Open

SETTING	DEFAULT
Show RTH Open (8:30)	Off
Show Weekly Open (Globex Sunday)	0n
Show Labels	0n
Alert Weekly Open Cross	0n
Look: dOpen blue, width 1; wkOpen white, width 2.	

9 Previous Week

SETTING	DEFAULT
Enable Prev Week Levels	0n
Show pwHigh / Show pwLow	0n
Show Labels	0n
Alert High/Low Break	0n
Look: white, width 2, solid.	

10 Previous Month

SETTING	DEFAULT
Show pmVAH/pmVAL	0n
Show pmPOC	0n
Show pmHigh/pmLow	0n
Show Labels	0n
Alert Prev Month Cross	0n
Look: white, width 3, solid.	

11 Volume Profile

SETTING	DEFAULT	WHAT IT DOES
Enable Volume Profile	0n	Developing and completed profiles and the Developing lines. Profile alerts keep working when it is off.
Profile Period	Weekly	Session, Weekly, Monthly or Yearly.
Session Time (CT)	0830-1500	The bars used when Profile Period is Session.
Session Duration (Hours)	6.5	Times the wall threshold in Session mode.
Calc Precision	1	Minutes per sub-bar used to build the profile.
Row Size	0.25	Minimum row height.
Value Area %	68	Value area of the profile and of the prior month.
Profile Width (Bars)	50	Length of the longest row.
Right Align	0n	Rows grow left from the anchor.
Profile Offset (Bars)	50	Where the developing profile sits right of the current bar.
Show POC / VAH / VAL	0n	Developing POC, VAH and VAL lines.
Show Labels	0n	Labels for the Developing lines.
Enable Profile Alerts / Alert Window (CT)	0n / 0830-1500	Alerts at the Developing POC, VAH and VAL inside the window.
Look: value-area rows blue-gray at 75% transparency, outer rows gray at 90%; POC blue-gray and VAH/VAL gray, width 2.		

12 Volume Profile Walls

SETTING	DEFAULT	WHAT IT DOES
Show Walls / Extend Walls	0ff / 0n	Draws walls on the developing profile, extended to the right edge.
Smoothing	2	Rows averaged around each row.
Min Wall Distance (rows)	40	Minimum gap between walls, in profile rows.
Use Auto-Scale Threshold	0n	Threshold moves from Start Mult (2.0) to End Mult (1.5) over the period.
Fixed Mult	2	Threshold when auto-scale is off.
Look: amber (#E6B300) at 25% transparency, width 1, solid.		

13 TPO & Single Prints

SETTING	DEFAULT	WHAT IT DOES
TPO Session (CT)	0830-1500	Session used for TPOs, single prints and poor highs/lows.
TPO Period (min)	30	Length of each TPO period.
Ticks per Block	1	Height of a TPO block in base ticks (times the row scale).
Min Single Print Size (ticks)	1	Smallest single-print run, measured from its first to its last block; 1 means at least two blocks.
Filter Tails / Max Tail Size	0n / 15	Hides single prints at the session extremes shorter than 15 ticks.
Max History Days	10	Single prints and poor highs/lows older than this are removed.
Show Poor Highs/Lows / Labels	0n	Poor high and low lines and their labels.
Look: single prints orange at 90% transparency, no border; poor high red, poor low green, dotted, width 2.		

14 Naked POCs

SETTING	DEFAULT	WHAT IT DOES
Enable nPOCs	0n	Tracks naked POCs.
Show Daily / Weekly / Monthly nPOC	0n	Each kind on or off.
Auto Bin Size (tick)	0n	POC bin = base tick times the row scale.
Use Manual Bin Size / Manual Bin Size	0ff / 0.25	Your bin size (times the row scale), used when Auto Bin Size is off and Use Manual Bin Size is on.
Show Labels	0n	nPOC labels.
Alert nPOC Touch	0n	Alert when price touches a naked POC.
Look: pink, widths 1 / 2 / 3 (daily / weekly / monthly), solid; labels small.		

15 Settlement & Inventory

SETTING	DEFAULT	WHAT IT DOES
Enable Inventory Trap Logic	0n	Counts overnight bars against settlement and flags traps.
Show Settlement Line	0n	The SETTLE / TRAP ACTIVE line.
Globex Start Hour (CT)	17	Start of the overnight count.
RTH Open Hour / Minute (CT)	8 / 30	End of the count; the trap alert can fire in the 30 minutes after.
Trap Text	TRAP ACTIVE	Label shown while a trap is active.
Show Labels / Alert Trap Detected	0n / 0n	Labels, and one alert per day while trapped.
Look: settle gray, trap bright green; dashed, width 1; label 40 bars right.		

16 Late Spike

SETTING	DEFAULT
Show Late Spike	On
Spike Window (CT)	1430-1500
Show Labels	On
Alert Spike Base Test	On
Look: green (support) or red (resistance), width 1; label 15 bars right.	

17 Dashboard

SETTING	DEFAULT
Show Dashboard	On
Position	Top Right
Text Size	Normal
Table RTH Session (CT)	0830-1500
Context Tracking Session (CT)	0815-1500
Daily ATR Period	14

Table RTH Session sets when the dashboard's RTH rows are live and where ATR USED starts. Context Tracking Session sets when the inventory reading is frozen and the PIVOT bias updates. Daily ATR Period feeds the dashboard, the Normal Day test and the pivot band; zones and flips always use a 14-day ATR.

18 Alerts

SETTING	DEFAULT	WHAT IT DOES
Enable Alert Storm Cap	On	Drops alerts once the cap is reached.
Max Alerts per Window / Window (minutes)	30 / 60	The cap: this many alerts in this many minutes.
Level Alert Mode NT	Cross	Cross, Zone Entry or Both.
Structure Alert Zone Half-Width (ticks) NT	4	Zone Entry band for lines other than daily levels.
Enable Alert Sound / Sound File NT	On / Alert1.wav	Sound from NinjaTrader's sounds folder.

19 Discord Alerts (Optional)NT

SETTING	DEFAULT	WHAT IT DOES
Send Chart Alerts to Discord	Off	Posts live alerts to a Discord channel. It does not import levels.
Discord Webhook URL	blank	In your server: Server Settings → Integrations → Webhooks → New Webhook, then Copy Webhook URL. An invite or channel link won't work.

20 NinjaTrader LimitsNT

SETTING	DEFAULT	WHAT IT DOES
Maximum Rows per Profile / TPO	100,000	Oldest rows are removed beyond this, with a notice.
Maximum Retained Structures	2,000	nPOCs, poor highs/lows and single prints combined; oldest removed first.

About NT shows the version (quote it when asking for help) and the website.



Glossary

Auction Market Theory

The market as a two-sided auction: it moves to find buyers and sellers and spends time where they agree.

POC

Point of control: the price with the most volume in a profile.

Initial balance (IB)

The range of the first RTH hour, 08:30–09:30 CT.

One-timeframing

Each bar makes a higher low (up) or a lower high (down) than the last.

TPO

Time price opportunity: each price traded in each 30-minute period. Together they form the market profile.

Poor high / low

A session extreme traded in several periods with no tail, often read as unfinished.

Settlement

In the Toolkit, the last RTH close before 15:00 CT.

80% Rule

An open outside prior value followed by acceptance back inside; Dalton's setup for a move to the other side of value.

ATR

Average true range: the average daily range, over 14 days by default.

Value area (VAH, VAL)

The price range holding most of a period's volume, 68% in the Toolkit. VAH is its top and VAL its bottom.

Naked POC

A past period's POC that price has not traded back to.

Range extension

Trading beyond the IB. The Toolkit measures it as the RTH range divided by the IB range.

Initiative activity

Buying above value or selling below it, as opposed to responsive activity that fades moves away from value.

Single prints

Prices traded in only one TPO period, usually left by a fast move.

Overnight inventory

Whether overnight traders are holding above or below settlement going into the open.

Trap

The whole overnight session held one side of settlement, so that inventory may need to be unwound.

Day types

Dalton's classification of how a session develops: Trend, Normal, Normal Variation, Neutral and Non-Trend.

VWAP

Volume-weighted average price.

GETTING HELP



Ask in the Tatanka Discord with a screenshot, your platform and the version from the dashboard header.

Install steps are in the Tatanka Indicators Setup Guide. The source code is on GitHub: tatankatrading.com/github.

Trading futures involves substantial risk of loss. The Toolkit is an analysis tool, not buy/sell signals or trade recommendations. Free and open source under the Mozilla Public License 2.0. Copyright (c) 2026 Tatanka Trading LLC.