



CREST WebGUI+ Operational Setup Guide

July 2025

Contents

1. About this Guide	3
1.1. Background	3
1.2. Document Scope	3
1.3. Other Documents	3
2. User Setup	4
2.1. Operators	4
2.1.1. Creating Operators	4
2.1.2. Operator Access Management	5
2.1.2.1. Operator Profiles	6
2.1.2.2. Operator Function Groups	7
2.2. User ISO Configuration	8
3. Participant Setup (Member)	9
3.1. Caps	10
3.2. CMAs	12
3.3. Member Accounts	14
3.4. Participant ISO Configuration	16
3.4.1. Participant ISO Reports	16
3.4.2. CMA ISO Reports	16
3.4.3. Member Account ISO Reports	16

1. About this Guide

1.1. Background

CREST WebGUI+, Euroclear UK and International's new Web GUI application, is the first stage of transformation for the CREST interactive system. The initial launch is a migration from the existing dedicated application onto a web platform, including some key enhancements such as improved dual authorisation, with screens and data otherwise remaining largely the same.

Although the processes remain largely unchanged from the legacy system, the screens used to perform these functions have undergone significant visual updates and may now be accessed from different areas of the menu. Therefore, this Guide has been created to facilitate the transition for the launch of the Web GUI, providing users with instructions on how to execute key setup processes. The processes detailed in this document are less frequently utilised compared to routine activities such as transaction input, and users may be unfamiliar with them if they have not been performed recently. Consequently, this document aims to act as both a refresher for current users during the Web GUI migration, and as a guide for new CREST users onboarding onto the Web GUI platform.

1.2. Document Scope

This Guide aims to provide instructions and information for new or existing users on setting up key participant and user data within the CREST system, using both written instructions and images. This guide is only focused on the initial setup and is not exhaustive – additional user or participant configuration options are available beyond the scope of this guide, and the screens referenced herein may contain advanced functionalities not covered. For scenarios requiring more detailed information on a specific screen, users should consult the GUI help file.

1.3. Other Documents

CREST WebGUI+ Migration Guide

2. User Setup

Certain data and functions must be configured at the level of the user (the top-level entity with a connection to the CREST system) rather than the individual participants that belong to it. This is required after the creation of a new user, but further configuration may be performed at any time.

2.1. Operators

An operator is required to interface with the Web GUI+ application, as well as to send messages through straight-through-processing methods. Operators are linked to users; they must connect via a user's gateway and can only access data relevant to that specific user. Operators may be of type master, admin, or ordinary.

The **master** operator is a unique operator with a maximum of one available. It has access to all functionality available to the user, and can create, amend and delete admin and ordinary operators (one or as many as required).

Admin operators may create and configure other ordinary operators, but cannot perform standard business functions within participants. It is recommended to use an admin to manage all ordinary operators, as multiple admin operators may be created, and the risk of locking the master operator with incorrect password attempts is reduced.

Ordinary operators are the standard type used to perform most business functions. These may also be assigned a session type of '**File Transfer**' to facilitate straight-through-processing DEX messaging, or '**Common Interface**' to facilitate straight-through-processing ISO messaging.

Upon the creation of a new user, only the master operator is available.

2.1.1. Creating Operators

To create a new operator while logged in as a master or admin operator, open the **Create Operator** page. This can be accessed through the quick link on the home screen, by searching in the menu, or by navigating to it in the menu through *Entity Data > Operator Management > Create Operator*.

The screenshot shows the 'Create Operator' form in the Web GUI+. The form is divided into several sections. The top section has an 'Operator Reference' field. The middle section has 'Operator Type' (set to 'Ordinary'), 'Operator Description', and 'Operator Status'. Below these are password fields for 'Admin/Master Password', 'New Password', and 'Verify Password', along with a 'Password Changed' checkbox. The 'Session Type' is set to 'Interactive'. Below this are checkboxes for 'FT Permanently Enabled', 'Unsolicited Operator', and 'Authorised for cash-only DEL' (which is checked). There are also fields for 'Next FT Sequence Number', 'Profile Number' (set to 1), 'Cash DEL Debit Limit (GBP)', and 'Next Cash DEL Debit Limit (GBP)'. At the bottom, there are 'Participant Access' options: 'All Participants' (selected), 'No Participants', and 'Single Participant'. A 'SUBMIT' button is at the bottom right.

The relevant fields when creating a new interactive (GUI) operator are as follows:

- **Operator Reference:** The unique operator reference that the operator will use to log into the Web GUI. Maximum of eight characters. May be letters, numbers, or a combination. Not case sensitive.
- **Operator Type:** This determines the type of operator. The master operator may create admin or ordinary while an admin may only create an ordinary operator. It is not possible to create an additional master operator, or a super operator, which is an internal EUI operator type.

- **Operator Description:** A free text field used to identify the operator – for example, someone’s name.
- **Session Type:** Determines if the operator will be used for the Web GUI (Interactive), File Transfer messaging, or ISO messaging (Common Interface).
- **Profile Number:** This is the profile that the operator will use, and will determine their access to CREST functions. Profile configuration is described in the [Operator Profiles](#) section. It is strongly recommended to create and configure a profile before making ordinary operators when in a production environment, but the profile number may be changed at a later stage if required.
- **Admin/Master Password:** Enter the password of the master or admin operator that you are currently logged in as. This is only required for initial operator creation, not for updating an existing operator.
- **New Password:** Enter the password that the new operator will use to log on for the first time. The password must be exactly 12 alphanumeric characters (A-Z, 0-9), contain at least one letter and one number and not contain more than 2 consecutive characters.
- **Verify Password:** Re-enter the new password the same as above.
- **All/No/Single Participant(s):** This determines if the operator can control all participants belonging to the user, just one specified participant or no participant data at all. (No participant data still allows access to base data and system functions, as long as the relevant functions are enabled)
- **Authorised for cash-only DEL:** If this box is checked, the operator is able to input cash-only delivery (DEL) transactions for any participant they can access. The operator still needs access to the delivery function (ADV N).
- **Cash DEL Debit Limit (GBP):** This indicates the daily limit of debit movements that that the operator may input in cash-only DEL transactions. If left blank, the operator has no limit. The amount is denominated in GBP but transactions in all currencies are considered and calculated using CREST’s FX rates. This field cannot be directly amended or updated on the same day, but rather must be amended overnight by completing the Next Cash DEL Debit Limit.

There are some differences when making different types of operators:

- **Admin** operators are always assigned to ‘No Participants’ and may not be provided access to act as a participant. This means that a profile does not need to be manually configured for admins to block participant functions (such as transaction input) as this is always blocked due to the operator type.
- **File Transfer** operators gain the fields **FT Permanently Enabled?** and **FT Status (Enabled/Disabled/Stalled)**.
- **Common Interface** operators gain the field **Unsolicited Operator?** to determine if they exist for the purpose of receiving scheduled reports.

Pressing **Submit** will create the operator provided that the form is completed with valid information. A created operator may be amended later by accessing the **View Operator Details** screen and retrieving the desired operator reference.

2.1.2. Operator Access Management

Operator access management is configured at various levels:

- The **Operator Profile** is a numeric value that assigns access levels to all CREST functions individually, and can be applied to multiple operators
- **Operator Group** configuration allows entire groups of functions to be blocked for an individual operator
- **Individual operators** may be configured on creation, or later through amendment, to restrict participant access or cash-only DELs

These controls work in combination to provide a precise level of access. For example, for an operator to input a cash-only delivery for a participant, it would need all of the following conditions to be true:

1. The profile number to allow access to the Delivery Input function ADVN
2. The specific operator to have the operator function group OG17, that contains ADVN, enabled
3. The Operator Reference set to authorised for cash-only DELs
4. The Operator Reference set to a participant access level of ‘All Participant’ or ‘Single Participant’ for the participant in question

2.1.2.1. Operator Profiles

Operator profiles form the high-level function access for participants. All operators must have an operator profile assigned to them upon creation. An operator profile defines the functions that the operator can use (assuming the individual operator also has the [function group](#) enabled), as well as determining the specific level of access they have to each function. Operator profiles are shown as a number between 1 and 99.

The function access levels that may be assigned to each function in a profile are as follows:

- **None** – The operator does not have any access to the function.
- **Input Only** – The operator has access to attempt to perform the function in the CREST GUI session, however, the action must be authorised by a second operator that has Authorise Only, Input or Authorise, or Full access to the function. The participant cannot perform authorisation for the function for another operator.
- **Authorise Only** – The operator has access to authorise the function being attempted by another operator that has Input Only or Input or Authorise access, but cannot attempt the function themselves.
- **Input or Authorise** – The operator has the access to attempt to perform the function and have it authorised by a second operator with sufficient access, or can authorise an action being attempted by another operator. The operator is not able to authorise their own attempt at performing a function.
- **Full** – The operator can perform the function alone, without additional authorisation.

To create or amend an operator profile while logged in as a master or admin operator, open the **Operator Profile List**. This can be accessed through the quick link on the home screen, by searching in the menu, or by navigating to it in the menu through *Entity Data > Operator Management > Operator Profile*.

FUNCTION ID	NAME	ACCESS LEVEL
AALL	Actioned Liquidity List	Full
AALR	Actioned Liquidity Retrieve	Full
AARA	Authorise Neg reg	Full
AATN	Own Account Transfer Input	Full

To create a new profile from the Operator Profile List, press the **Create New** near the top right of the page. This will open the **Create Operator Profile** window.

The Operator Profile window has two fields that can be completed:

- In the **Profile Number** box, enter a number of your choice that the new profile will use. The number must not already be in use.
- The **Template Profile Number** is an optional field. If left blank, the new profile will default to an access level of **Full** for all functions. If you have previously created and configured an operator profile, you can enter the profile number of the existing profile, and the newly created profile will use the existing profile's set of functions as a template, when can then be amended.

To create the new profile, press **Submit**.

To amend the function access levels of an existing or newly created profile, enter the profile number to be amended in the Operator Profile List screen, and press Retrieve. This will return the access level for each function that belongs to that profile.

Use the drop-down boxes in the Access Level column to amend the access to each individual function for the selected operator profile. Press the Update button to apply any changes.

Operator Profile List

Profile Number: 50 RETRIEVE

FUNCTION ID	NAME	Access Level
AALL	Actioned Liquidity List	
AALR	Actioned Liquidity Retrieve	
AARA	Authorise Neg reg	
AATN	Own Account Transfer Input	Input Only
ABAN	Buyer Accept	Full
ADU 41	Even 1 Available Permissions	Full

Use the Next and Prev buttons to navigate back and forth between pages. Please note that each page must be individually updated, and moving to the next page without updating will cause any changes to be lost.

2.1.2.2. Operator Function Groups

CREST functions all belong to a parent operator group, where they are grouped alongside similar functions.


Operator groups can be enabled or disabled for each operator, and can be used in combination with the access management control provided through the operator profile. An operator must have both a profile allowing access to the function, and the function's group enabled, in order to use it.

To view or amend operator groups while logged in as the master or an admin operator, open the **Operator Group List**. This can be accessed through the quick link on the home screen, by searching in the menu, or by navigating to it in the menu through *Entity Data > Operator Management > Operator Group List*.

In the Operator Group List, first enter an Operator Reference and retrieve. This will display all operator groups with a checkbox displaying if the function group is enabled. To enable or disable a group, click the checkbox and press update at the bottom of the page.

Use the Next and Prev buttons to navigate back and forth between pages. Please note that each page must be individually updated, and moving to the next page without updating will cause any changes to be lost.

The eye icon at the end of each row can be pressed and will open the Operator Group Functions screen, which shows the functions contained within each group.



2.2. User ISO Configuration

If the user is to make use of unsolicited ISO/Common Interface messaging, a common interface operator must have previously been created and set to **Unsolicited**, before being linked to the user **by EUI**. As well as this, some message types can be enabled at user level. This can be done by accessing the **User ISO Interface Unsolicited Message Profile List** by using the menu search, or navigating to *Entity Data > Subscriptions > User ISO Interface Unsolicited Message Profile List*.

The screen allows the following message types to be generated when appropriate:



- MT 518** – Trade Confirmation
- MT 544** – Receive Free Confirmation
- MT 545** – Receive against Payment Confirmation
- MT 546** – Deliver Free Confirmation
- MT 547** – Deliver against Payment Confirmation
- MT 548** – Settlement Status
- MT 564** – Corporate Action Notification
- MT 566** – Corporate Action Confirmation
- MT 567** – Corporate Action Instruction Status
- MT 578** – Settlement Allegement

To enable or disable a message type, click the checkbox and press update at the bottom of the page. Enabling a message type will cause it to be received for all participants belonging to the user. These messages, with the exception of the MT564 (CA Notification) may instead be enabled on an individual participant basis by using the [Participant ISO Interface Unsolicited Message Profile List](#).

3. Participant Setup (Member)

Upon the creation of any new participant of type 'Member', some setup must be performed before the participant can hold securities and settle transactions. This includes an account to hold securities, a Cap to control credit available for the participant CREST, and a Cash Memorandum Account (CMA) to record and report cash positions and postings.

To execute actions for a specific participant, use the 'Act as Participant' function to assume the identity of the desired participant ID. Once this function is activated, all viewed data will pertain exclusively to that participant, and any inputs created will be restricted to it.



3.1. Caps

A cap is used to control the amount of credit available to CREST participants. It is set by agreement between a member and their payment bank. The input of the cap must be performed by the requesting member, but the enablement of the cap may only be performed by the payment bank. Amendments to the cap after creation may be performed by either the member or the payment bank, however, amendments by the member will result in the cap being disabled until the payment bank validates the changes and re-enables the cap if the changes are in line with their expectations.

A cap must exist before a CMA can be created, as the CMA must link to a cap upon creation. However, a cap may not be enabled without a CMA existing. Therefore, the order of operations must be:

1. Cap created by member at 'New' status.
2. CMA created by member and linked to new cap.
3. Cap validated by payment bank and set to 'Enabled' status.

It is possible to have a cap per currency in CREST (GBP, EUR, USD), each linked to a CMA in its respective currency, or to have a single cap restricting the credit available across all three currencies together. In the latter case, payments made or received in a currency not matching the cap will be calculated using CREST FX rates, and a high spend in one currency may block payments in other currencies if no more credit is available.

The relevant CREST functions for member account management in the GUI are:

JCPR – Cap Retrieve (Also used to view Cap List)

JCPN – Cap Input

JCPA – Cap Amend

JCPD – Cap Delete

The image displays two screenshots of the Euroclear - CREST web application interface.

Top Screenshot: View Cap List

The top screenshot shows the 'View Cap List' screen. The left sidebar contains a navigation menu with categories: ENTITY DATA, SETTLEMENT, ASSET SERVICING, COLLATERAL MANAGEMENT, CASH MANAGEMENT (highlighted), ACCOUNT MANAGEMENT, LIQUIDITY MANAGEMENT, and ENQUIRY. Under ENQUIRY, 'View Cap List' is selected. The main content area has a header 'View Cap List' and a 'CREATE NEW' button. Below the header, there are filters for Bank ID, Participant ID (DEMO1), Status (All), and Date Range (Current Date). A 'RETRIEVE' button is on the right. Below the filters is a table with columns: BANK ID, PARTICIPANT ID, CCY, CAP NAME, REPO LIMIT, SECURED LIMIT, UNSECURED LIMIT, STATUS, and EFFECTIVE DATE. The table is currently empty, showing 'NO RECORDS TO DISPLAY'.

Bottom Screenshot: Create Cap

The bottom screenshot shows the 'Create Cap' screen. The left sidebar is similar to the top screenshot, but 'Create Cap' is selected under the CASH MANAGEMENT section. The main content area has a header 'Create Cap'. Below the header, there are input fields for Participant ID (DEMO1), Bank ID (CPAY), and Cap Name (GBPCAP). There are two buttons: 'Last Forward Dated Amendment' and 'Selected Date' (highlighted). Below these, there is a date field set to 17/01/2025. The form is divided into several sections with input fields: Participant Name, Participant Status, Bank Name, Bank Status, Currency (GBP), Cap Status, Unsecured Limit (1000000.00), Secured Limit (1000000.00), MSV, Repo Limit, Repo Value, Maximum Credit Available, Current Position, Headroom, and Effective Date. A 'SUBMIT' button is at the bottom right.

To create a cap in the Web GUI, while acting as the member participant open the **Create Cap** screen, either by navigating to it using the menu under *Cash Management > Account Management*, or by pressing the Create New button in the cap list: *Cash Management > Enquiry > View Cap List*.

The following fields are relevant when making a cap:

- **Bank ID:** The participant ID of the payment bank that the Cap should link to.
- **Cap Name:** Free text field - the name for the Cap you are creating.
- **Currency:** The currency of the Cap.
- **Unsecured Limit:** The maximum amount of spending available using credit alone. This should be entered at the value agreed with the payment bank.
- **Secured Limit:** The upper limit of spending that can be utilised provided that the member holds sufficient stock to be secured under a floating charge arrangement. This should be entered at the value agreed with the payment bank.
- **Repo Limit:** The maximum value of the member's stock that can be moved to the payment bank repo member in SCR transactions. May be left blank and will default to the maximum value.
- **Effective Date:** The date on which the cap details entered will become effective (if not immediately).

Press **Submit** to create the Cap. If authorisation is required, the input will first move to the **Dual Authorisation Instruction List** before being complete. Once the input is complete, the cap will move to a status of 'new' and is ready to be linked to by a CMA, after which it must be enabled by the payment bank before it can be used to facilitate settlement.

The created cap will be visible in the Cap list. The eye icon at the end of the row may be used to open details of an existing cap, along with providing the ability to amend or delete it.

Euroclear - CREST

Environment: DH Operator: EOC003 Participant: DEMO1 17/01/2025

CASH MANAGEMENT > ENQUIRY > CAPS

View Cap List CREATE NEW

View Cap List RETRIEVE

BANK ID	PARTICIPANT ID	CCY	CAP NAME	REPO LIMIT	SECURED LIMIT	UNSECURED LIMIT	STATUS	EFFECTIVE DATE
CPAY	DEMO1	EUR	EURCAP	999,999,999.99	500,000.00	500,000.00	New	
CPAY	DEMO1	GBP	GBPCAP	999,999,999.99	10,000,000.00	10,000,000.00	Disabled	
PB06	DEMO1	GBP	GBPCAP2	999,999,999.99	100,000,000.00	100,000,000.00	New	

< PREVIOUS NEXT >

3.2. CMAs

A CMA is used to record cash movements throughout the course of the day. A CMA is required in each currency that a participant wishes to settle transactions into. A maximum of 3 active CMAs are possible, one for each currency in CREST (GBP, EUR, USD). As described in the Caps section, a cap must exist before a CMA can be created.

CMAs cannot be manually deleted, but it's possible to amend a CMA, for example, when changing payment bank. When the CMA is amended using new valid details (a new bank ID and a new cap), the currently active CMA for that currency will be set to inactive, and a new active CMA will be generated using the new details.

JCMR – CMA Retrieve (also used to view CMA List)

JCMN – CMA Input

JCMA – CMA Amend

The image shows two screenshots of the Euroclear - CREST web application. The top screenshot displays the 'Cash Memorandum Accounts List' page. The page has a sidebar menu on the left with options like ENTITY DATA, SETTLEMENT, ASSET SERVICING, COLLATERAL MANAGEMENT, CASH MANAGEMENT (selected), ACCOUNT MANAGEMENT, LIQUIDITY MANAGEMENT, ENQUIRY, SYSTEM, MARKET DATA, and REGISTRATION. The main content area shows the 'Cash Memorandum Accounts List' with a search bar containing 'Balance Date: 17/01/2025', 'Bank ID', 'Participant ID: DEMO1', 'Cap Name', and 'CCY: GBP'. A 'RETRIEVE' button is visible. Below the search bar is a table with columns: PARTICIPANT ID, BANK ID, CCY, PAYMENT TYPE, CMA NAME, CASH POSITION, TIMESTAMP, CAP NAME, and CMA STATUS. The table is currently empty, showing 'NO RECORDS TO DISPLAY'. A 'CREATE NEW' button is in the top right corner. The bottom screenshot shows the 'Create CMA' form. The form has fields for: Balance Date, Currency (GBP), Payment Type (Central), Bank ID (CPAY), Bank Name, Bank Status, Participant ID, Participant Name, Participant Status, Cap Name (GBPCAP), Cap Status, Cash Position, CMA Name (GBPCMA), and CMA Status. There is a checkbox for 'Postings Available' which is checked. A 'HELP' button and a 'SUBMIT' button are at the bottom right. A green notification banner at the top right says 'Create CMA Record(s) Added Successfully'.

To create a new CMA, while acting as the member participant, the **Create CMA** screen must be used. This screen can only be accessed by pressing the **Create New** button in the **Cash Memorandum Account list**, which can be reached in the menu by navigating to *Cash Management > Account Management > Cash Memorandum Account List*.

The follow fields are relevant when creating a CMA:

- **Bank ID:** The participant ID of the payment bank that the CMA should link to.
- **Cap Name:** The name of an existing Cap that the CMA should link to.
- **Ccy:** The currency of the CMA.
- **Payment Type:** For GBP or EUR CMAs, select 'Central'. For USD CMAs, select 'Bilateral'.
- **CMA Name:** Free text field – The name for the CMA you are creating.
- **Postings Available:** Check this option to allow the payment bank visibility of transaction postings.

Press **Submit** to create the CMA. If authorisation is required, the input will first move to the **Dual Authorisation Instruction List** before being complete. Once complete, the CMA will move to a status of 'Active'.

Once the CMA has been created, it will become visible within the list. The menu at the end of the row may be used to edit the CMA, or view cash postings in that currency.

At this stage, the Cap may now be enabled by the payment bank which will complete the cash setup.

The screenshot displays the Euroclear - CREST web application interface. The top navigation bar includes the Euroclear logo, the title "Euroclear - CREST", and user information: Environment DH, Operator EOC003, Participant DEMO1, and a date of 17/01/2025. A left-hand sidebar contains a menu with categories: ENTITY DATA, SETTLEMENT, ASSET SERVICING, COLLATERAL MANAGEMENT, CASH MANAGEMENT (highlighted), LIQUIDITY MANAGEMENT, and ENQUIRY. Under CASH MANAGEMENT, the "Cash Memorandum Account List" is selected. The main content area is titled "Cash Memorandum Accounts" and features a "CREATE NEW" button. Below this is a "Cash Memorandum Accounts List" section with a search bar and a table. The search bar includes fields for Balance Date (17/01/2025), Bank ID, Participant ID (DEMO1), Cap Name, and CCY (GBP), with a "RETRIEVE" button. The table lists two accounts: DEMO1 with Bank ID CPAY, GBP, Central payment type, CMA Name GBPCMA, Cash Position 0.00, Timestamp 15:07:23, Cap Name GBPCAP, and CMA Status Active; and DEMO1 with Bank ID PB06, GBP, Central payment type, CMA Name GBPCMA, Cash Position 0.00, Timestamp 15:07:23, Cap Name GBPCAP2, and CMA Status Inactive. A "POSTING" button is visible at the bottom right of the table.

PARTICIPANT ID	BANK ID	CCY	PAYMENT TYPE	CMA NAME	CASH POSITION	TIMESTAMP	CAP NAME	CMA STATUS
DEMO1	CPAY	GBP	Central	GBPCMA	0.00	15:07:23	GBPCAP	Active
DEMO1	PB06	GBP	Central	GBPCMA	0.00	15:07:23	GBPCAP2	Inactive

3.3. Member Accounts

A member account is required to hold securities in CREST or to settle a transaction. A participant may hold stock within a single member account, or across as many as needed.

The relevant CREST functions for member account management in the GUI are:

- IMAR** – Member Account Retrieve (also used to view Member Account List)
- IMAN** – Member Account Input
- IMAA** – Member Account Amend
- IMAD** – Member Account Delete

To create a member account, the **Create Member Account** screen must be used while acting as the specified participant ID. This screen can be accessed directly in the menu by navigating to *Entity Data > Security Account Management > Create Member Account* or by pressing the **Create New** button in the **Member Account List** (*Entity Data > Security Account Management > Member Account List*).

The screenshot displays the Euroclear - CREST web interface. The top navigation bar includes the Euroclear logo, the text "Euroclear - CREST", and user information: Environment DH, Operator EOCD003A, Participant DEMO1, and a date of 16/01/2025. A "Quick search" bar is also present.

The left sidebar contains a menu with categories: ENTITY DATA, SECURITY ACCOUNT MANAGEMENT, ACCOUNT SETTINGS, SUBSCRIPTIONS, CLEARING DETAILS, STAMP ASSESSMENT, SETTLEMENT, ASSET SERVICING, COLLATERAL MANAGEMENT, CASH MANAGEMENT, and SYSTEM. The "SECURITY ACCOUNT MANAGEMENT" section is expanded, showing "ACCOUNT MANAGEMENT" and "ACCOUNT SETTINGS".

The main content area is titled "Member Accounts" and features a "CREATE NEW" button. Below this is the "Member Account List" section, which includes a "Status" dropdown and a "RETRIEVE" button. A table with columns "BANK ID", "CAP NAME", "ACCOUNT ID", "ACCOUNT TYPE", "ACCOUNT STATUS", "REPORTING FIRM ID", and "REPORTING FIRM CODE TYPE" is shown, but it contains no records.

The bottom section is titled "Member Account Details" and contains the "Create Member Account" form. The form has three tabs: "ACCOUNT" (selected), "CAP", and "BANK REPO LINK". The "ACCOUNT" tab includes fields for "Participant ID" (DEMO1), "Cap Name", and "Account ID" (ACCOUNT1). Below these are sections for "ACCOUNT", "CAP", and "BANK REPO LINK" details, including "Participant ID", "Participant Name", "Participant Status", "Account Description" (Member Account 1), "Category" (Other Financial), "Account Tax Status" (Standard Rate), "Status", "Delete Date", "Delete Status", "Delete Failure Reason", "Reporting Firm ID", "Reporting Firm Type Code", and "CSDR Account Type" (Own Account). A "SUBMIT" button is at the bottom right.

The relevant fields when creating a new basic member account are as follows:

- **Account ID:** Enter a name for the new account. It may contain letters and numbers and can be up to eight characters in length. An 'undesigned' account may be created by leaving the account ID blank.
- **Account Description:** An optional free text account description to help operators identify the account.
- **Account Type:** Select '**Ordinary**' under all circumstances, even for repo accounts.
- **Category:** The industry sectoral classification of the ownership of assets within the account
- **Account Tax Status:** The stamp duty treatment for the member account
- **CSDR Account Type:** Used to indicate if the securities within the account are own assets, individually segregated assets, or pooled assets belonging to various beneficial owners.

Press **Submit** to create the member account. If authorisation is required, the input will first move to the **Dual Authorisation Instruction List** before being complete. Once the input is complete, the account status will immediately move to Enabled status and be available for use.

Additional fields may be entered upon creation or through an amendment at a later date to:

1. Allow securities to have a floating charge placed on them under a **secured credit** agreement
2. Allow eligible securities within the member account to be used for **self-collateralised repo (SCR)**.
3. Allow both secured credit and SCR as described above

To achieve this, in the **Cap** tab complete the following fields:

- **New Bank ID:** The Payment Bank ID of the bank providing the payment facility (which is also the Bank ID specified within the Cap).
- **New Cap Name:** The name of the cap that the account should link to. The cap must exist prior to linking, but may be linked before the cap is enabled.
- **Next Repo Indicator:** Check this box to allow SCR.
- **Next Secured Credit Indicator:** Check this box to allow secured credit.

The bank ID and cap name must be provided. One or both of the repo indicator and secure credit indicator must be checked. The update will take place overnight. The **Bank Repo Link** tab is only for members belonging to payment banks. This requires the bank ID to be entered, and will allow eligible securities in the account to be used in SCR at any time. The update will take place overnight.

Once an account has been created, they will appear in the list. The eye icon at the end of each row can be pressed to view the full details, as well as to amend or delete the account.

The screenshot displays the Euroclear - CREST web application interface for managing Member Accounts. The main content area shows a 'Member Account List' table. The table has the following columns: BANK ID, CAP NAME, ACCOUNT ID, ACCOUNT TYPE, ACCOUNT STATUS, REPORTING FIRM ID, and REPORTING FIRM CODE TYPE. The table lists three accounts: ACCOUNT1, ACCOUNT2, and ACCOUNT3, all of type 'Ordinary' and status 'Enabled'. A 'View Details' tooltip is shown for ACCOUNT2. The interface includes a sidebar with navigation links, a top header with the Euroclear logo and user information, and a bottom footer with copyright and legal notices.

BANK ID	CAP NAME	ACCOUNT ID	ACCOUNT TYPE	ACCOUNT STATUS	REPORTING FIRM ID	REPORTING FIRM CODE TYPE
		ACCOUNT1	Ordinary	Enabled		
		ACCOUNT2	Ordinary	Enabled		
		ACCOUNT3	Ordinary	Enabled		

3.4. Participant ISO Configuration

Certain ISO messages may be configured for the entire user and all its participants, or on an individual participant basis, and some may only be configured on an individual participant basis. As with the User ISO Configuration, an Unsolicited Common Interface operator must have been established for the reports to function.

3.4.1. Participant ISO Reports

Participant ISO reports are located within the *Entity Data > Subscriptions* section of the menu while acting as the participant to be configured. Before the reports may be enabled, a profile must be created by pressing the **Create Profile** button. Once a profile has been created, the below message types will appear in the list, and can be enabled or disabled by using the checkbox before pressing update at the bottom of the screen.

- MT 518** – Trade Confirmation
- MT 544** – Receive Free Confirmation
- MT 545** – Receive against Payment Confirmation
- MT 546** – Deliver Free Confirmation
- MT 547** – Deliver against Payment Confirmation
- MT 548** – Settlement Status
- MT 566** – Corporate Action Confirmation
- MT 567** – Corporate Action Instruction Status
- MT 578** – Settlement Allegement

3.4.2. CMA ISO Reports

Cash reports may be set up in the **CMA ISO Interface Report Profile List** screen from the *Entity Data > Subscriptions* section of the menu, while acting as the participant to be configured. Unlike the participant ISO reports, a profile does not need to be created. The below message types will appear in the list, and can be enabled or disabled by using the checkbox before pressing update at the bottom of the screen.

- MT 941** – Balance Report
- MT 940** – Customer Statement

3.4.3. Member Account ISO Reports

Member account reports may be set up in the **Member Account ISO Interface Report Profile List** screen from the *Entity Data > Subscriptions* section of the menu, while acting as the participant to be configured. Unlike the participant ISO reports, a profile does not need to be created. The below message types will appear in the list, and can be enabled or disabled by using the checkbox before pressing update at the bottom of the screen.

- MT 535** – Stock Balances (Complete)
- MT 535** – Stock Balances (Changed)
- MT 535** – Open Stock Balances
- MT 536** – Stock Postings
- MT 537** – Open Transactions (All)
- MT 537** – Open Transactions (Unmatched)
- MT 575** – Stamp Constituents



© 2025 Euroclear UK & International Limited is incorporated in England and Wales under registered number 2878738, with registered address at 33 Cannon Street, London EC4M 5SB, United Kingdom – Tel: +44 20 7849 0000 – Euroclear UK & International Limited is the operator of the CREST settlement system and the EMX Message System

Euroclear is the marketing name for the Euroclear System, Euroclear Holding SA/NV, Euroclear SA/NV and their affiliates. All rights reserved. The information and materials contained in this document are protected by intellectual property or other proprietary rights. All information contained herein is provided for information purposes only and does not constitute any recommendation, offer or invitation to engage in any investment, financial or other activity. We exclude to the fullest extent permitted by law all conditions, guarantees, warranties and/or representations of any kind with regard to your use of any information contained in this document. You may not use, publish, transmit, or otherwise reproduce this document or any information contained herein in whole or in part unless we have given our prior written consent. Your use of any products or services described herein shall be subject to our acceptance in accordance with the eligibility criteria determined by us.