



# **Built-in Exceptions**

In Python, all exceptions must be instances of a class that derives from BaseException. In a try statement with an except clause that mentions a particular class, that clause also handles any exception classes derived from that class (but not exception classes from which it is derived). Two exception classes that are not related via subclassing are never equivalent, even if they have the same name.

The built-in exceptions listed below can be generated by the interpreter or built-in functions. Except where mentioned, they have an "associated value" indicating the detailed cause of the error. This may be a string or a tuple of several items of information (e.g., an error code and a string explaining the code). The associated value is usually passed as arguments to the exception class's constructor.

User code can raise built-in exceptions. This can be used to test an exception handler or to report an error condition "just like" the situation in which the interpreter raises the same exception; but bew are that there is nothing to prevent user code from raising an inappropriate error.

The built-in exception classes can be subclassed to define new exceptions; programmers are encouraged to derive new exceptions from the Exception class or one of its subclasses, and not from BaseException. More information on defining exceptions is available in the Python Tutorial under User-defined Exceptions.

When raising (or re-raising) an exception in an except or finally clause \_\_context\_\_ is automatically set to the last exception caught; if the new exception is not handled the traceback that is eventually displayed will include the originating exception(s) and the final exception.

When raising a new exception (rather than using a bare raise to re-raise the exception currently being handled), the implicit exception context can be supplemented with an explicit cause by using from with raise:

```
raise new_exc from original_exc
```

The expression following from must be an exception or None. It will be set as \_\_cause\_\_ on the raised exception. Setting \_\_cause\_\_ also implicitly sets the \_\_suppress\_context\_\_ attribute to True, so that using raise new\_exc from None effectively replaces the old exception with the new one for display purposes (e.g. converting KeyError to AttributeError), while leaving the old exception available in \_\_context\_\_ for introspection when debugging.

The default traceback display code show s these chained exceptions in addition to the traceback for the exception itself. An explicitly chained exception in \_\_cause\_\_ is alw ays show n when present. An implicitly chained exception in \_\_context\_\_ is show n only if \_\_cause\_\_ is None and \_\_suppress\_context\_\_ is false.

In either case, the exception itself is alw ays shown after any chained exceptions so that the final line of the traceback alw ays shows the last exception that was raised.

## Base classes

The following exceptions are used mostly as base classes for other exceptions.

## exception BaseException

The base class for all built-in exceptions. It is not meant to be directly inherited by user-defined classes (for that, use Exception). If str() is called on an instance of this class, the representation of the argument(s) to the instance are returned, or the empty string when there were no arguments.

#### args

The tuple of arguments given to the exception constructor. Some built-in exceptions (like OSError) expect a certain number of arguments and assign a special meaning to the elements of this tuple, while others are usually called only with a single string giving an error message.

## with\_traceback(tb)

This method sets *tb* as the new traceback for the exception and returns the exception object. It was more commonly used before the exception chaining features of **PEP 3134** became available. The following example shows how we can convert an instance of SomeException into an instance of OtherException while preserving the traceback. Once raised, the current frame is pushed onto the traceback of the OtherException, as would have happened to the traceback of the original SomeException had we allowed it to propagate to the caller.

```
try:
    ...
except SomeException:
    tb = sys.exc_info()[2]
    raise OtherException(...).with_traceback(tb)
```

#### exception Exception

All built-in, non-system-exiting exceptions are derived from this class. All user-defined exceptions should also be derived from this class.

## exception ArithmeticError





Go

## exception BufferError

Raised when a buffer related operation cannot be performed.

### exception LookupError

The base class for the exceptions that are raised when a key or index used on a mapping or sequence is invalid: IndexError, KeyError. This can be raised directly by codecs.lookup().

## Concrete exceptions

The following exceptions are the exceptions that are usually raised.

### exception AssertionError

Raised when an assert statement fails.

#### exception AttributeError

Raised when an attribute reference (see Attribute references) or assignment fails. (When an object does not support attribute references or attribute assignments at all, TypeError is raised.)

The name and obj attributes can be set using keyw ord-only arguments to the constructor. When set they represent the name of the attribute that w as attempted to be accessed and the object that w as accessed for said attribute, respectively.

Changed in version 3.10: Added the name and obj attributes.

#### exception EOFError

Raised when the input() function hits an end-of-file condition (EOF) without reading any data. (N.B.: the io.IOBase.read() and io.IOBase.readline() methods return an empty string when they hit EOF.)

## exception FloatingPointError

Not currently used.

#### exception GeneratorExit

Raised when a generator or coroutine is closed; see generator.close() and coroutine.close(). It directly inherits from BaseException instead of Exception since it is technically not an error.

### exception ImportError

Raised when the import statement has troubles trying to load a module. Also raised when the "from list" in from ... import has a name that cannot be found.

The name and path attributes can be set using keyw ord-only arguments to the constructor. When set they represent the name of the module that w as attempted to be imported and the path to any file w hich triggered the exception, respectively.

Changed in version 3.3: Added the name and path attributes.

#### exception ModuleNotFoundError

A subclass of ImportError which is raised by import when a module could not be located. It is also raised when None is found in sys.modules.

New in version 3.6.

### exception IndexError

Raised when a sequence subscript is out of range. (Slice indices are silently truncated to fall in the allowed range; if an index is not an integer, TypeError is raised.)

## exception KeyError

Raised when a mapping (dictionary) key is not found in the set of existing keys.

### exception KeyboardInterrupt

Raised when the user hits the interrupt key (normally Control-C or Delete). During execution, a check for interrupts is made regularly. The exception inherits from BaseException so as to not be accidentally caught by code that catches Exception and thus prevent the interpreter from exiting.

### exception MemoryError

Raised when an operation runs out of memory but the situation may still be rescued (by deleting some objects). The associated value is a string indicating what kind of (internal) operation ran out of memory. Note that because of the underlying memory management architecture (C's malloc() function), the interpreter may not alw ays be able to completely recover from this situation; it nevertheless raises an exception so that a stack traceback can be printed, in case a run-aw ay program was the cause.







Go

The name attribute can be set using a keyw ord-only argument to the constructor. When set it represent the name of the variable that was attempted to be accessed.

Changed in version 3.10: Added the name attribute.

## exception NotImplementedError

This exception is derived from RuntimeError. In user defined base classes, abstract methods should raise this exception when they require derived classes to override the method, or while the class is being developed to indicate that the real implementation still needs to be added

Note: It should not be used to indicate that an operator or method is not meant to be supported at all - in that case either leave the operator / method undefined or, if a subclass, set it to None.

NotImplementedError and NotImplemented are not interchangeable, even though they have similar names and purposes. See Note: NotImplemented for details on when to use it.

## exception OSError([arg])

## exception **OSError**(errno, strerror[, filename[, winerror[, filename2]]])

This exception is raised when a system function returns a system-related error, including I/O failures such as "file not found" or "disk full" (not for illegal argument types or other incidental errors).

The second form of the constructor sets the corresponding attributes, described below. The attributes default to None if not specified. For backwards compatibility, if three arguments are passed, the args attribute contains only a 2-tuple of the first two constructor arguments.

The constructor often actually returns a subclass of OSError, as described in OS exceptions below. The particular subclass depends on the final errno value. This behaviour only occurs when constructing OSError directly or via an alias, and is not inherited when subclassing.

#### errno

A numeric error code from the C variable error

#### winerror

Under Windows, this gives you the native Windows error code. The errno attribute is then an approximate translation, in POSIX terms, of that native error code.

Under Windows, if the winerror constructor argument is an integer, the errno attribute is determined from the Windows error code, and the errno argument is ignored. On other platforms, the winerror argument is ignored, and the winerror attribute does not exist.

#### strerror

The corresponding error message, as provided by the operating system. It is formatted by the C functions perror() under POSIX, and FormatMessage() under Windows.

## filename

## filename2

For exceptions that involve a file system path (such as open() or os.unlink()), filename is the file name passed to the function. For functions that involve two file system paths (such as os.rename()), filename2 corresponds to the second file name passed to the function.

Changed in version 3.3: EnvironmentError, IOError, WindowsError, socket.error, select.error and mmap.error have been merged into OSError, and the constructor may return a subclass.

Changed in version 3.4: The filename attribute is now the original file name passed to the function, instead of the name encoded to or decoded from the filesystem encoding and error handler. Also, the filename2 constructor argument and attribute was added.

## exception OverflowError

Raised when the result of an arithmetic operation is too large to be represented. This cannot occur for integers (which would rather raise MemoryError than give up). How ever, for historical reasons, Overflow Error is sometimes raised for integers that are outside a required range. Because of the lack of standardization of floating point exception handling in C, most floating point operations are not checked.

### exception RecursionError

This exception is derived from RuntimeError. It is raised when the interpreter detects that the maximum recursion depth (see sys.getrecursionlimit()) is exceeded.

New in version 3.5: Previously, a plain RuntimeError w as raised.







#### exception RuntimeError

Raised when an error is detected that doesn't fall in any of the other categories. The associated value is a string indicating what precisely went wrong.

#### exception StopIteration

Raised by built-in function next() and an iterator's \_\_next\_\_() method to signal that there are no further items produced by the iterator.

The exception object has a single attribute value, which is given as an argument when constructing the exception, and defaults to None.

When a generator or coroutine function returns, a new StopIteration instance is raised, and the value returned by the function is used as the value parameter to the constructor of the exception.

If a generator code directly or indirectly raises StopIteration, it is converted into a RuntimeError (retaining the StopIteration as the new exception's cause).

Changed in version 3.3: Added value attribute and the ability for generator functions to use it to return a value.

Changed in version 3.5: Introduced the RuntimeError transformation via from \_\_future\_\_ import generator\_stop, see PEP 479.

Changed in version 3.7: Enable PEP 479 for all code by default: a StopIteration error raised in a generator is transformed into a RuntimeError.

## exception StopAsyncIteration

Must be raised by \_\_anext\_\_() method of an asynchronous iterator object to stop the iteration.

New in version 3.5.

#### exception SyntaxError(message, details)

Raised when the parser encounters a syntax error. This may occur in an import statement, in a call to the built-in functions compile(), exec(), or eval(), or when reading the initial script or standard input (also interactively).

The str() of the exception instance returns only the error message. Details is a tuple whose members are also available as separate attributes.

#### filename

The name of the file the syntax error occurred in.

#### lineno

Which line number in the file the error occurred in. This is 1-indexed; the first line in the file has a lineno of 1.

### offset

The column in the line where the error occurred. This is 1-indexed: the first character in the line has an offset of 1.

#### text

The source code text involved in the error.

## end\_lineno

Which line number in the file the error occurred ends in. This is 1-indexed: the first line in the file has a lineno of 1.

## end\_offset

The column in the end line where the error occurred finishes. This is 1-indexed: the first character in the line has an offset of 1.

For errors in f-string fields, the message is prefixed by "f-string:" and the offsets are offsets in a text constructed from the replacement expression. For example, compiling f'Bad  $\{a\ b\}$  field' results in this args attribute: ('f-string: ...', (", 1, 2, '(a b)n', 1, 5)).

Changed in version 3.10: Added the end\_lineno and end\_offset attributes.

## exception IndentationError

Base class for syntax errors related to incorrect indentation. This is a subclass of SyntaxError.

## exception TabError

Raised when indentation contains an inconsistent use of tabs and spaces. This is a subclass of IndentationError.

## exception SystemError

Go





You should report this to the author or maintainer of your Python interpreter. Be sure to report the version of the Python interpreter (sys.version; it is also printed at the start of an interactive Python session), the exact error message (the exception's associated value) and if possible the source of the program that triggered the error.

### exception SystemExit

This exception is raised by the <code>sys.exit()</code> function. It inherits from <code>BaseException</code> instead of <code>Exception</code> so that it is not accidentally caught by code that catches <code>Exception</code>. This allows the exception to properly propagate up and cause the interpreter to exit. When it is not handled, the Python interpreter exits; no stack traceback is printed. The constructor accepts the same optional argument passed to <code>sys.exit()</code>. If the value is an integer, it specifies the system exit status (passed to C's <code>exit()</code> function); if it is <code>None</code>, the exit status is zero; if it has another type (such as a string), the object's value is printed and the exit status is one.

A call to sys.exit() is translated into an exception so that clean-up handlers (finally clauses of try statements) can be executed, and so that a debugger can execute a script without running the risk of losing control. The os.\_exit() function can be used if it is absolutely positively necessary to exit immediately (for example, in the child process after a call to os.fork()).

#### code

The exit status or error message that is passed to the constructor. (Defaults to None.)

#### exception TypeError

Raised when an operation or function is applied to an object of inappropriate type. The associated value is a string giving details about the type mismatch.

This exception may be raised by user code to indicate that an attempted operation on an object is not supported, and is not meant to be. If an object is meant to support a given operation but has not yet provided an implementation, NotImplementedError is the proper exception to raise

Passing arguments of the wrong type (e.g. passing a list when an int is expected) should result in a TypeError, but passing arguments with the wrong value (e.g. a number outside expected boundaries) should result in a ValueError.

#### exception UnboundLocalError

Raised when a reference is made to a local variable in a function or method, but no value has been bound to that variable. This is a subclass of NameError

## exception UnicodeError

Raised when a Unicode-related encoding or decoding error occurs. It is a subclass of ValueError.

UnicodeError has attributes that describe the encoding or decoding error. For example, err.object[err.start:err.end] gives the particular invalid input that the codec failed on.

### encoding

The name of the encoding that raised the error.

#### reason

A string describing the specific codec error.

## object

The object the codec was attempting to encode or decode.

#### start

The first index of invalid data in object.

### end

The index after the last invalid data in object.

## exception UnicodeEncodeError

Raised when a Unicode-related error occurs during encoding. It is a subclass of UnicodeError.

## exception UnicodeDecodeError

Raised when a Unicode-related error occurs during decoding. It is a subclass of UnicodeError.

## exception UnicodeTranslateError

Raised when a Unicode-related error occurs during translating. It is a subclass of  $\mbox{UnicodeError}$ .

## exception ValueError

Raised when an operation or function receives an argument that has the right type but an inappropriate value, and the situation is not described by a more precise exception such as IndexError.



The following exceptions are kept for compatibility with previous versions; starting from Python 3.3, they are aliases of OSError.

#### exception EnvironmentError

#### exception IOError

#### exception WindowsError

Only available on Windows.

## OS exceptions

The following exceptions are subclasses of OSError, they get raised depending on the systemerror code.

## exception BlockingIOError

Raised when an operation would block on an object (e.g. socket) set for non-blocking operation. Corresponds to errno EAGAIN, EALREADY, EWOULDBLOCK and EINPROGRESS.

In addition to those of OSError, BlockingIOError can have one more attribute:

#### characters\_written

An integer containing the number of characters written to the stream before it blocked. This attribute is available when using the buffered I/O classes from the io module.

## exception ChildProcessError

Raised when an operation on a child process failed. Corresponds to errno ECHILD.

## exception ConnectionError

A base class for connection-related issues.

Subclasses are BrokenPipeError, ConnectionAbortedError, ConnectionRefusedError and ConnectionResetError.

## exception BrokenPipeError

A subclass of ConnectionError, raised when trying to write on a pipe while the other end has been closed, or trying to write on a socket which has been shutdown for writing. Corresponds to error EPIPE and ESHUTDOWN.

## exception ConnectionAbortedError

A subclass of ConnectionError, raised when a connection attempt is aborted by the peer. Corresponds to errno ECONNABORTED.

## exception ConnectionRefusedError

 $A \ subclass \ of \ {\it ConnectionError}, \ raised \ when \ a \ connection \ attempt \ is \ refused \ by \ the \ peer. \ {\it Corresponds} \ to \ errno \ {\it ECONNREFUSED}.$ 

## exception ConnectionResetError

A subclass of ConnectionError, raised when a connection is reset by the peer. Corresponds to errno ECONNRESET.

## exception FileExistsError

Raised when trying to create a file or directory which already exists. Corresponds to errno EEXIST.

## exception FileNotFoundError

Raised when a file or directory is requested but doesn't exist. Corresponds to errno ENOENT.

## exception InterruptedError

Raised when a system call is interrupted by an incoming signal. Corresponds to errno EINTR.

Changed in version 3.5: Python now retries system calls when a syscall is interrupted by a signal, except if the signal handler raises an exception (see PEP 475 for the rationale), instead of raising InterruptedError.

### exception IsADirectoryError

Raised when a file operation (such as os.remove()) is requested on a directory. Corresponds to errno EISDIR.

## exception NotADirectoryError

Raised when a directory operation (such as os.listdir()) is requested on something which is not a directory. On most POSIX platforms, it may also be raised if an operation attempts to open or traverse a non-directory file as if it were a directory. Corresponds to errno ENOTDIR.



### exception ProcessLookupError

Raised when a given process doesn't exist. Corresponds to errno ESRCH.

#### exception TimeoutError

Raised when a system function timed out at the system level. Corresponds to errno ETIMEDOUT.

New in version 3.3: All the above OSError subclasses were added.

See also: PEP 3151 - Rew orking the OS and IO exception hierarchy

## Warnings

The following exceptions are used as warning categories; see the Warning Categories documentation for more details.

#### exception Warning

Base class for warning categories.

#### exception UserWarning

Base class for warnings generated by user code.

#### exception DeprecationWarning

Base class for warnings about deprecated features when those warnings are intended for other Python developers.

Ignored by the default warning filters, except in the \_\_main\_\_ module (PEP 565). Enabling the Python Development Mode shows this warning.

The deprecation policy is described in PEP 387.

#### exception PendingDeprecationWarning

Base class for warnings about features which are obsolete and expected to be deprecated in the future, but are not deprecated at the moment

This class is rarely used as emitting a warning about a possible upcoming deprecation is unusual, and DeprecationWarning is preferred for already active deprecations.

Ignored by the default warning filters. Enabling the Python Development Mode shows this warning.

The deprecation policy is described in PEP 387.

## exception SyntaxWarning

Base class for warnings about dubious syntax.

## exception RuntimeWarning

Base class for warnings about dubious runtime behavior.

#### exception FutureWarning

Base class for warnings about deprecated features when those warnings are intended for end users of applications that are written in Python.

### exception ImportWarning

Base class for warnings about probable mistakes in module imports.

Ignored by the default warning filters. Enabling the Python Development Mode shows this warning.

## exception UnicodeWarning

Base class for warnings related to Unicode.

### exception EncodingWarning

Base class for warnings related to encodings.

See Opt-in EncodingWarning for details.

New in version 3.10.

## exception BytesWarning

Base class for warnings related to bytes and bytearray.



3.10.0



Go

Ignored by the default warning filters. Enabling the Python Development Mode shows this warning.

New in version 3.2.

## **Exception hierarchy**

The class hierarchy for built-in exceptions is:

```
{\bf Base Exception}
 +-- SystemExit
 +-- KeyboardInterrupt
 +-- GeneratorExit
 +-- Exception
     +-- StopIteration
      +-- StopAsyncIteration
      +-- ArithmeticError
         +-- FloatingPointError
          +-- OverflowError
          +-- ZeroDivisionError
      +-- AssertionError
      +-- AttributeError
      +-- BufferError
      +-- EOFError
      +-- ImportError
           +-- ModuleNotFoundError
      +-- LookupError
          +-- IndexError
          +-- KeyError
      +-- MemoryError
      +-- NameError
           +-- UnboundLocalError
      +-- OSError
           +-- BlockingIOError
           +-- ChildProcessError
           +-- ConnectionError
               +-- BrokenPipeError
               +-- ConnectionAbortedError
               +-- ConnectionRefusedError
                +-- ConnectionResetError
           +-- FileExistsError
           +-- FileNotFoundError
           +-- InterruptedError
           +-- IsADirectoryError
           +-- NotADirectoryError
           +-- PermissionError
           +-- ProcessLookupError
           +-- TimeoutError
      +-- ReferenceError
      +-- RuntimeError
          +-- NotImplementedError
           +-- RecursionError
      +-- SyntaxError
           +-- IndentationError
               +-- TabError
      +-- SystemError
      +-- TypeError
      +-- ValueError
           +-- UnicodeError
               +-- UnicodeDecodeError
                +-- UnicodeEncodeError
               +-- UnicodeTranslateError
      +-- Warning
           +-- DeprecationWarning
           +-- PendingDeprecationWarning
           +-- RuntimeWarning
           +-- SyntaxWarning
           +-- UserWarning
           +-- FutureWarning
           +-- ImportWarning
           +-- UnicodeWarning
           +-- BytesWarning
           +-- EncodingWarning
           +-- ResourceWarning
```