

TITLE: CMSMS Config Variables AUTHOR: Robert Campbell

Copyright and License:

copyright © 2011 by the CMS Made Simple development team. All Rights Are Reserved.

This document is free. You can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

However, as a special restriction to the GPL, when modifying and redistributing this document this notice in its entirety, along with a list of further copyright entitlements must be provided.

This document is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA. Or read it online

© 2011 CMS Made Simple™ Page 1 of 13



Table of Contents

Copyright and License:	1	
ntroduction:	3	3
Scope:	3	3
Organization:	3	3
Variable Reference:	3	3
dbms	3	3
db_hostname	3	3
db_name	3	3
db_username	4	ļ
db_password	4	ļ
db_prefix	4	ļ
db_port	4	ļ
timezone	5	5
root_path	5	5
root_url	5	5
ssl_url	5	5
admin_url	5	5
uploads_path	6	3
uploads_url	6	3
ssl_uploads_url	6	3
image_uploads_path	6	3
image_uploads_url	6	3
debug	7	7
admin_dir	7	7

persist_db_conn	7
use_adodb_lite	7
process_whole_template	8
output_compression (deprecated)	8
previews_path (deprecated)	
max_upload_size (deprecated)	
default_upload_permission (deprecated)	
use_smarty_php_tags	
auto_alias_content	
url_rewriting	9
page_extension	
query_var	10
image_manipulation_prog	
image_transform_lib_path	10
locale	
admin_encoding	11
default_encoding	
set_names	11
wiki_url	11
show_performance_info	12
debug_to_log	12
Revision History:	13
debug_to_log	12



-____

Introduction:

This document is intended to provide a reference to the various config variables available in CMS Made Simple, and how to use them. It is intended as a reference for those people familiar with such concepts as database connectivity, file paths, permissions, and url rewriting, not as a tutorial or how-to guide.

Scope:

This document describes the variables as available in CMS Made Simple version 1.10 it does not include descriptions of variables used by third party addon modules, or for previous versions of CMSMS. Additionally, this document cannot be considered a complete reference. third party modules and plugins may ignore some of these values or add their own.

Organization:

This document is organized roughly by the importants of the variables, from the top down. Most commonly used configuration variables will be described first.

Variable Reference:

dbms

Description: Specifies the database management system and libraries that

CMSMS should use.

Status: Required Type: String

Accepted Values: mysql, mysqli, postgres

db_hostname

Description: Specifies the hostname of the system that hosts the database.. This

should be provided by your host.

Status: Required Type: String

Accepted Values: Any hostname, or IP address. 'localhost' is the proper value on most

hosts.

db_name

Description: Specifies the name of the database that CMSMS should use

Status: Required Type: String

Accepted Values: A valid database name. If you are unsure of this value, contact your

hosting provider.

© 2011 CMS Made SimpleTM Page 3 of 13



db_username

Description: The username of the database user that has sufficient privilege to the

database name specified above. This is used to allow CMSMS to

connect to the database.

Status: Required Type: String

Accepted Values: The username of your account, or the database username created in

the admin console. Contact your host for the proper value for this field

if you are uncertain.

db_password

Description: Specify the password associated to the database user. This is used to

allow CMSMS to connect to the database.

Status: Required Type: String

Accepted Values: The password (plain text) that is associated with the database

username specified above.

db_prefix

Description: Specify a prefix to use infront of all table names. This variable can be

used to allow multiple applications to coexist inside the dame

database.

Status:RequiredType:StringDefault Value:cms_

db_port

Description: Specify an alternate port number to use when connecting to the

database. This is useful when your database is available on a port that is not the standard. The information provided from your host

should indicate this.

Status: Optional Type: integer

Default Value: 3306 for mysql, may be different for postgres or other systems.

© 2011 CMS Made Simple™ Page 4 of 13



timezone

Description: The server system timezone. This is used for ensuring that time

calculations between the database and the server itself are

synchronized.

Note: Note: Behaviour has changed regarding timezones between PHP

versions, when running PHP 5.2 this variable may not need to be set. However in PHP 5.3 it needs to be set to a valid value for your server.

Status: Required Type: String

Example: \$config['timezone'] = 'America/Denver';

Accepted Values: See this link: http://www.php.net/manual/en/timezones.php

See Also: http://php.net/manual/en/function.date-default-timezone-set.php

root_path

Description: Specify the full and complete filesystem path to this CMSMS

installation

Status: Optional Type: String

Accepted Values: A valid path specification

Default Value: Determined automatically from the script location.

root_url

Description: Specify the normal (insecure) URL to the top of your website.

Status: Optional Type: String

Accepted Values: The valid fully qualified URL to the home page of the website.

Default Value Determined Automatically from server variables.

ssl url

Description: Specify the secure URL to the top of your website

Status: Optional Type: String

Accepted Values: A valid fully qualified HTTPS url to the home page of the website

Default Value: The root url with http:// replaced with https://

admin_url

Description: A url to specify a web accessible url to the CMSMS admin console

Status: Optional Type: String

Default Value: \$config['root_url'].'/'.\$config['admin_dir']

© 2011 CMS Made SimpleTM Page 5 of 13



uploads_path

Description: This variable contains the absolute filesystem path to the location

where files should be uploaded.

Status: Optional Type: String

Accepted Values: A valid filesystem path. Please ensure permissions are set correctly

to allow the web server to write files to this directory.

Default Value: \$config['root_path'].'/uploads';

uploads_url

Description: The web accessible URL that corresponds to the uploads path

Status: Optional **Type**: String

Accepted Values: A valid web acceptable URL. Please ensure that it corresponds to the

uploads_path variable specified above.

Default Value: \$config['root_url'].'/uploads';

ssl_uploads_url

Description: Specify the secure version of the URL corresponding to your

uploads_url above. This is only necessary when using SSL for some

or all pages.

Status: Optional **Type**: String

Accepted Values: A valid, web accessible URL. Please ensure that it corresponds to the

uploads path variable specified above.

Default Value: \$config['ssl_url'].'/uploads';

image_uploads_path

Description: The path used by the image manager and other functionality to upload

and manages images for your website.

Status: Optional Type: String

Accepted Values: A fully qualified filesystem path where images should be stored.

Default Values: \$config['uploads_path'].'/images';

image_uploads_url

Description: Specify the web accessible URL where images will be available. This

must correspond to the image_uploads_path above.

Status: Optional.

Type: String

Accepted Values: A web accessible URL

Default Values: \$config['uploads_url'].'/images'

© 2011 CMS Made Simple™ Page 6 of 13



debug

Description: Indicates wether debug mode is enabled. When debug mode is

enabled automatic redirection is disabled and query and trace information is appended to the output. This mode should also be enabled to assist in diagnosing errors when error messages are

hidden by default.

Status: Optional Type: boolean Accepted Values: true or false

Default Value: FALSE

admin_dir

Description: Specify the name of the admin directory. This option can be used by

advanced users to specify an alternate admin directory name.

Although this may cause difficulty with the upgrade process.

Status: Optional Type: String

Accepted Values: A valid directory name (relative to the root_path above).

Default Value: admin

persist_db_conn

Description: A flag that indicates wether persistent database connections should

be used. This variable may be of use on high load servers. Contact your host if encountering problems and wondering wether this setting

should be used.

Status:OptionalType:booleanAccepted Values:true or false

Default Value: FALSE

use_adodb_lite

Description: An optional variable indicating wether the system should look for the

(default) adodb_lite system, or the optional full adodb database abstraction library. CMSMS ships with adodb_lite but is capable of $\,$

operating with the full adodb if specified.

Status:OptionalType:IntegerDefault Value:1Accepted Values:0 or 1

© 2011 CMS Made Simple™ Page 7 of 13



process_whole_template

Description: By default CMSMS will process your page template in three pieces.

Firstly the portion above the head section, then the body section, and then the head section. This allows smarty variables created in the body section to be utilized in the head for things like page title and

meta data.

Status:OptionalType:booleanAccepted Values:true or false

Default Value: FALSE

output_compression (deprecated)

Description: Specify wether CMSMS should enable output compression for each

request.

Note: This option is deprecated, and will be removed at a later date. The

server config options provide a better mechanism to enable output compression and this option may interfere with the functionality of

some modules i.e: for downloading files.

Status:OptionalType:booleanAccepted Values:true or false

Default Value: FALSE

previews_path (deprecated)

Description: Specify a location where the temporary information used for

generating previews should be stored.

Status:OptionalType:string

Accepted Values: A complete path specification that has write permissions by the web

server process.

Default Value: Internal value.

max_upload_size (deprecated)

Description: A value (in bytes) that specifies the maximum size of files that can be

uploaded to your website.

Note: This value does not override server settings. If experiencing problems

with limited file upload sizes please check your server configuration.

Status: Optional Type: integer Accepted Values: integer

Default Value: The maximum upload size specified by the system.

See Also: http://php.net/manual/en/ini.core.php

© 2011 CMS Made SimpleTM Page 8 of 13



default_upload_permission (deprecated)

Description: Specify the permission that should be given (by default) to uploaded

files.

Status: Optional

Type: String representing octal value

Example:: \$config['default_upload_permission'] = '644';

Default Value: 644

use_smarty_php_tags

Description: Indicate wether smarty {php} tags should be allowed in templates.

This is an advanced option which should only be enabled by

experionced developers who are familiar with the potential drawbacks

to this functionality.

Status:OptionalType:BooleanDefault Value:FALSE

auto alias content

Description: Specify wether page aliases should automatically be created for new

pages.

Status:OptionalType:BooleanDefault Value:FALSE

url_rewriting

Description: What type of URL rewriting should we be using for pretty URLs. The

possible values for this variable are system dependant.

Status: Optional Type: String

Accepted Values: none, internal, mod_rewrite

Example:: \$config['default_upload_permission'] = 'none';

Default Value: none

See Also: http://wiki.cmsmadesimple.org/index.php/FAQ/Installation/Pretty_URL

s#Pretty_URLs

page_extension

Description: Used when the url_rewriting is a value other than 'none' this variable

specifies the extension that should be appended to all URLS that the

system generates.

Status: Optional Type: String Default Value: n/a

Example: \$config['page_extension'] = '.html';

© 2011 CMS Made Simple™ Page 9 of 13



query_var

Description: Specifies the name of the URL variable that will indicate the page

alias. You should not need to override this value unless the default

value interferes with another software package.

Status:OptionalType:StringDefault Value:page

image_manipulation_prog

Description: Specify the program (or library) that should be used for image

manipulation.

Status: Optional Type: String Default Value: gd

Accepted Values gd or imagemagick

See Also: http://wiki.cmsmadesimple.org/index.php/User_Handbook/Admin_Pan

el/Content/Image_Manager

image_transform_lib_path

Description: When using imagemagick as a manipulation program specify the

library path to that program.

Status: Optional Type: String

Default Value: /usr/bin/ImageMagick

locale

Description: Locale to use for various default date handling functions, etc. Leaving

this blank will use the server's default. This might not be good if the

site is hosted in a different country than it's intended audience.

Note: Though you can specify any valid locale, the locale information you

specify must be installed on the server.

Status: Optional Type: String Default Value: n/a

See Also: http://php.net/manual/en/function.setlocale.php

© 2011 CMS Made SimpleTM Page 10 of 13



admin_encoding

Description: Specify the encoding to use for admin translations.

Note: In almost all cases, default_encoding should be empty (which defaults

to utf-8) and admin_encoding should be utf-8. If you'd like this to be different, change both. Keep in mind, however, that the admin interface translations are all in utf-8, and will be converted on the fly to match the admin_encoding. This could seriously slow down the

admin interfaces for users.

Status: Optional Type: string Default Value: utf-8

default_encoding

Description: Specify the encoding to use for admin translations.

Note: In almost all cases, default_encoding should be empty (which defaults

to utf-8) and admin_encoding should be utf-8. If you'd like this to be different, change both. Keep in mind, however, that the admin

interface translations are all in utf-8, and will be converted on the fly to match the admin_encoding. This could seriously slow down the

admin interfaces for users.

Status: Optional Type: string Default Value: n/a

set_names

Description: A flag indicating wether a 'set names' command should be given to a

mysql database upon connection. Applies to mysql only

Status:OptionalType:BooleanDefault Value:FALSE

wiki url

Description: A URL indicating where the CMSMS wiki is located. Used for help

links

Status: Optional **Type**: string

Default Value: http://wiki.cmsmadesimple.org/index.php/User_Handbook/Admin_Pan

el

© 2011 CMS Made SimpleTM Page 11 of 13



show_performance_info

Description: A flag indicating wether performance information should be appended

to all output from CMSMS requests.

Note: This setting when enabled could interfere with the output of some

modules, for example when downloading files or exporting XML

information.

Status:OptionalType:BooleanDefault Value:FALSE

debug_to_log

Description: A flag indicating wether the debug_to_log method should actually

output anything. This variable should be set to false for production

environments.

Status:OptionalType:BooleanDefault Value:FALSE

© 2011 CMS Made SimpleTM Page 12 of 13



Revision History:

August 2011 - Robert Campbell

Initial Revision

© 2011 CMS Made SimpleTM Page 13 of 13