> **Current instructions:** Start with the current user guide and its five workspace chapters. They cover the included audio-tool-import-1 application and take precedence over preserved historical chapters, control rows and version claims below. Use them for composing from scratch, current imports, save formats and supported recovery.

NES Forge user manual

Alpha.11 reading edition · restored complete 1.9.0 manual with current usage notes

Use the Tutorial for the current first-project path, and read Alpha.11 usage updates before the longer reference below. The original full workshop and control chapters have been restored; this is not a claim that every historical control table has been rewritten or revalidated for alpha.11.

The supplied application is **2.0.0-alpha.11 / audio-tool-import-1**, schema 12, SHA-256 `1fd884cdc1b568b72e3bc777ef3a0b1a926b6020e8b143d8110a9a9001dc821d`. All older application hashes, dated success totals and future-version promises below describe the historical edition only.

Current correction to the historical text	What to use now
MusicXML/MIDI export	**AUDIO → Export Score Data** exports supported scores. It is not a full native project/timbre backup.
Source authoring	**CODE → Open source workspace → Build source ROM** assembles the bounded `forge-6502-v1` NROM profile. Save the source workspace separately.
Source intake	**Analyze source** is diagnostic inspection; it does not prove a build or migration.
Newer editor workflows	Seeded mashup, Movement rules and declared native recovery routes have their own current guides.
Mobile diagnostics	Expanded Play exposes current performance readings. Follow the updated triage guide instead of old scheduling/status-line advice.
Control inventory and illustrations	The restored tables and images document 1.9.0. Use the current supplement for selected additions.

Open the full alpha.11 updates, Operator Reference, Reviewer Checklist, or Mobile Performance Triage. Use Feedback_Template.txt to report a difference between a guide and the interface.

Preserved 1.9.0 manual and workshop

> **Historical chapter scope.** The following complete chapters originate in the September 30, 2026 kit. Version/date-specific claims below belong to that edition. Current instructions above override them. Original Markdown is retained verbatim in `Reference/Historical/Documentation_Source/`; the rendered reading copy corrects local links and marks known superseded statements.

NES Forge 1.9.0


User Manual and Blank-Project Workshop

Reviewer documentation edition · Gameplay Core — Alpha / mobile-play-1 · September 30, 2026

Start with an empty project, make your own terrain and character, connect the authoring tabs, build a World, and then add supported gameplay and sound. No imported Scout project or prebuilt JSON is required for the workshop.

> **About the historical 1.9.0 copy:** That edition updated the reconstructed comprehensive manual and blank-project workshop for the September 28 Mobile Play candidate. Its original application was included unchanged in the September 30 archive. It is a functional alpha for review, not an accepted release. The September 28 package records 702/702 automated checks in 28 suites; no new application regression run or fresh browser replay of the workshop is claimed by this documentation update.

Start here



Historical blank-project illustration from the corrected Gameplay Core reference. It shows the workshop starting point, not a fresh screenshot of Mobile Play.

Extract the ZIP before opening its contents. Open **START_HERE.html** for the package entry page, **Manual.html** for the comprehensive manual, or **Manual.pdf** for reading and printing. Open **NES_Forge.html** separately to work in the editor. The focused **Tutorial.html** / **Tutorial.pdf** follows the blank-project workshop. Keep the instructions beside the editor in another window.

The workshop is documentation you follow inside ordinary NES Forge. It is not a second application, embedded wizard, special project mode or supplied starter game. Build the first World on the device where you can comfortably use the authoring panels; then use the same generated ROM to review mobile play.

Historical September 30 review status	Evidence / boundary
Core create/build/play workflow	Functional 1.9.0 alpha candidate with the existing September 28 regression evidence.
Mobile touch controls	Owner reports they work on September 30; device/browser details are not yet recorded.
Mobile audio/video performance	Owner reports lag; cause, scope and measurements remain open.
Physical USB/Bluetooth controllers	Implemented through the browser, but actual controller hardware remains untested.
Acceptance	Further browser/device checks and owner acceptance remain pending.

The quickest useful learning order is **Orientation → Blank-project workshop → Gameplay Core → Audio → Saving and troubleshooting**. Use the tab reference when a particular control is unfamiliar. You do not need to read the architecture documents to complete the workshop.

The supporting **Reference/Operator_Reference.html** / **PDF** describes every documented control, and **Reference/Control_Index.csv** provides a searchable control table. Application source and historical evidence retain their original version statements; use the current status in this manual and the review-kit entry page when those historical statements differ.

Orientation: what NES Forge is doing

NES Forge is an NES authoring application, generated-ROM toolchain, and bundled emulator. Different editor tabs work on different representations. Seeing artwork in one editor does not automatically place it in every other editor or in the running game.

The terrain path is **background CHR → Metatile definition → World placement → World Runtime → ROM**. The retained animated Player path is **sprite CHR → Metasprite pose → Animation → Entity Studio bindings → selected World Player → ROM**. Gameplay Core adds reusable Actor Definitions, placed Actor Instances, behavior tables, and scoped variables to supported generated runtimes. AUDIO compiles tracker data when its runtime option is enabled. These paths meet at Build & Run, not merely when you change tabs. [S1, S2, S3]

The four distinctions that prevent most confusion

Distinction	Meaning in this candidate
Scene versus World	A Scene owns source art, palettes and legacy scene/entity data. A World references a Scene's metatile library and places terrain across screens.
Sprite versus Metasprite	A raw sprite is a hardware-sized placement. A Metasprite is a reusable composition of pieces with an origin; it is useful for character poses.
Entity Studio versus Gameplay Core	Entity Studio supplies retained Player/Target animation bindings. Gameplay Core provides canonical definitions, instances and a bounded behavior evaluator. The compatibility Player still uses the retained executor.
Project versus ROM	JSON/ZIP is the native editable backup. A ROM is executable output; the ability to recover editable source from it depends on its backend.

Why an object sometimes appears in one tab but not another

METASPRITES shows a pose. ANIM shows a selected frame and contacts/events. ENTITY STUDIO previews a selected entity and its bindings. SCENE shows the active scene composition. WORLD shows the World map and its authoring markers. GAMEPLAY CORE is primarily a set of typed authoring tables. **None of these is a persistent live view of the running ROM.** Use EMULATOR after Build & Run to see the game that was actually compiled. [S1, S4]

Scroll the sidebar all the way down before concluding a panel is missing. WORLD RUNTIME is near the lower part of WORLD; Gameplay Core tables live under the gameplay panel. Collapsed sections must be expanded. The small first canvas you see may be a pose editor rather than the entire Scene.

Hexadecimal tile labels versus numeric inputs

Tile sheets label indices such as `$10`. That is hexadecimal 10, which is decimal **16**. When a field is an ordinary number input, enter the decimal value: `$01` is 1, `$10` is 16, `$11` is 17, and `$FF` is 255. A wrong tile number can select valid but unrelated artwork.

Build modes at a glance

Mode	What you get
Scene viewer	Displays selected packed scenes; it is not automatically a platformer.
First Playable Room	Retained single-room Player/optional Target gameplay configured through the existing gameplay panel.
World Runtime	Explicitly selected Player traverses authored Worlds through screen transitions and linked markers.
Gameplay Core enabled	Adds the supported canonical Actor/Behavior subset to applicable generated single-room or World execution.
Authored assembly	CODE supplies the program. It is an advanced route, not required by the workshop; generated World and Audio features do not silently merge into arbitrary assembly.

Build & Run builds the current editor project. Run Original plays retained cartridge bytes without applying your current edits. Changing the project does not hot-reload the running game in this release. [S1, S2, S3]

Before your first edit

Save any open project before choosing New Project. Begin with a blank project, leave CODE empty, leave Audio Runtime and Gameplay Core off until the terrain/Player loop works, and enable World Runtime only after its required references exist. Save a native project checkpoint after each major workshop section.

Blank-project World workshop

This is the preserved from-scratch workshop adapted to the current 1.9.0 alpha candidate. The main terrain and retained Player path is deliberately learned with Gameplay Core and Audio off; later chapters add both. You may begin with an 8×8 player to prove the references, then upgrade to a four-piece or six-piece pose. This rebuilt edition does not claim a new automated replay of these steps. [S2, S6]

Workshop I — Start completely blank

Step 1. Open the kit and choose your working window

1. Extract the entire package to one folder; leave its companion files and image folders together.
2. Open **START_HERE.html**, then open **NES_Forge.html** in a separate browser tab or window.
3. Keep **Tutorial.html** or this manual visible beside the application. These instructions do not run inside a separate workshop mode.
4. Save/export any project already open before choosing New Project. The workshop starts blank and needs no imported project or ROM.
5. For this first pass, leave Gameplay Core and Audio Runtime disabled until the terrain/Player loop is working. Later chapters introduce them separately.

Checkpoint: you can see the normal NES Forge editor and the workshop instructions. You have not overwritten an existing project.

Coordinate convention: cell coordinates are zero-based. X=0/Y=0 is the top-left cell. SCENE samples use 8×8 tile positions; WORLD uses 16×16 metatile positions. Tile labels such as `$10` are hexadecimal; type **16** in an ordinary numeric Tile input.

Step 2. Create the project

1. Open the included **NES Forge 1.9.0 Alpha — Mobile Play** application, `NES_Forge.html`.
2. Click **New Project**.
3. Stay with the default scene, **My First Room**.
4. Make sure **CODE** is empty.

A blank New Project starts with:

- one Side-View source scene,
- no Worlds,
- no entities,
- no metasprites,
- no animations,
- blank BG CHR,

- blank Sprite CHR,
- World Runtime disabled.

You can rename the project/scene later. For the tutorial, `My First Room` is fine.

Workshop II — Create terrain from your own CHR

If you already know how to draw CHR tiles, this section is the important bridge from **CHR** into **METATILES** and then **WORLD**.

Step 3. Draw one background tile

Open **CHR SHEET**.

1. Select **BG Bank ($0000)**.
2. Select tile **$01**.
3. Draw any visible 8×8 ground/brick pattern.
4. Leave tile **$00** blank. We will use `$00` as empty/background space.

Your artwork does not have to match Scout. Mechanically, we only need:

- `$00` = empty-looking tile,
- `$01` = visible ground tile.

Choose/edit a BG palette so `$01` is visible.

Checkpoint

You should now have at least one visible BG tile in CHR SHEET.

Step 4. Tell NES Forge that tile $01 is solid

Open **COLLISION**.

1. Under **Active Property**, choose **1 - Solid (blocks all)**.
2. In **Tile Assignments**, click BG tile **$01**.
3. Leave `$00` as **0 - Empty**.

For the retained World Runtime profile, executable terrain may use **Empty** and **Solid** collision. Other authored collision types are retained by NES Forge but are not currently valid for World Runtime terrain.

Step 5. Build a 16×16 "Ground Surface" sample in SCENE

A metatile is four 8×8 BG tiles:

```
TL  TR
BL  BR
```

We are going to make a useful Scout-style ground surface whose top 8 pixels are empty and bottom 8 pixels are solid:

```
$00  $00      collision: Empty  Empty
$01  $01                 Solid  Solid
```

In CHR SHEET

1. Select **BG Bank**.
2. Click tile `$01` so it becomes the current Scene brush.

In SCENE

At the **top-left 16×16 cell** of the Scene:

1. Leave the top-left 8×8 tile as `$00`.
2. Leave the top-right 8×8 tile as `$00`.
3. Paint `$01` into the bottom-left 8×8 position.
4. Paint `$01` into the bottom-right 8×8 position.

The two painted bottom tiles are Scene tile coordinates **(0,1)** and **(1,1)**. They are the second row of 8×8 tiles within the top-left sample.

You have just created a temporary 16×16 source sample.

Step 6. Convert that sample into a reusable metatile

Open **METATILES**.

1. Use **Select cells**.
2. Click the 16×16 sample cell you just made.
3. Click **+ From Selected Cell**.
4. Rename it **Ground Surface**.
5. Set Category to `terrain` if desired.

The Selected Metatile should represent:

```
CHR QUADRANTS
TL = $00
TR = $00
BL = $01
BR = $01

COLLISION QUADRANTS
```

```
TL = Empty
TR = Empty
BL = Solid
BR = Solid
```

Because `$01` was marked Solid in COLLISION before the metatile was created, NES Forge should capture that collision into the bottom quadrants.

Detach the sample cell

Click **Detach Selected Cell**.

This is useful for a from-scratch workflow: it keeps **Ground Surface** in the Metatile Library, but prevents this temporary source sample from automatically seeding the first World when you press **+ World**.

> If you do not detach sample cells, that is not data loss or a bug. A new World is initially seeded from the source scene's linked 16×15 `metaMap`, so those linked sample cells can appear in the first World. You can simply erase them there. Detaching first gives you a cleaner blank World.

Step 7. Create a full Solid Block metatile

We also want a completely solid 16×16 block.

In SCENE

Use `$01` to turn the same temporary 16×16 source cell into:

```
$01  $01
$01  $01
```

In METATILES

1. Select that same 16×16 cell.
2. Click **+ From Selected Cell**.
3. Rename the new definition **Solid Block**.
4. Confirm all four Collision Quadrants are **Solid**.
5. Click **Detach Selected Cell** again.

You now have a real reusable tileset even though the Scene itself is only acting as a source/staging area.

Checkpoint

In METATILES you should have at least:

- **Ground Surface** — bottom half Solid,

- **Solid Block** — all four quadrants Solid.

The Scene's linked map can be empty; the **library definitions remain available**.

Workshop III — Build the actual multi-screen World

Step 8. Create your first World

Open **WORLD**.

Click **+ World**.

Then explicitly verify/set:

- **Name:** `My First World`
- **Tileset Scene:** `My First Room`
- **Width:** `2` screens
- **Height:** `1` screen

A World screen is **16×15 metatile cells**. Therefore this World is:

```
32 cells wide × 15 cells tall
512 px wide × 240 px tall
```

The World editor only shows one NES screen viewport at a time. Use the left/right View arrows or the minimap to move between screen 1 and screen 2.

If METATILE BRUSH is empty

Stop here and check **Tileset Scene**.

The selected scene must contain a Metatile Library. The WORLD sidebar should say something like:

> `My First Room · 2 metatiles available.`

If it says **0 metas**, return to METATILES and create the library first, or choose the correct Tileset Scene.

Step 9. Paint a floor across both screens

Use **WORLD TOOLS → Paint** or **Rect**.

A reliable beginner layout is:

- metatile row **12** = `Ground Surface`
- rows **13–14** = `Solid Block`

With rows numbered 0–14, **row 12 is the third row from the bottom**. The playable surface is in that row, with additional solid terrain below it. This layout is authored manually; no fixture is needed.

Screen 1

1. Choose **Ground Surface** in the Metatile Brush/Palette.
2. Paint row 12 across all 16 columns.
3. Choose **Solid Block**.
4. Paint rows 13 and 14 across all 16 columns.

Screen 2

1. Click the → View button or click the second screen in the minimap.
2. Repeat the same three terrain rows.

You should now have a continuous floor spanning two NES screens.

> Empty World cells are visually blank and collision-empty. You do not need to fill the sky with an "empty" metatile.

Step 10. Place the start Spawn

Still in WORLD:

1. Choose **WORLD TOOLS → Spawn**.
2. On screen 1, click approximately **cell X=3, Y=12**.
3. Switch back to **Select** and click the Spawn if you want to rename it, for example `Player Start`.

World Runtime uses the marker's cell to calculate the player's centered-feet position:

```
world pixel X = cell X × 16 + 8
world pixel Y = cell Y × 16 + 8
```

For `(3,12)`, choose the **fourth column and third row from the bottom** of screen 1. The starting feet are approximately `(56,200)` pixels in the World.

The Player body must fit inside the World and must not intersect Solid collision at the start marker.

Important distinction

The **Spawn marker** determines where World Runtime starts the Player.

The Player entity's X/Y in ENTITY STUDIO identifies the authored source entity; it is **not** the World starting position.

Workshop IV — Build the player from your own sprite CHR

Step 11. Draw one sprite tile

Open **CHR SHEET**.

1. Choose **Sprite Bank ($1000)**.
2. Select tile **$10**.
3. Draw a simple visible 8×8 character/icon.
4. Choose/edit a Sprite palette so it is visible.

Use at least one **nonzero sprite pixel value** in the artwork: sprite pixel index 0 is transparent. `$10` is decimal 16 if entered in a numeric Tile field. For the first successful build, one 8×8 piece is enough; larger poses can follow afterward.

Step 12. Turn the sprite tile into a metasprite pose

Open **METASPRITES**.

1. Click **+ New frame**.
2. Name it **Hero Stand**.
3. Confirm **Source scene = My First Room**.
4. Use **Sprite size = 8 × 8**.
5. Click **+ Piece**.
6. Set the piece:
   - Tile = `$10` / decimal `16`
   - X = `0`
   - Y = `0`
   - Palette = `Sprite palette 0` or the palette you used
7. Click **Set origin at feet**.

For a single 8×8 piece at `(0,0)`, Set origin at feet places the anchor at the horizontal center and bottom of the artwork: approximately `(4,8)`.

That cyan origin cross is important. World Runtime positions and facing are based on the reusable frame origin, not on the upper-left corner of the tile.

Checkpoint

You should see **Hero Stand** in the Metasprite Composer and no missing-source warning.

Workshop V — Create the required animation states

Step 13. Make `idle`

Open **ANIM**.

1. Click **+ Add Animation**.
2. Name: `Hero Idle`
3. State: `idle`
4. **Loop:** On
5. Select the first frame.
6. Set Duration to about `12` ticks/frames.
7. Set **Frame source = Metasprite**.
8. Set **Metasprite = Hero Stand**.

One animation frame is enough for the first build.

Step 14. Make `walk`

Create another animation:

- Name: `Hero Walk`
- State: `walk`
- Loop: **On**
- Duration: about `8`
- Frame source: **Metasprite**
- Metasprite: **Hero Stand**

For now it is okay for `walk` to reuse the exact same art as `idle`. We are proving the complete authoring chain first.

Later, create `Hero Step A` / `Hero Step B` metasprites and add multiple frames to this animation.

Step 15. Make `attack`

Create a third animation:

- Name: `Hero Attack`
- State: `attack`
- **Loop: Off**
- Duration: about `8`
- Frame source: **Metasprite**
- Metasprite: **Hero Stand**

This detail is mandatory:

> **World Runtime requires the Player's attack animation to be nonlooping.**

The retained World Runtime profile plays this animation when you press **X or S / NES B / touch B**, but it does not yet apply generic World target damage. **All three tutorial animations currently reuse Hero Stand**, so the attack state has no visibly different artwork yet. That is expected; later, give attack a distinct pose if you want to see the change.

Optional `jump`

You may create and bind a `jump` state. If you do not, World Runtime falls back to idle artwork while airborne.

Workshop VI — Create the Player entity and bind the animations

Step 16. Add a Player in ENTITY STUDIO

Open **ENTITY STUDIO**.

Under **PLACE AN ENTITY**:

1. Type = **Player**
2. Scene X = `48`
3. Scene Y = `200`
4. Click **Add at X / Y**.

Those Scene coordinates are reasonable source-authoring values, but remember: the World Spawn determines the runtime start position.

Step 17. Bind the required states

With the Player selected, under **STATES** create these bindings exactly:

State name	Animation
`idle`	Hero Idle
`walk`	Hero Walk
`attack`	Hero Attack

For each one:

1. Enter the lowercase State name.
2. Choose the matching Animation.
3. Click **Assign state**.

Then set:

- **Default state:** `idle`
- **Default facing:** `Right`

The state names matter. World Runtime looks specifically for:

```
idle
walk
attack
```

and optionally:

```
jump
```

If any required state is missing, the World build rejects instead of guessing.

Workshop VII — Connect everything in WORLD RUNTIME

Step 18. Enable World Runtime

Return to **WORLD** and find the **WORLD RUNTIME** section near the bottom of the sidebar.

Check:

> **Build this project as World Runtime**

Then explicitly choose:

- **Start world:** `My First World`
- **Start marker:** your `Player Start` / Spawn marker
- **Player source scene:** `My First Room`
- **Player:** the Player entity you created

NES Forge intentionally does **not** infer these selections from whichever object happens to be selected in another tab.

Step 19. Set movement and body values

Expand **Movement and collision body**.

For the tiny one-piece tutorial character, use:

Setting	Tutorial value
Move speed	2
Jump speed	9

Setting	Tutorial value
Gravity	1
Maximum fall	6
Body width	8
Body height	8

Set both body dimensions explicitly to 8. The existing defaults are 12×22 and do not match the tiny first character. A later larger character can use a larger movement body once its artwork and starting clearance are checked.

World Runtime body width must be even because Player X is the center of the feet.

The WORLD RUNTIME status should become green and report that the start/player references are valid. Full map/collision/resource validation happens during Build & Run.

Workshop VIII — Build and play your own World

Step 20. Build & Run

Click **Build & Run** in WORLD RUNTIME or the main toolbar.

NES Forge should compile the project as the **World** backend and load the generated mapper-0 ROM in the bundled emulator.

For a mobile play check, open **EMULATOR → Play view** and choose **Run** if paused. Use the on-screen D-pad and A/B buttons with separate fingers. **Fullscreen** requests native browser fullscreen; if unavailable, the expanded view stays inside the browser. **Exit to editor** returns to authoring without rebuilding or resetting the ROM. See the Mobile Play controls in the operator reference for controller setup and input-release behavior.

Run/Pause starts/stops emulator execution. The on-screen **Start** button sends NES Start to the game; in this workshop's generated World profile it restarts at the configured start marker. They are different operations.

Controls:

Key	Action
Left / Right / touch D-pad	Move
Z or A / NES A / touch A	Jump
X or S / NES B / touch B	Play attack animation
Up / touch D-pad Up	Use a linked Entrance/Exit
Enter / NES Start / touch Start	Restart at configured start marker

Walk to the right edge of screen 1.

When the Player crosses into the second World screen, the runtime should change the displayed NES screen and continue the same World-space movement/physics.

> **The current World profile uses complete 256×240 screen transitions, not smooth pixel scrolling.**

This first build is intentionally silent because Audio Runtime is still off. It also has no distinct walking/attack artwork until you add different poses. Use movement, jumping, screen changes and restart as the first checks. Evaluate the reported audio lag later with authored music enabled or a known sounding, independently shareable ROM.

Save and reopen checkpoint

1. Use **Exit to editor** if Play view is expanded.
2. Choose **Save Project As…** and save a native project JSON to a location you can find again. Verify the downloaded/saved file exists.
3. Use **Open Project…** to reopen that saved JSON.
4. Check that `My First World`, its tileset, selected Player and required animation bindings remain present, then choose **Build & Run** again.

Checkpoint: the reopened project still produces your moving/jumping Player and the two connected screens. Save the native project even if you also export a `.nes` file; this JSON is your editable workshop backup.

What you have built at this point

Without importing any prebuilt project, you have authored:

```
Your BG CHR
   ↓
Your Solid collision
   ↓
Your reusable 16×16 Metatiles
   ↓
Your 2-screen World
   ↓
Your Spawn

Your Sprite CHR
   ↓
Your Metasprite pose
   ↓
Your idle / walk / attack animations
   ↓
Your Player entity bindings

All of the above
   ↓
```

```
World Runtime
   ↓
Generated 6502 NES ROM
```

That is the complete from-scratch path.

Workshop IX — Extend it into a Scout-style linked World

You can extend your own two-screen World with a separate one-screen area and linked markers. Create both maps manually.

Step 21. Create World 2

In WORLD:

1. Click **+ World**.
2. Explicitly select **Tileset Scene = My First Room**.
3. Name it `Courtyard`.
4. Width = `1`.
5. Height = `1`.
6. Paint row 12 with **Ground Surface**.
7. Paint rows 13–14 with **Solid Block**.
8. Place a **Spawn** around cell `(4,12)`.
9. Rename it `Courtyard Spawn` if desired.

Your project now has two independent World maps using the same source tileset.

Step 22. Add an Exit from World 1 to World 2

Select `My First World` in the World dropdown.

1. Move the View to screen 2.
2. Choose **WORLD TOOLS → Exit**.
3. Place it somewhere reachable on the floor, for example around global cell `(25,12)`.
4. Choose **Select** and click the Exit.
5. Under **SELECTION / PROPERTIES**, set:
   - **Target World:** `Courtyard`
   - **Target Marker:** `Courtyard Spawn`

Both destination fields are required.

The destination must be a **Spawn** or **Entrance**.

Step 23. Optional return link

In `Courtyard`:

1. Place another **Exit** in a reachable floor cell.
2. Select it.
3. Set:
    - Target World = `My First World`
    - Target Marker = your original Player Start Spawn

Build & Run again.

Stand in the Exit cell and press a **new Up press**.

The runtime changes to the target World and positions the Player at the destination marker.

Holding Up through a reciprocal transition does not immediately bounce you back; the runtime requires a new press.

Workshop X — Rooms and Cameras: when to use them

You do **not** need Rooms or Camera Regions for the first playable World. If no Camera Region matches the Player, World Runtime simply displays the Player's current World screen.

Once basic traversal works, add them deliberately.

Rooms / Chunks

Rooms describe named World regions. They do not create invisible walls and do not instantiate Scene entities.

Runtime requirements for Room rectangles:

- X and width are aligned to **16 metatile cells** (whole NES screens horizontally),
- Y and height are aligned to **15 metatile cells** (whole NES screens vertically),
- rectangles stay inside the World,
- Room rectangles may not overlap other Rooms.

For a simple 2×1 World, you can use **+ Current Screen** once on screen 1 and once on screen 2.

Camera Regions

Camera Regions are also whole-screen aligned and may not overlap other Camera Regions.

Modes:

Mode	Behavior
`follow`	Display follows Player screen on both axes.

Mode	Behavior
`horizontal`	Follows Player screen column; holds the region's first row.
`vertical`	Holds first column; follows Player screen row.
`locked`	Always shows region's first/top-left screen.

Cameras choose the displayed screen. They do **not** prevent movement.

A player can therefore move off the displayed screen when using a locked or axis-limited Camera Region; the sprite is clipped rather than wrapped.

Workshop XI — Turn the tiny player into a Scout-style player

Once the one-piece character works, upgrade the art without changing the World pipeline.

Step 24. Build a larger metasprite

In METASPRITES, a Scout-like standing pose can be made from six 8×8 pieces arranged roughly as:

```
[0][1]
[2][3]
[4][5]
```

That produces a 16×24-pixel character.

A convenient source coordinate layout is:

```
X = 0 / 8
Y = 0 / 8 / 16
```

Then use **Set origin at feet**. For a 16×24 pose beginning at `(0,0)`, the origin becomes approximately `(8,24)`.

This is the same basic anchor convention used by the Scout reference asset.

Step 25. Make distinct poses

Create or duplicate frames such as:

- Hero Idle
- Hero Step A
- Hero Step B
- Hero Attack

Then change ANIM:

- `idle` → one or more Idle frames,
- `walk` → alternate Step A / Step B,
- `attack` → one or more attack frames, Loop off,
- optional `jump` → airborne pose.

You can also author per-frame contact boxes and events in ANIM. With Audio Runtime enabled, supported `sound` events execute through the retained animation paths. Contact boxes and other events do not automatically enable richer generalized combat or scripting.

Workshop XII — Where the other tabs fit

ATTR MAP

Use ATTR MAP / Scene palette editing if your source 16×16 sample must use a specific BG palette row. A Metatile stores one NES palette row along with its four tile IDs.

SPRITES

The SPRITES tab edits raw Scene OAM. For World Runtime Player authoring, you can skip it and compose frames directly in METASPRITES.

Alternatively, build a pose in SPRITES and use **METASPRITES → Capture scene OAM** to turn the visible OAM pieces into a reusable frame.

AUDIO

The included candidate can compile tracker music and SFX into generated ROMs. Enable **Compile Audio Runtime** explicitly. Follow the Audio workshop after the terrain/Player loop works.

CODE

World Runtime generates its own code. If custom assembly exists in CODE, the WORLD RUNTIME status rejects the build and tells you to save/clear the custom assembly first.

COLLISION

The COLLISION tab is useful when creating metatiles from Scene samples because METATILES captures the source tile properties into four 8×8 collision quadrants.

After a metatile exists, you can also edit its four collision quadrants directly in METATILES.

Workshop XIII — Common from-scratch failures

"Tileset has no metatiles" / empty World brush

Cause: The World points to a Scene with no Metatile Library.

Fix:

1. Open METATILES on the intended Tileset Scene.
2. Create definitions with **+ From Selected Cell** or **Analyze Scene → Library**.
3. Return to WORLD.
4. Explicitly select the correct **Tileset Scene**.

My new World contains weird blocks I used only as metatile samples

Cause: + World seeds its first screen from the source Scene's linked `metaMap`.

Fix: Before creating the World, use **Detach Selected Cell** on temporary source samples, or erase those cells in WORLD after creation.

The Metatile Library itself is not deleted by detaching a Scene cell.

"The player needs an `idle` / `walk` / `attack` animation binding"

In ENTITY STUDIO, bind these exact lowercase state names:

```
idle
walk
attack
```

`jump` is optional.

"The player attack animation must be nonlooping"

Open ANIM → Hero Attack and turn **Loop** off.

Player is invisible

Check:

1. The artwork is in **Sprite Bank**, not BG Bank.
2. The metasprite piece uses the correct Sprite CHR tile.
3. The piece uses a visible Sprite palette.
4. The animation frame source is **Metasprite**.

5. ENTITY STUDIO binds that animation to the required state.

Player appears above/below where I expect

Check the Metasprite **origin** and World Runtime **body height**.

The Player's World position represents the **center of the feet**, not the top-left corner of the art.

Use **Set origin at feet** in METASPRITES as a reliable starting point.

Starting spawn intersects solid collision

Move the Spawn higher or change the collision layout.

For the terrain pattern in this tutorial:

```
row 12 = Ground Surface (top empty / bottom solid)
row 13 = Solid Block
row 14 = Solid Block
```

placing the Spawn at approximately `Y=12` is appropriate.

The compiler does not silently move an invalid Spawn to a nearby safe position; it rejects the build.

I painted collision in SCENE but WORLD behaves differently

World Runtime executes the collision stored in the **Metatile definitions used by WORLD**.

SCENE tile properties help create those collision quadrants when you capture a metatile, but WORLD is not executing the SCENE nametable as the level.

Build complains about custom assembly

Clear CODE. World Runtime generates its own engine code.

It changes screens instead of smooth scrolling

Expected in the current World traversal profile.

World Runtime tracks World-space movement and changes the displayed camera by complete NES screens. Smooth scrolling is not implemented yet.

My Enemy/NPC entity does nothing in World Runtime

Expected in the current World traversal profile.

The retained entity workflow executes the selected bound Player. For additional supported actors, use **Gameplay Core**, enable it explicitly, and choose valid reachable World/Room placements. Legacy Scene enemies are not implicitly converted into canonical actors.

Workshop XIV — Save and reopen your work

Save the editable source

Use **Save Project As…** or **Export…** for a complete native JSON/ZIP backup, and browser **Save** as an additional convenience. Do not substitute a single-room ROM for a native Gameplay Core backup.

Export the ROM

Use **Build .NES ROM** when you want the generated cartridge file without immediately running it.

Reopen a Forge World ROM

Use **Open Forge ROM**, not append-style Import ROM, for the new World Runtime layout.

A WG17 World ROM carries a checked compressed authoring-source record, allowing NES Forge to reconstruct the editable project when reopened.

Run Original ROM plays the retained opened/imported ROM bytes independently of your current edits.

Workshop XV — The entire blank-project recipe on one page

Use this as the quick checklist after you have completed the tutorial once.

1. **New Project**.
2. **CHR SHEET / BG Bank:** draw terrain tiles.
3. **COLLISION:** mark terrain source tiles Empty/Solid.
4. **SCENE:** arrange temporary 2×2 BG tile samples.
5. **METATILES:** `+ From Selected Cell`; name definitions; confirm collision quadrants; detach temporary sample cells if you want a blank World seed.
6. **WORLD:** `+ World`; choose the Tileset Scene; choose dimensions; paint terrain.
7. **WORLD:** place at least one **Spawn** or **Entrance** for the start.
8. **CHR SHEET / Sprite Bank:** draw Player tiles.
9. **METASPRITES:** make reusable pose(s); **Set origin at feet**.
10. **ANIM:** create `idle`, `walk`, and **nonlooping** `attack`; assign metasprite frames. Optional `jump`.
11. **ENTITY STUDIO:** create a **Player**; bind `idle`, `walk`, `attack`; choose default state/facing.

12. **WORLD → WORLD RUNTIME:** Enable; choose Start World, Start Marker, Player source Scene, Player; set movement/body dimensions.
13. Leave **CODE** blank.
14. **Build & Run**.
15. After the first build works, add more screens, a second World, Exit/Entrance links, Rooms, Camera Regions, larger metasprites, and richer animation.

Gameplay Core workshop

This chapter builds on the World you made in the blank-project workshop. It does not replace the World Player setup. The included candidate's **GAMEPLAY CORE · TYPED TABLES** panel adds new canonical records while retaining the existing Player executor. [S1, S4]

Find the tables and choose placement first

Open the gameplay panel and expand **GAMEPLAY CORE · TYPED TABLES**. Check **Enable canonical Gameplay Core**. Before using **Add template** or **New Actor Instance**, choose the placement kind and its owner in the controls at the top of the tables:

Kind	Choose	Intended location
`scene`	A Scene	Retained single-room placement; not a shortcut for placing the actor throughout a World.
`world`	A World	World-owned placement at authored coordinates.
`room`	A World and one of its authored Rooms	Placement belonging to that Room and usable with its Room-scoped bindings.

For the first exercise choose **world → My First World**. A World actor's coordinates are authored World coordinates, not the coordinate of the currently selected screen in the editor. For example, X greater than 255 is on a later horizontal screen. Consult its placement row rather than assuming a newly added template appears under the mouse.

Expected result: the panel reports the number of definitions, instances, behaviors, and profile variables. Enabled here means the system is requested; only the executable build determines whether every configured operation is supported.

Understand definitions, instances and behavior selection

An **Actor Definition** is a reusable archetype. Its component/default changes affect instances referencing it. An **Actor Instance** is an authored placement with its own position, facing, parameter overrides and persistence bindings. A **Runtime Actor** is transient game state; its slots/timers are not save-game data. A **Persistent Variable** stores one explicitly declared Room/World value. [S1]

The table's definition selection determines which **Typed Components / Parameters** you are editing. The **Canonical State Table** has its own Behavior selector. Check both before editing: a newly created definition can reference an existing behavior. Creating a new definition does not guarantee a private copy of that behavior. Use **New Behavior** and assign it in the definition row when you need an independent behavior.

Likewise, **New Actor Instance** initially references an available definition. Change its Definition selector explicitly to the one you intend to place.

Add one template at a time

The five available recipe families are Sideview Player, Ground Patrol Enemy, Stationary Contact Hazard, Collectible Pickup, and Switch + Door. Recipes create ordinary editable records; the template name is not a separate runtime script. [S1, S4]

Begin with **Collectible Pickup**. Select the recipe and click **Add template**. Inspect the newly created Actor Definition, Behavior, Actor Instance and Persistent Variable. Move the instance into reachable empty space above your floor and select the proper World/Room owner. Check its Render component's source Scene, sprite tile and palette; do not assume the recipe has drawn custom art for you.

The recipe's default Y is 208, which is not a universal placement recommendation. In the earlier half-solid ground workshop, the ground begins at pixel Y=200. Move generic artwork above that floor according to its displayed dimensions rather than copying the Player's feet coordinate into an unrelated top-left placement field.

Build & Run and walk into the pickup. **Checkpoint:** the instance's supported collection behavior changes its bound variable and deactivates it. Test a supported leave/re-enter path to verify its scoped state persists during the session. Rebuilding or resetting the runtime starts a fresh session; it is not a durable game save.

Next add **Ground Patrol Enemy**, select its instance and place it on a visible area with reasonable motion bounds. Inspect its `moveWithinBounds` action rather than assuming the name means pathfinding, terrain-aware navigation, or generalized physics. Contact damage is owned by Behavior `contactDamage` actions. Build and check movement and contact separately.

For **Stationary Contact Hazard**, inspect the scoped enable variable and the state synchronization action before changing defaults. Keep health/damage values within the typed field bounds. Add one actor, test it, then add the next; this makes a wrong placement or binding much easier to diagnose.

Player compatibility warning

The **Sideview Player** template is a compatibility binding. It does not create a second independent generic controller or remove the need for your World Runtime Player source and animation bindings. Movement, collision and Player animation still use the retained executor. Do not interpret an Input component on an arbitrary new definition as a complete new playable-character runtime. [S1]

Rendering warning

The generic actor's Render component uses its supported source art fields. The retained Player's multi-piece, animated Metasprite path is not automatically assigned to every canonical actor. Configure only the

visual bindings exposed for the selected actor/profile. A Metasprite in the library is not by itself a placed or animated enemy.

Use Switch + Door as the alpha state example

Add **Switch + Door** after the pickup is working. It creates linked records; inspect both instances and their shared persistent variable. Give them distinct visible art and separated positions. Build and trigger the switch according to its authored transition conditions.

Expected result: the shared variable changes and the Door's active/visible state changes. **Do not expect a closed Door to block movement.** The owner explicitly deferred physical blocking. In this profile `syncActiveFromPersistent` can deactivate an active actor, but inactive actors do not keep evaluating; reversing the variable does not reactivate that actor until reconstruction. This is a one-way alpha state/persistence demonstration, not a finished reversible gate or door-collision system. [S1]

Changing the recipe's name, art or shared flag does not enable later collision capabilities. Retain native project backups before experimenting with state transitions.

Author a timed behavior without a recipe

This exercise shows how to build a small behavior using the ordinary controls. It is a source-derived walkthrough for this rebuilt edition, not a newly executed runtime test.

1. In **Canonical State Table**, choose **New Behavior**. Rename the behavior `Timed Token`.
2. Rename its first state `Waiting`. Leave that state selected as the Initial state.
3. Click **Add state** and name the second state `Gone`.
4. Under **Waiting → onEnter**, choose **Add action**, select `setTimer`, and set `ticks` to **120**. Keep this action out of `onTick`; repeatedly resetting the timer would defeat the countdown.
5. Under **Gone → onEnter**, add the `despawn` action.
6. Click **Add transition**. Set From to `Waiting`, To to `Gone`, and Priority to **0**.
7. The new transition begins with an `always` condition. Replace it with `timerDone`. Leaving `always` would make the transition immediate rather than timer-controlled.
8. Click **New Actor Definition**, name it `Timed Token`, and assign the Behavior selector to your new `Timed Token` behavior. Check that its Behavior component is enabled.
9. In **Typed Components / Parameters**, add a **Render** component. Choose your source Scene and a visible sprite tile/palette using the typed controls.
10. Choose the desired World placement at the top of the panel. Click **New Actor Instance**, then set its Definition selector to `Timed Token` and choose a visible, reachable position.
11. Build & Run. The intended result is a visible token that despawns when its timer completes. At a nominal 60 ticks per second, 120 ticks is about two seconds. Real elapsed time follows emulator execution speed.

What this proves conceptually: a template is optional. States, transitions, typed conditions and actions can describe a supported behavior directly. It does not authorize arbitrary scripting or imply every canonical dropdown operation can execute on mapper 0.

Removal order

A state may be referenced by the Initial state selector and transitions. Before removing it, retarget/remove those references. Before removing a persistent variable, remove or change its actions and instance bindings. Before removing a definition, handle its placed instances. Validation errors are preferable to silently leaving broken executable references.

Create a persistent variable and bind it intentionally

Use **New persistent variable** under **Room / World Persistent Variables**. Choose a Boolean, bounded unsigned integer, or Enum; set its name, owner, type and default value. For a Room variable, choose the authored Room in the correct World. The current single-room backend can use its Scene as the logical Room owner; that is not a new general Scene persistence scope. [S4]

Select the Actor Instance and click **Add binding**. Choose the compatible declared variable and its purpose. Actor Instance bindings are authoritative. The component table marks persistence mirrors as mirrors rather than providing a second independent routing source. Conditions/actions use explicit variable IDs; a similar display name in a different World is not the same variable.

For a World-level switch affecting another Room, both actors must deliberately refer to the same World variable. For a room-local collectible, use that Room's variable and Room placement. Cross-owner and incompatible references are build errors; do not solve them by renaming IDs until validation happens to pass.

Session semantics: normal supported Room/World reconstruction retains declared values. Runtime Actor timers, velocity and working state reconstruct. Runtime reset/power-cycle/newly loaded build returns to authored defaults. There is no SRAM, password, save-slot UI or checkpoint system in 1.9.0. [S1]

Work within the current executable vocabulary

The canonical authoring vocabulary is broader than the mapper-0 executable subset. Keep this distinction visible while learning. [S4]

Executable conditions	Executable actions
`always`	`persistentSet`
`inputHeld`	`despawn`
`inputEdge`	`setTimer`
`timerDone`	`moveWithinBounds`
`overlapPlayer`	`contactDamage`
`persistentCompare`	`syncActiveFromPersistent`

Every operation requires its typed operands. `setTimer` needs `ticks`; a persistence operation needs a valid variable/value; motion bounds must be consistent. Operations such as `setFacing`, `setVelocity`, `accelerate`, `selectAnimation` or `emitTrigger` may exist canonically but are not permission to execute them in the current bounded profile. Read the actual profile error and either use a supported operation or keep the work as authoring-only.

Disabling a **Behavior** component keeps its records and may keep the actor placed/rendered, but the corrected profile performs no behavior lifecycle work: no entry/tick/exit actions, transitions, timers or behavior-driven damage/persistent writes. Do not confuse disabled Behavior with despawning the actor.

The runtime plan limit is **12 executable Actor Instances total**, including the compatibility Player, and **64 one-byte persistent values**. A reachable World added later can increase the same total. Unreachable records can remain in the project, but the compiler reports exclusions; it must not silently discard reachable actors to fit capacity. [S1]

Audio workshop

Audio preview and cartridge audio are separate choices. The AUDIO tracker can preview notes in the browser, but the generated ROM plays authored music only when **Compile Audio Runtime** is enabled. MIDI and MusicXML feed this same tracker model rather than a separate player. [S3]

Make a small melody yourself

1. Open **AUDIO** and click **+ Add Instrument**. Select the instrument and give it a useful name.
2. Set a pulse duty and inspect the Volume and Arpeggio envelopes. A nonlooping volume envelope ends in silence; that can be desirable for plucked notes. Keep the default envelope initially rather than changing every setting at once.
3. Select a cell in **Pulse 1** and enter notes with the displayed tracker piano keys: Z–M for the lower range and Q–U for the higher range. Arrow keys navigate; Delete clears a note, while Backspace creates a cut.
4. Place a few separated notes, then use the transport **Play** and **Stop**. Confirm the selected pattern/order is the one containing the notes.
5. Set Tempo and Speed deliberately. Pattern Order selects which pattern each channel plays; adding a pattern does not by itself make it part of the song.
6. In **NES Runtime**, check **Compile Audio Runtime** and retain **Autoplay tracker order as music** for background music.
7. Keep CODE empty for generated World gameplay. Build & Run, then listen in EMULATOR with its Audio control enabled.

Checkpoint: hearing the tracker preview is not the completion criterion. The compiled ROM should play music while the game runs. Audible browser output still depends on the browser allowing audio after user interaction and on your device/output settings.

Connect a short SFX to an animation

Use a separate tracker pattern for a short effect so it does not unintentionally replace your background melody. Add an SFX definition in the Audio Runtime panel. Set its Name, hardware Channel, Pattern, Start row and End row. The row range is inclusive. Record its stable SFX ID.

In **ANIM**, select a retained Player animation such as `Hero Attack`. Select the frame that should produce sound, add an event of type **sound**, and set its value to the SFX ID (a unique SFX name is also accepted by the documented resolver). Enable Audio Runtime and rebuild.

Press the attack input and listen for the frame-entry sound. The event fires once when the runtime enters the frame, not once every rendered frame while it stays selected. Only one SFX plays at a time; a request arriving while an SFX is active is ignored. Its selected channel returns to music after the effect finishes. A scene viewer has no animation executor, so it only autoplays music. [S3]

Import MIDI or MusicXML

Save a native project checkpoint first. Use the import controls in AUDIO. After import, inspect the generated instruments, patterns, and Pattern Order before building. Import appends normal patterns/instruments and changes the music order while retaining existing SFX pattern references; it is one undoable operation and does not enable Audio Runtime automatically. [S3]

Format	Supported input and boundaries
MIDI	Standard MIDI format 0 or 1, PPQN timing, pitch, velocity, initial tempo, track/program information. MIDI channel 10 maps to Noise. Format 2 and SMPTE timing reject.
MusicXML	Uncompressed `score-partwise` XML, divisions, notes/rests/chords, durations, backup/forward timing, initial tempo. Compressed `.mxl` is unsupported.
Arrangement	Sixteenth-note row quantization, three simultaneous pitched voices and one Noise voice. Excess polyphony/overlapping percussion rejects instead of silently deleting notes.
Tempo	Later tempo changes flatten to the initial tempo with a warning.

Alpha.11 update: MIDI and MusicXML score export are now available through **AUDIO → Export Score Data**. The historical import description above is not a claim of complete interchange fidelity. DPCM, executable tracker effects, tablature transcription and image/PDF score recognition remain outside the supported workflow described here; native project Save As is the full authoring backup. See the alpha.11 updates at the top of this manual.

PART II - COMPLETE OPERATOR / CONTROL REFERENCE

Operator reference scope

Control-by-control reference · 1.9.0 Gameplay Core — Alpha / mobile-play-1 · September 30, 2026

Application source package: `NES_Forge_1.9.0_Alpha_Mobile_Play_Candidate.zip`
Source package SHA-256: `aa734c7e734adea8c4821ac57ec2297d105cb1a5e9813635a0a52ad9f2f77088`
Application SHA-256: `e7c75ccd43007c46b5e0336105f6551f4b6183cc39730802cd1fba226eb7fe12`


Historical identity: These hashes identify the application/source in the original September 30 kit, which is retained separately. This kit's root `NES_Forge.html` is alpha.11; see the current identity above. The old application/source ZIP is not duplicated in this kit.

> **Historical September 2026 status:** The original 1.9.0 package was a functional alpha candidate. Its September 28 automated run passed 702/702 checks in 28 suites; this is not evidence for the current alpha.11 application. On September 30 the owner reported that touchscreen controls work on mobile, and also reported audio/video lag. Physical controllers remain untested; the device, browser/version, ROM and performance measurements for that report have not been recorded. This documentation update neither fixes performance nor establishes broad device compatibility.

How to read the tables

- **Project data** means the control changes saved authoring data.
- **Editor view/selection** changes what you see or what will be edited, without itself changing project semantics.
- **Build output** creates or changes an external ROM/package.
- **Runtime** means the compiled game/emulator behavior is affected when the selected runtime supports that capability.
- A control can be authorable but still be unsupported by the current generated runtime profile; in that case executable builds should reject it rather than silently ignore it.

Global UI map



Historical toolbar illustration from the corrected Gameplay Core reference. It locates the existing editor controls; Mobile Play controls added afterward are documented below.

#	Area
1	Grid / Attr / Meta overlays
2	Global canvas Zoom
3	Upload Image
4	Load .zip Pack
5	Export project ZIP
6	Build .NES ROM
7	Build & Run
8	Import ROM
9	Clean Cache
10	Active Scene selector
11	Scene add / duplicate / delete / rename
12	Undo / Redo / Copy
13	Paste
14	New Project
15	Project identity + Save / Load / Save Project As / Open Project
16	Open Forge ROM
17	Gameplay shortcut
18	SCENE sidebar / Gameplay details

The mental model in one page

```
BACKGROUND: CHR SHEET -> METATILES -> WORLD -> World Runtime -> ROM
CHARACTER:  SPRITE CHR -> METASPRITES -> ANIM -> ENTITY STUDIO -> retained Player runtime
GAMEPLAY:   Actor Definition -> Actor Instance -> Behavior table -> Gameplay Core compiler ->
Runtime Actor
AUDIO:      Tracker / MIDI / MusicXML -> NES Forge Audio -> AudioCompiler -> APU runtime
DEBUG:      Build & Run -> EMULATOR -> Capture / DISASM / diagnostics
```

Key separation rules

1. **Scene is not World.** A Scene owns source graphics/palettes/legacy entity data; a World places metatiles across many screens.
2. **Legacy Entity is not Gameplay Core Actor Instance.** They coexist in 1.9.0 for compatibility.
3. **Metasprite is not Animation.** Metasprite is one composed pose; Animation sequences poses over time.

4. **Entity Studio state is not Gameplay Core behavior state.** Entity Studio binds visual animation states to legacy Scene entities.
5. **Build & Run is not Run Original.** Build & Run compiles current edits; Run Original runs preserved imported ROM bytes.
6. **Authorable is not necessarily executable in every profile.** The current Gameplay Core NROM profile rejects unsupported operations.
7. **ROM is not your only source backup.** Save JSON/ZIP projects.

Complete control reference

GLOBAL TOOLBAR

The global toolbar is always about context, importing, building, Scene selection, and editor history. Build controls act on the current project; they do not implicitly save it first.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Grid	checkbox	Shows/hides the editor grid overlay on applicable canvas views.	Editor view only	Scene/CHR/other canvas views	Does not change saved tile data.
Attr	checkbox	Shows/hides attribute/palette-zone overlay where applicable.	Editor view only	SCENE	Overlay only; palette data is edited elsewhere.
Meta	checkbox	Shows/hides metatile-oriented overlay where applicable.	Editor view only	SCENE/METATILES	Does not create metatile definitions.
Zoom 2x / 3x / 4x	select	Changes canvas rendering scale for applicable editor views.	Editor view only	Most canvas tabs	World and Metasprite Composer have their own zoom controls.
Upload Image	button	Imports an image, resizes/quantizes it to a 256x240 NES scene, and adds it as a new Scene.	Project data	SCENE, CHR, palettes	Conversion is constrained by NES tile/palette limits; imported image is not automatically a World.
Load .zip Pack	button	Loads a NES Forge ZIP. If project.json exists, restores the project; otherwise imports supported binary asset-pack files.	Project data	Project/CHR/scenes/assets	Do not confuse with Open Project JSON or Import ROM.
Export ...	button	Creates a portable .nesforge.zip package containing project.json and binary assets.	External file	All domains	Primary portable ZIP backup/export; not the same as building a ROM.
Build .NES ROM	button	Compiles the current edited project using the selected runtime/build mode and Save As flow.	Build output	CODE, WORLD Runtime, Gameplay, Audio	A successful build only includes capabilities supported by the selected runtime profile.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Build & Run	button	Builds the current edited project, loads the newly built ROM into the bundled emulator, and runs it.	Build + runtime	EMULATOR	Never silently runs an old imported ROM.
Import ROM	button	Imports/preserves an existing .nes ROM and exposes capture/extraction workflows.	Project + imported original	EMULATOR, CHR, Capture	Import does not imply full editable source recovery.
Clean Cache	button	Clears recovery data and temporary audio/runtime cache and stops transient playback.	Browser recovery/temp state	Autosave recovery, Audio, Emulator	Saved IndexedDB projects and the open workspace are preserved.
Scene selector	select	Switches the active authoring Scene.	Editor selection	SCENE, CHR source, ENTITY STUDIO	Changing active Scene does not change the configured World Runtime start World/player automatically.
+ Scene	button	Creates a new Scene.	Project data	SCENE	A new Scene does not automatically contain metatiles or become a World.
Duplicate Scene	button	Creates an independent copy of the active Scene.	Project data	SCENE/assets	Useful before destructive experimentation.
Delete Scene	button	Deletes the active Scene after validation/confirmation.	Project data	World/asset references	Referenced assets may make deletion invalid or create missing-reference errors.
Rename Scene	button	Renames the active Scene.	Project data	Scene selectors throughout app	Name is presentation; stable IDs carry references.
Undo	button / Ctrl+Z	Restores the previous editor snapshot.	Project/editor history	Most authoring domains	Some browser/file actions are outside undo history.
Redo	button / Ctrl+Shift+Z	Reapplies an undone snapshot when available.	Project/editor history	Most authoring domains	May be shown on later UI layer even if base shell only contains Undo.
Copy	button / Ctrl+C	Copies the currently selected tile in tile-oriented contexts.	Clipboard inside app	CHR/SCENE	Not a general project-object copy operation.
Paste	button / Ctrl+V	Pastes the copied tile into the selected tile slot/context.	Project data	CHR/SCENE	Disabled until an internal tile copy exists.

PROJECT BAR

Project lifecycle controls are deliberately separate from ROM import/build controls. Treat portable JSON/ZIP as your editable source backup.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
New Project	button	Replaces the workspace with a blank project using the normal authoring tools.	Project lifecycle	All tabs	Undoable in the current workflow; does not load a hidden starter game.
Project name	status	Shows the current project identity/name.	Editor status	Save/Load	Project name is not a ROM title field.
Save	button	Saves the complete project to browser IndexedDB.	Browser storage	Load	Browser-local storage is not a portable backup.
Load	button	Opens the browser-saved project list and restores a selected IndexedDB project.	Browser storage -> project	Save	Different browser/profile may not have the same saves.
Save Project As...	button	Writes a complete portable project JSON through native Save As or explicit browser fallback.	External file	Open Project	Best portable editable backup; cancellation does not silently download.
Open Project	button	Loads a portable NES Forge project JSON.	Project lifecycle	Save Project As	Schema validation occurs before replacement.
Open Forge ROM	button	Opens a supported NES Forge-generated ROM as an editable project when source envelope/metadata supports it.	Project lifecycle	World WG17 / generated ROM formats	World ROM source recovery is more complete than current single-room source recovery.
Gameplay	button	Switches to SCENE and opens the Gameplay details containing retained single-room configuration and Gameplay Core tables.	Editor navigation	SCENE, GAMEPLAY CORE	Gameplay Core is a SCENE details panel, not a top-level tab.
Recovery: Restore	banner button	Restores a discovered autosave/recovery snapshot.	Project lifecycle	Autosave	Autosave stays held until Restore or Dismiss is chosen.
Recovery: Dismiss	banner button	Discards/ignores the pending recovery snapshot and resumes normal autosave behavior.	Browser recovery	Autosave	Use deliberately if current workspace should win.
Load Project modal Close	button	Closes the browser project list without loading a project.	Editor view	Load	No data change.
Drag-and-drop overlay	drop target	Accepts images, .zip packs, .nes ROMs, and .json projects and routes them to the matching importer.	Depends on file type	Global imports	Use dedicated buttons when you want the operation to be unambiguous.
Tab context menu: Open in new tab	context command	Opens the selected editor view in another browser tab.	Editor view	Cross-tab sync	Middle-click is the shortcut.
Tab context menu: Open all views in tabs	context command	Opens the supported editor views in separate tabs.	Editor view	Cross-tab sync	Browser popup policy may limit this.
Tab context menu: Detach as popup	context command	Opens a selected view in a dedicated popup window.	Editor view	Cross-tab sync	Popup blockers may apply.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Sync dot	status	Shows whether linked NES Forge tabs are connected for live editor-state synchronization.	Editor status	Detached/multi-tab views	Not network multiplayer; browser-local editor synchronization.
Bottom status bar	status fields	Shows issue status, selected Tile, usage, Palette, Position, Zone, Undo count, clipboard, unique/free tile counts, and metatile status.	Editor diagnostics	Most tabs	Values are context-dependent.

SCENE

SCENE is the active Scene authoring workspace: raw 8x8 background painting, palettes/attributes, legacy Scene entities, camera metadata, and the host for Gameplay configuration. It is not the same thing as WORLD.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Main scene canvas	canvas	Paints the active Scene background in 8x8 tiles; drag paints continuously; right-click eyedrops tile and palette.	Project data + editor	CHR, palettes, metatiles	Scene is a source/room asset; it is not automatically a multi-screen World.
Scene browser	list	Selects scenes and shows scene thumbnails/status.	Editor selection	Global Scene selector	Selection does not alter saved runtime configuration references.
Metatile Brush selector	select	Chooses a scene-local 16x16 metatile definition for Scene painting.	Editor selection	METATILES	Empty until the active Scene owns a Metatile Library.
Enable 16x16 Brush	button/toggle	Switches Scene painting from raw 8x8 tiles to complete linked metatiles.	Editor mode	METATILES	Raw edits to a linked cell can detach that cell if it no longer matches.
Selected Tile preview	preview/status	Shows selected BG tile and usage count.	Editor status	CHR SHEET	Selection is used by raw Scene painting.
Palette row labels P0-P3	selector	Selects active background palette row.	Editor selection	Scene paint/CHR preview	Palette row is part of attribute data.
Palette swatches	selector	Selects one of four pixel colors within the active palette.	Editor selection	CHR pixel editor	Color 0 participates in NES universal-background behavior.
Palette edit pencil	button	Opens NES palette color picker for the selected palette entry.	Project palette data	Scene, CHR, metatiles	Changes every use of that palette entry in the owning Scene context.
Live Stats	status	Shows unique tiles, free slots, metatiles, 1x/2x tile counts, reuse ratio.	Diagnostics	Build capacity planning	Informational, not a compiler guarantee.
ATTR Editor cells	grid	Cycles palette assignment 0->1->2->3 for attribute quadrants.	Project attribute data	ATTR MAP, rendering	Editing attributes can detach linked metatile cells whose palette no longer matches.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Scene Type: Side-View	select option	Marks Scene as side-view authoring metadata.	Project data	Gameplay/runtime validation	Used by retained platformer/World assumptions where applicable.
Scene Type: Top-Down	select option	Marks Scene as top-down authoring metadata.	Project data	Future/runtime metadata	Current World Gameplay profile is not a universal top-down engine.
Scene Type: Static Screen	select option	Marks Scene as a static-screen type.	Project data	Viewer/metadata	Does not automatically disable all camera metadata.
Scroll: None	select option	Stores no-scroll scene intent.	Project data	Single-room validation	Single-room platformer requires no scrolling.
Scroll: Horizontal / Vertical / Both	select options	Stores scene scrolling intent.	Project data	Metadata/future runtime profiles	Current 1.9 World Runtime uses screen transitions, not smooth scrolling.
BG Color 0-63	number	Sets Scene background NES palette index.	Project palette/runtime data	Scene render/build	Must be valid NES palette index.
Gravity: None / Down / Heavy / Up	select	Stores legacy Scene gravity metadata.	Project data	Legacy/runtime metadata	Gameplay Core Physics is not simply this Scene dropdown.
Entity placement toolbar	buttons	Chooses a legacy Scene entity/object type, then places it on the Scene canvas.	Project legacy entity data	ENTITY STUDIO, retained Player path	Legacy Scene entities and Gameplay Core Actor Instances are different models.
Placed Entities list	list	Selects existing legacy Scene entities.	Editor selection	Entity Properties / ENTITY STUDIO	Does not list generic Gameplay Core Actor Instances.
Entity Properties	form	Edits type-specific legacy entity values and position.	Project legacy entity data	ENTITY STUDIO / retained runtimes	Semantics vary by entity type.
Delete Entity	button	Deletes selected legacy Scene entity.	Project data	Entity bindings/runtime refs	Can invalidate configured Player/Target references.
Camera/View Show	checkbox	Shows/hides authored view/camera bounds on the Scene canvas.	Editor view	View W/H/Borders	Does not alter World camera regions.
View W / H	numbers	Sets authored Scene viewport width/height metadata.	Project data	Single-room/camera metadata	World Runtime uses its own screen/camera model.
H Border / V Border	numbers	Sets authored camera border margins.	Project data	Scene camera metadata	Not the same as World Camera Region mode.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Scene Links list	list	Shows legacy Scene links created by Door/Exit entities.	Project data	Legacy viewer/scene navigation metadata	World Entrances/Exits are separate and live in WORLD.
Gameplay disclosure	details	Opens retained single-room configuration and the 1.9 Gameplay Core authoring tables.	Editor navigation	Single-room + GAMEPLAY CORE	World Runtime, when enabled, supersedes the saved viewer/single-room mode.

SCENE cross-tab effects

Change in SCENE	Where it appears next
Raw BG tile paint	SCENE, ATTR/META analyses, viewer/custom builds; WORLD only if you rebuild/use metatile definitions rather than assuming raw Scene paint changes an existing World map
Palette/ATTR edit	SCENE render, CHR contextual appearance, metatile matching/linked-cell integrity
Legacy Player entity	ENTITY STUDIO and retained Player selectors in single-room/World Runtime
Gameplay details	Retained single-room config and Gameplay Core compiler inputs
Camera/View metadata	Scene viewer/single-room metadata; not the same as WORLD Camera Regions

SCENE > GAMEPLAY (RETAINED SINGLE-ROOM)

These are the retained historical viewer/single-room settings. World Runtime disables them when enabled. Gameplay Core tables live in the same SCENE Gameplay details but are a separate canonical actor model.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
ROM mode	select	Chooses Scene viewer/custom assembly or Single-room platformer for the retained build path.	Project build config	CODE, Build & Run	World Runtime overrides these controls while enabled.
Playable room	select	Chooses the Scene used by the single-room platformer.	Project build config	Legacy entities/art	Must satisfy sideview/no-scroll/fixed-view requirements.
Player	select	Chooses a legacy Player entity in the playable room.	Project build config	ENTITY STUDIO animation binding	Retained Player executor is not generic Gameplay Core runtime unification.
Training target	select	Chooses optional Enemy/NPC target for the historical playable-room slice.	Project build config	Retained runtime	Not a generalized enemy system.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Move speed	number 1-4	Player horizontal speed in pixels per 60 Hz tick.	Project runtime config	Player movement	Only current retained single-room/World Player executor.
Jump speed	number 1-12	Initial jump velocity.	Project runtime config	Player movement	Pixel/tick convention.
Gravity	number 1-3	Downward acceleration per tick squared.	Project runtime config	Player movement	Different from Scene Gravity dropdown metadata.
Maximum fall	number 1-8	Caps downward velocity.	Project runtime config	Player movement	Current generated profile bound.
Body width	number 2-32 even	Sets Player collision-body width.	Project runtime config	Solid collision	Even width required.
Body height	number 2-48	Sets Player collision-body height.	Project runtime config	Solid collision	Feet/center conventions matter for placement.
Build & Play	button	Builds and launches the selected retained mode.	Build + runtime	Build & Run	Disabled if configuration validation fails or World Runtime is selected.
Edit room	button	Navigates to the configured playable Scene.	Editor navigation	SCENE	No data change.
Bind animations	button	Opens ENTITY STUDIO for the selected retained Player.	Editor navigation	ENTITY STUDIO	Player typically needs idle/walk/attack; attack nonlooping in current retained gameplay checks.
Status/help	status	Explains validation results and whether World Runtime has superseded this mode.	Diagnostics	CODE/WORLD	Do not interpret green references-only validation as proof of final ROM capacity.

CHR SHEET

CHR SHEET edits 8x8 pattern data. The same source tile may be reused in many higher-level assets, so editing one tile can intentionally update many appearances.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
BG Bank ($0000)	button	Edits the Scene background CHR set used by nametables/metatiles.	Project CHR data	SCENE, METATILES	BG and Sprite source banks are separate authoring arrays.
Sprite Bank ($1000)	button	Edits the Scene sprite CHR set.	Project CHR data	SPRITES, METASPRITES	Used by sprite/metasprite art.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
ROM CHR Banks selector	select	Selects a physical/logical CHR bank from an imported ROM when available.	Editor/import state	Import ROM	Only visible after relevant ROM import/capture.
-> BG	button	Copies selected imported ROM CHR bank into the active Scene BG CHR source.	Project CHR data	SCENE/METATILES	This is an explicit import into project assets.
-> Spr	button	Copies selected imported ROM CHR bank into active Scene sprite CHR source.	Project CHR data	SPRITES/METASPRITES	Explicit import.
CHR sheet tile grid	canvas	Selects an 8x8 tile for editing.	Editor selection	Tile editor	Arrow keys move selection.
8x8 pixel editor	canvas	Paints 2-bit pixel indices 0-3 in selected tile.	Project CHR data	All references to that tile	Changing a source tile updates all assets that reference it.
Pixel Color 1-4	palette selector / keys 1-4	Chooses pixel index used by the tile editor.	Editor selection	8x8 editor	These are palette indices, not independent RGB colors.
Clear Tile	button	Sets selected tile pixels to zero.	Project CHR data	All uses of tile	Undoable.
Copy Tile	button	Copies selected tile pixels to internal clipboard.	Editor clipboard	Paste Tile	No source change.
Paste Tile	button	Overwrites selected tile with copied pixels.	Project CHR data	All uses of destination tile	Undoable.
Preview Palette mode: Scene colors (auto)	select option	Previews tile using dominant/current Scene usage context.	Editor preview	CHR contexts	Preview only; does not duplicate or recolor the tile data.
Preview Palette mode: Selected palette	select option	Forces chosen palette row for preview.	Editor preview	Palette editor	Preview only.
Preview Palette mode: Pixel values	select option	Shows raw pixel-index diagnostic colors.	Editor preview	CHR debugging	Not an NES palette appearance.
Appearance/context selector	select	Chooses among alternate Scene appearances when a reused tile appears with multiple palettes/masks.	Editor preview	Runtime capture contexts	Does not mutate project palette assignment.
Tile Usage Map	visualization	Shows frequency/placement usage of CHR tile indices.	Diagnostics	Capacity/reuse decisions	Counts depend on active Scene.
Highlight in Scene	button	Finds selected tile in Scene and highlights placements.	Editor navigation	SCENE	Does not change tiles.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Auto-track	checkbox	Automatically refreshes Find in Scene when selected tile changes.	Editor behavior	CHR selection	Can be turned off when manually inspecting results.
Find mini-scene	canvas	Shows selected tile placements; click a position to jump to that tile in SCENE.	Editor navigation	SCENE	Jump selects tile and switches tab.

METATILES

METATILES owns reusable Scene-local 16x16 terrain definitions and quadrant collision. It links raw CHR/palette data upward into WORLD authoring.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Analyze Scene -> Library	button	Scans static Scene 2x2 tile cells and creates/reuses 16x16 metatile definitions without changing visible pixels.	Project metatile data	SCENE/WORLD	Exact raster captures are read-only; make a lossless static copy first.
+ From Selected Cell	button	Creates a metatile definition from the currently selected 16x16 Scene cell.	Project metatile data	SCENE brush/WORLD palette	Useful for hand-built samples.
Relink Matches	button	Reattaches matching raw Scene cells to existing metatile definitions.	Project metatile links	SCENE/WORLD	Matches are based on definition content.
Tool: Select cells	select option	Selects 16x16 cells for inspection/editing rather than painting.	Editor mode	Selected cell actions	No data change until an edit action.
Tool: Paint metatile	select option	Paints chosen metatile onto Scene cells.	Project Scene + links	SCENE data	Writes underlying nametable/attributes while preserving metatile identity.
Brush	select	Chooses the metatile ID used by paint tool.	Editor selection	Scene/metatile painting	Scene-local library only.
Show metatile collision overlay	check box	Shows quadrant collision classifications over the metatile view.	Editor view	Collision quadrants	Display only.
Library cards	selection	Selects a metatile definition and shows usage count.	Editor selection	Selected Metatile form	Definition edits propagate to linked placements.
Name	text	Renames selected metatile.	Project data	WORLD brush labels	Stable numeric/internal ID remains reference identity.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Category	text	Stores authoring category/tag for selected metatile.	Project metadata	Palette/search organization	No direct runtime behavior by itself.
Palette P0-P3	select	Sets palette row used by the whole metatile definition.	Project metatile/palette data	Render/build	NES attribute constraints apply.
TL / TR / BL / BR CHR fields	number inputs	Sets the four 8x8 BG tile references making the 16x16 metatile.	Project metatile data	Scene/World rendering	Edits every linked placement.
Capture Selected Cell -> Definition	button	Overwrites selected metatile definition from selected Scene cell.	Project metatile data	All linked placements	Use carefully: changes every placement linked to definition.
Duplicate	button	Creates a new independent metatile definition copied from selected.	Project metatile data	Library	Best way to branch one tile into a variation.
Delete	button	Deletes selected metatile definition and reconciles references where applicable.	Project data	World/Scene links	World references may be cleared/reconciled; use Undo if accidental.
Collision TL/TR/BL/BR	selects	Assigns collision property independently to four 8x8 quadrants.	Project metatile collision	World Runtime collision	Current generated runtime primarily executes Empty/Solid semantics.
Collision All + Set all 4	select + button	Sets all four collision quadrants to one property in one action.	Project metatile collision	Runtime collision	Useful for fully solid/empty blocks.
Semantic flags	check boxes	Stores metatile semantic flags such as Foreground/Destructible/Animated/Interactive where available.	Project metadata	Future/gameplay tooling	Presence in authoring data does not guarantee current runtime execution.
Detach Selected Cell	button	Breaks the selected Scene cell’s link to its metatile definition while preserving current appearance.	Project Scene/metatile links	SCENE	Use before making a one-off raw edit.

METATILES workflow relationship

`CHR tiles + palette + quadrant collision -> Metatile definition -> SCENE linked placement and WORLD brush -> World Runtime terrain/collision`

A definition edit intentionally changes every linked placement. Duplicate first when you need a variant; Detach Selected Cell when only one Scene sample should diverge.

WORLD

WORLD owns large multi-screen metatile maps, Rooms, markers, camera regions, and the World Runtime configuration. It references a Scene as its tileset source rather than copying a second independent CHR library.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
World selector	select	Chooses active project-level World.	Editor selection	World tools/runtime config	World is distinct from Scene.
+ World	button	Creates a new World using a Scene that has a metatile library.	Project World data	METATILES	If active Scene has no metatiles, current UI prefers a compatible tileset Scene or prompts recovery.
Duplicate World	button	Copies World map/regions/markers into an independent World.	Project data	World links	Stable IDs are regenerated/remapped as required.
Delete World	button	Deletes active World.	Project data	Runtime start/marker links	Can invalidate runtime or entrance references.
Name	text	Renames active World.	Project data	Selectors	Stable ID preserves links.
Tileset Scene	select	Chooses the Scene whose metatile/CHR/palette library renders this World.	Project data	METATILES/CHR	Changing tileset must be deliberate; unresolved IDs are preserved/reported rather than silently destroyed in corrected workflows.
Width / Height screens	number 1-16	Sets World size in NES screens; underlying map is 16x15 metatile cells per screen.	Project World data	World canvas/runtime	Large maps are subject to build/runtime capacity.
View arrows	buttons	Pans the editor viewport by one screen left/right/up/down.	Editor view	World canvas	Does not move World content.
World Zoom 1x/2x/3x	select	Changes World editor canvas scale.	Editor view	World canvas	Separate from global canvas zoom.
Basic Metatile Brush	select	Chooses metatile used for World paint.	Editor selection	World paint tools	Requires chosen Tileset Scene to have metatiles.
Use [scene] / Open METATILES recovery	buttons	Recovers from a zero-metatile tileset by selecting a compatible Scene or opening the library editor.	Editor/project configuration	METATILES	Prevents blank brush confusion.
+ Current Screen room	button	Creates a 16x15-cell Room rectangle covering current viewport screen.	Project World data	Gameplay Core Room scope	Rooms are authoring/gameplay scope boundaries; not merely decoration.
+ Entrance / + Spawn / + Exit	buttons	Adds World markers near the current screen center.	Project World data	World Runtime navigation/start	Linked Entrance/Exit needs both Target World and Target Marker.
+ Current Screen Region	button	Creates a camera region covering current screen.	Project World camera data	World Runtime camera selection	Mode controls follow/locked/horizontal/vertical behavior where supported.
Tool: Select	tool button	Selects/moves/resizes Rooms/Cameras, selects markers, or drags a rectangular map region.	Editor mode	Inspector/region actions	Lower-right cell acts as resize handle for Room/Camera.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Tool: Paint	tool button	Paints selected metatile across World cells.	Project World map	World Runtime terrain	Left-drag; right-click eyedrops.
Tool: Erase	tool button	Sets World cells to empty/unpainted.	Project World map	Runtime terrain	Undoable.
Tool: Fill	tool button	Flood-fills contiguous matching cells with current brush.	Project World map	Runtime terrain	Use carefully on large regions.
Tool: Rect	tool button	Drag-paints a rectangle with current metatile.	Project World map	Runtime terrain	Faster room/block painting.
Tool: Room	tool button	Drag-creates a Room rectangle.	Project World data	Room persistence / authoring scope	Room is a scoped object with ID/name/bounds.
Tool: Entrance / Spawn / Exit	tool buttons	Click-places the corresponding marker at a World cell.	Project World data	Runtime start/transitions	Marker coordinates are metatile-cell coordinates in current authoring model.
Tool: Camera	tool button	Drag-creates a Camera Region.	Project World camera data	Runtime camera selection	Runtime profile remains screen-transition oriented.
Metatile search	text	Filters the visual World metatile palette by name/category/ID.	Editor view	Palette	Does not alter library.
Favorites-only star	toggle	Filters palette to favorited metatiles.	Editor preference/session	Palette	Favorites are authoring convenience, not runtime data.
Palette metatile card	button/card	Selects a brush; star toggles favorite.	Editor selection	Paint/Rect/Fill	Selecting may switch tool to Paint.
Region Copy	button	Copies selected rectangular World cells to World clipboard.	Editor clipboard	Region Paste	Selection must exist.
Region Paste	button	Pastes copied World region at selected/target location.	Project World map	World runtime	Preserves metatile IDs subject to target bounds.
Region Clear	button	Clears selected World region.	Project World map	World runtime	Undoable.
Minimap / Overview	canvas	Shows entire World and jumps editor viewport when clicked.	Editor navigation	World view	Not a runtime minimap asset.
Room inspector: Name/X/Y/W/H	form	Edits selected Room identity label and bounds.	Project World data	Gameplay Core Room placement/persistence	Coordinates/sizes are clamped to World bounds.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Delete room	button	Removes selected Room.	Project World data	Gameplay references	May invalidate Actor/persistent owner references.
Camera inspector: Name/X/Y/W/H	form	Edits selected Camera Region.	Project World data	World runtime camera	Bounds clamped.
Camera Mode: follow/locked/horizontal/vertical	select	Sets selected Camera Region mode.	Project runtime metadata	World runtime	Current engine is screen-transition; modes are still canonical World data.
Delete camera	button	Removes selected Camera Region.	Project data	World runtime	Undoable.
Marker Kind	select	Changes marker among entrance/spawn/exit.	Project World data	Runtime navigation	Changing type can alter how it is used by runtime selection.
Marker Name / X / Y	form	Edits marker label and location.	Project World data	World runtime	Location clamped to World grid.
Target World	select	Sets destination World for Entrance/Exit.	Project World links	World Runtime	Changing target World clears incompatible target marker selection.
Target Marker	select	Sets destination Spawn or Entrance marker in the selected target World. Exit is not a valid destination in the current runtime.	Project World links	World Runtime	Both destination fields required for runtime link.
Delete marker	button	Removes selected marker.	Project data	Start/links	May invalidate start marker or links.
Build Status	status	Shows World map/metatile usage and build/runtime warnings.	Diagnostics	Build	Current viewer/runtime limitations are surfaced here.

WORLD workflow relationship

`Tileset Scene -> Metatile Library -> World map -> Rooms/Markers/Cameras -> World Runtime config -> BuildGraph -> ROM`

Gameplay Core Room/World placements and persistent-variable owners depend on stable WORLD/Room IDs, so deleting or retargeting those objects can invalidate gameplay references.

WORLD > WORLD RUNTIME

World Runtime turns authored WORLD data into the generated multi-screen runtime. Current 1.9.0 behavior is screen-transition based rather than smooth scrolling.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Build this project as World Runtime	checkbox	Makes World Runtime the generated runtime mode for Build/Build & Run.	Project build config	WorldCompiler/RuntimeCompiler	Supersedes saved viewer/single-room config while enabled.
Start world	select	Chooses World loaded at game start.	Project runtime config	Start marker	Must be reachable/valid.
Start marker	select	Chooses Spawn/Entrance marker used as initial Player location.	Project runtime config	World marker data	Source Scene Player X/Y is not the runtime start location.
Player source scene	select	Chooses Scene containing the legacy Player entity/art source.	Project runtime config	ENTITY STUDIO/animations	Source assets must be linkable.
Player	select	Chooses bound legacy Player entity.	Project runtime config	ENTITY STUDIO	Retained compatibility executor.
Move speed / Jump speed / Gravity / Maximum fall	numbers	Controls retained Player movement in World Runtime.	Project runtime config	World runtime	NES/pixel-per-tick bounds enforced.
Body width / Body height	numbers	Controls retained Player collision body.	Project runtime config	Metatile solid collision	Body sizes must remain within profile bounds.
Build & Run	button	Builds and launches World Runtime with current configuration.	Build + runtime	EMULATOR	Preflight validates reachable worlds/resources/capacity.
Runtime status	status	Shows configuration validation/errors and control hints.	Diagnostics	Build	Does not replace final compiler validation.

ATTR MAP

ATTR MAP displays the full-map palette zones. In the current app, left-clicking a 16×16 quadrant cycles its palette with Undo support. The SCENE ATTR EDITOR also edits attributes.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Attribute visualization canvas	canvas/view	Displays palette assignment across the active Scene, color-coded by P0-P3 with 32x32 attribute boundaries.	Editor visualization	SCENE ATTR EDITOR	Current authoritative editing is the SCENE ATTR Editor; treat this tab primarily as inspection.
Palette zone counts	status	Counts Scene cells assigned to palette rows 0-3.	Diagnostics	Palette planning	Informational.
Global Attr overlay	top checkbox	When applicable, overlays attribute information on other canvas views.	Editor view	SCENE	Separate from this full-map visualization.

SPRITES

SPRITES edits Scene OAM-style sprite entries and the source sprite CHR/palettes used by composed frames.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
+ Add Sprite	button	Creates a new hardware-style OAM sprite entry in the active Scene.	Project OAM data	METASPRITES capture, viewer/runtime	NES has 64 OAM slots; current editor warns on limits.
OAM Slots list	list	Selects and orders/inspects Scene sprite entries.	Editor selection	Sprite properties	Lower OAM index affects overlap priority.
Delete Selected	button	Deletes selected Scene OAM sprite.	Project data	Metasprite capture/source	Undoable.
Sprite canvas click	canvas interaction	Places/selects a sprite on Scene; drag moves it; right-click deletes in the Sprite view.	Project OAM data	Scene sprite composition	Arrow keys nudge selected sprite.
Tile	number 0-255	Sets selected sprite CHR tile.	Project OAM data	Sprite CHR	8x16 mode may involve lower tile pairing.
X / Y	number 0-255 / 0-239	Sets selected sprite screen position.	Project OAM data	Rendering/build	NES OAM stored Y has hardware offset on export.
Palette SP0-SP3	select	Chooses one of four sprite palettes.	Project OAM data	Sprite render/build	Separate from BG palettes.
FlipH / FlipV	checkboxes	Sets NES sprite flip attribute bits.	Project OAM data	Render/build	8x16 vertical flip swaps pair order appropriately in composed tooling.
Behind	checkbox	Sets sprite priority behind nontransparent background.	Project OAM data	Render/build	NES priority semantics.
Draw Sprite Tile pixel editor	canvas	Edits selected sprite CHR tile pixels directly.	Project sprite CHR	All uses of tile	Same source data visible from CHR SHEET Sprite Bank.
Clear Tile	button	Clears selected sprite CHR tile.	Project CHR data	All references	Undoable.
Open in CHR Sheet	button	Navigates to CHR SHEET with sprite bank/tile selected.	Editor navigation	CHR SHEET	No data change.
Sprite CHR Picker	grid	Chooses tile used by selected/next sprite.	Editor selection	OAM Sprite	Source Scene sprite bank.
Sprite Palettes	palette editor	Edits Scene sprite palette rows.	Project palette data	Sprites/Metasprites	Changes all uses of palette entry.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Hardware warnings	status	Warns about OAM/scanline limits such as more than 8 sprites on a scanline.	Diagnostics	Build/render planning	Warnings are frame-local; multiple metasprite actors share hardware budget at runtime.

METASPRITES

METASPRITES builds reusable multi-piece sprite frames from source Scene sprite CHR. It is the pose/composition layer below ANIM.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
+ Piece	button	Adds a sprite piece to the selected reusable frame using current CHR brush.	Project metasprite data	ANIM	One piece corresponds to one OAM slot in 8x8 or one 8x16 pair slot.
Fit frame	button	Adjusts composer view so the current frame bounds fit the canvas.	Editor view	Composer	No data change.
Zoom 0.25x-8x	select	Changes composer scale.	Editor view	Composer canvas	Does not alter stored coordinates.
Snap 1px / 8px	select	Sets drag movement grid for pieces.	Editor interaction	Piece positioning	Coordinates are still stored in pixels.
Grid	checkbox	Shows/hides composer grid.	Editor view	Canvas	No project change.
Boxes	checkbox	Shows/hides piece bounds/selection boxes.	Editor view	Canvas	No project change.
Hardware limits	checkbox	Previews first 64 OAM pieces and eight sprites/scanline constraints.	Editor simulation	Hardware budget	Diagnostic approximation for this frame; multiple runtime actors share limits.
Frame selector	select	Chooses reusable metasprite frame.	Editor selection	ANIM frame source	Frames are project assets with stable IDs.
+ New frame	button	Creates empty reusable metasprite frame.	Project data	ANIM	Choose source Scene/sprite mode.
Capture scene OAM	button	Builds a metasprite frame from active/source Scene OAM arrangement.	Project metasprite data	SPRITES	Useful for converting a composed Scene sprite into reusable frame.
Duplicate	button	Copies selected frame independently.	Project data	Animation pose variations	Preserves pieces/source.
Mirror copy	button	Creates mirrored copy of selected frame.	Project data	Left/right pose authoring	Uses origin as mirror reference.
Delete	button	Deletes selected metasprite frame.	Project data	ANIM references	Referenced animations may become invalid.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Export frames	button	Exports metasprite frame data for external/reference use.	External file	Metasprite library	Project Save/Export remains authoritative backup.
Name	text	Renames frame.	Project data	ANIM selectors	Stable ID remains reference.
Source scene	select	Chooses Scene supplying sprite CHR/palettes.	Project asset reference	SPRITES/CHR	Edits to source art update every frame using it.
Sprite size 8x8 / 8x16	select	Chooses NES hardware sprite-size interpretation for frame pieces.	Project metasprite data	Build/OAM linking	8x16 has pair and hardware-size rules.
Origin X / Y	numbers	Defines frame anchor; piece placement is relative to this origin.	Project metasprite data	ANIM/Entity placement	Origin is essential for consistent pose alignment.
Set origin at feet	button	Moves frame origin to calculated feet/bottom anchor.	Project data	Animation/player placement	Useful for side-view characters.
Hardware Budget	status	Reports piece count, scanline pressure, and related warnings.	Diagnostics	NES constraints	Not a guarantee for multiple simultaneous actors.
Pieces OAM order list	list/buttons	Selects a piece and displays OAM order.	Editor selection	Earlier/Later	Earlier OAM index wins overlapping sprite pixels.
Duplicate piece	button	Copies selected piece.	Project data	Frame geometry	Undoable.
Remove piece	button	Deletes selected piece.	Project data	Frame geometry	Undoable.
Earlier / Later	buttons	Moves selected piece in OAM ordering.	Project data	Sprite overlap priority	Also affects budget ordering.
Tile / lower	numbers	Sets top tile and lower tile in 8x16 mode.	Project data	Sprite CHR	8x8 mode effectively uses top tile.
Piece X / Y	numbers	Sets piece position relative to frame coordinate system.	Project data	Frame bounds	Range supports off-origin composition.
Palette 0-3	select	Sets sprite palette for piece.	Project data	Source Scene sprite palettes	Palette data comes from source Scene.
Flip H / Flip V / Behind BG	checkboxes	Sets per-piece OAM attributes.	Project data	Rendering/build	Behind BG meaningful against actual scene background.
Mirror X at origin / Mirror Y at origin	buttons	Mirrors selected piece position/orientation around frame origin.	Project data	Pose creation	Different from creating full Mirror copy frame.
Source Sprite CHR sheet	canvas	Click chooses tile brush; double-click adds selected tile as a new piece.	Editor selection + project on double-click	SPRITES/CHR	Color 0 is transparent.

ANIM

ANIM sequences legacy tiles or metasprite frames, stores durations, frame contact areas, and ordered frame-entry events.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
+ Add Animation	button	Creates a new animation asset.	Project animation data	ENTITY STUDIO	Animation frames can use legacy tiles or metasprites.
Animation list	list	Selects animation for editing.	Editor selection	Animation properties	Stable animation IDs are used by bindings.
Name	text	Renames animation.	Project data	ENTITY STUDIO/Game references	ID remains stable.
State	select	Stores descriptive state category: idle/walk/run/jump/fall/attack/hurt/custom.	Project animation metadata	Entity binding/templates	Binding can use custom lowercase state names independently.
Loop	checkbox	Controls whether preview/runtime binding loops after final frame.	Project animation data	Runtime animation	Current retained attack generally needs nonlooping behavior.
Flip on reverse	checkbox	Allows reversed-facing playback to flip composed art where supported.	Project animation data	ENTITY STUDIO facing	Does not create a separate mirrored frame asset.
Timeline frame buttons	timeline	Selects animation frame; displays duration/source/event counts.	Editor selection	Frame editor	Click chooses frame.
+ Frame / - Frame	buttons	Adds/removes animation frames.	Project animation data	Runtime playback	Duplicated/added frame source can then be configured.
Frame source: Legacy tile	select option	Uses one sprite tile index for the animation frame.	Project animation data	Source Scene sprite CHR	Simpler historical path.
Frame source: Metasprite	select option	Uses reusable METASPRITES frame.	Project animation data	METASPRITES	Preferred for multi-piece characters/objects.
Metasprite	select	Chooses composed frame when Frame source is Metasprite.	Project reference	METASPRITES	Missing referenced metasprite is reported.
Tile $	number	Sets legacy sprite tile index when Frame source is Legacy tile.	Project animation data	Sprite CHR	Disabled while metasprite source is selected.
Duration	number 1-255	Sets frame duration in 60 Hz ticks/frames.	Project animation data	Preview/runtime	Entity Studio uses one tick = 1/60 second.
Preview Play / Stop	buttons	Starts/stops animation preview.	Editor preview	ANIM canvas	Leaving ANIM stops preview.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Frame contact tool: Select / move	button	Selects and manipulates hit/hurt areas on selected frame.	Editor mode	Frame contact areas	Contact boxes are authoring data; execution depends on runtime capability.
Draw hit	button	Drag-creates red attack/hit area on selected frame.	Project animation data	Future/richer combat	1.9.0 current generic NROM profile does not provide full hitbox combat.
Draw hurt	button	Drag-creates green vulnerable/hurt area.	Project animation data	Future/richer combat	Same runtime caveat.
+ Hit / + Hurt	buttons	Adds default contact area without drag.	Project animation data	Contact area list	Up to 16 of each kind per frame.
Contact area list	select	Selects hit/hurt area for exact field editing.	Editor selection	Area fields	Selection is frame-specific.
Area Name / X / Y / Width / Height	form	Edits selected contact area in pixels relative to sprite origin.	Project animation data	Contact rendering/runtime	Arrow keys nudge; Shift = 8 px; Delete removes; Escape cancels drag.
Delete area	button	Removes selected hit/hurt area.	Project data	Animation frame	Undoable.
Show areas	checkbox	Shows/hides frame contact boxes in editor preview.	Editor view	ANIM	No project semantic change.
New event type	select	Chooses frame-entry event type to add.	Editor selection	+ Event	Available types defined by current model; custom supported.
+ Event	button	Adds ordered marker emitted when selected frame begins.	Project animation data	ENTITY STUDIO event log / Audio runtime sound events where supported	Events do not automatically execute damage/sound in the ANIM preview.
Event list	select	Selects ordered frame-entry event.	Editor selection	Event fields	Max 16 per frame.
Event Type / Name / Value	form	Edits selected event payload.	Project animation data	Runtime/event consumers	Runtime support varies by event type.
Earlier / Later	buttons	Reorders selected frame-entry event.	Project data	Event emission order	Order can matter to consumers.
Delete event	button	Removes selected event.	Project data	Animation frame	Undoable.

ENTITY STUDIO

ENTITY STUDIO binds animations to legacy Scene entities and previews pose/state playback. It is not the Gameplay Core behavior state machine.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
State	select	Chooses bound animation state to preview for selected legacy Scene entity.	Editor preview	Animation bindings	This is preview/binding state, not Gameplay Core behavior state.
Play / Pause	button	Runs/stops animation-state preview.	Editor preview	Timeline/events	No gameplay logic executes here.
Restart	button	Restarts preview from tick/frame zero.	Editor preview	Timeline	No project change.
Tick +1	button	Advances preview one 1/60-second tick.	Editor preview	Frame entry events	Useful for event timing inspection.
Facing Right / Left	select	Temporarily previews bound animation facing.	Editor preview	Flip-on-reverse	Separate from saved default facing below.
Boxes	checkbox	Shows/hides frame hit/hurt boxes in preview.	Editor view	ANIM data	No runtime execution here.
Labels	checkbox	Shows/hides overlay labels in preview.	Editor view	Preview	No data change.
Timeline range	slider	Scrubs preview tick through current animation.	Editor preview	Frame timeline	No data change.
Frame timeline buttons	buttons	Jump preview to start of selected animation frame.	Editor preview	Animation	Shows duration/events.
Clear log	button	Clears preview frame-entry event log.	Editor preview log	Events	No project data change.
Scene	select	Chooses Scene containing legacy entities.	Editor selection	Entity selector	Gameplay Core Actor Instances are separate.
Entity	select	Chooses legacy Scene entity whose animation bindings/defaults are edited.	Editor selection	Bindings	Player in retained runtime is configured here.
Edit in scene	button	Navigates to selected Scene/entity.	Editor navigation	SCENE	No data change.
Edit animation	button	Navigates to currently bound animation in ANIM.	Editor navigation	ANIM	Requires binding/selection.
Binding rows + Remove	list/buttons	Shows state -> animation mappings and removes selected mappings.	Project legacy entity data	Retained Player runtime	Bindings are saved on legacy entity.
State name	text	Names animation state binding, e.g. idle/walk/attack.	Project entity binding	Assign state	Lowercase letters/digits/_/-; up to 16 states.
Animation	select	Chooses animation asset assigned to state name.	Project entity binding	ANIM	Reusing state name updates assignment.
Assign state	button	Creates/updates state binding on selected entity.	Project entity binding	Retained runtime	Does not create Gameplay Core state-table behavior.
Default state	select	Chooses animation state used when entity begins preview/runtime context.	Project entity binding	Retained Player	Must reference assigned state.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Default facing	select	Stores Right/Left default facing for entity.	Project entity data	Retained Player	Preview-facing control is temporary.
Place Entity Type	select	Chooses legacy entity type to create.	Editor selection	Add/Place	Legacy entity system.
Scene X / Y	numbers	Sets exact coordinates for new legacy entity.	Editor input	Add at X/Y	0-255 / 0-239 bounds.
Add at X / Y	button	Creates legacy entity at typed coordinates.	Project entity data	SCENE/Bindings	Does not enter click-placement mode.
Place in scene	button	Switches to SCENE placement workflow for chosen entity type.	Editor mode	SCENE	Click scene to place.
Frame-entry event log	status list	Logs events when preview enters frames; latest 200 entries retained.	Editor diagnostics	ANIM events	No attack, damage, or sound runs in Entity Studio preview.

GAMEPLAY CORE

Gameplay Core is the 1.9.0 generalized actor/behavior authoring panel. Templates create ordinary editable canonical records. The current mapper-0 generated profile executes only a bounded subset of the wider canonical operation vocabulary.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Enable canonical Gameplay Core	checkbox	Enables generalized 1.9.0 Actor/Behavior data for applicable generated runtimes.	Project gameplay config	RuntimeCompiler	Does not convert legacy Player/Target records destructively.
Placement kind: Scene / Room / World	select	Chooses where newly created templates/instances/variables are authored.	Editor authoring context	Placement selector	Room/World placement is important for scoped persistence and reachable World compilation.
Placement selector	select	Chooses actual Scene, World, or Room matching placement kind.	Editor authoring context	Add template/New Instance/New variable	Stable IDs are stored, not display names.
Template selector	select	Chooses one of five 1.9.0 recipes: Sideview Player, Ground Patrol Enemy, Stationary Contact Hazard, Collectible Pickup, Switch + Door.	Editor selection	Add template	Templates generate ordinary canonical records; there is no template runtime engine.
Add template	button	Adds Actor Definition, Behavior, Actor Instance and any declared variables/bindings required by chosen recipe.	Project gameplay data	All Gameplay Core tables	Five-template 1.9.0 limit is intentional.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Gameplay Core status	status	Shows enabled/disabled and counts/validation messages including persistent profile usage.	Diagnostics	Compiler	Executable profile validation still occurs at build.
New Actor Definition	button	Creates reusable Actor Definition asset.	Project gameplay data	Instances/components/behavior	Definition is archetype, not placement.
Actor Definition table	table	Lists ID/name/behavior and selects a definition for typed editing.	Editor selection + project data	Components/parameters	Stable ID is reference identity.
Definition Name	text	Renames selected Actor Definition.	Project data	Selectors	Does not change stable ID.
Definition Behavior	select	Binds canonical Behavior Definition to Actor Definition.	Project data	State table/runtime	Missing behavior reference fails validation.
Remove Definition	button	Deletes Actor Definition.	Project data	Actor Instances	References must be repaired/removed first.
New Actor Instance	button	Creates a placed instance of an Actor Definition at current placement context.	Project gameplay data	Runtime Actor generation	Instance has own stable ID and overrides/bindings.
Instance Definition	select	Chooses reusable Actor Definition for selected instance.	Project reference	Runtime compilation	Changing it changes capabilities/defaults inherited by instance.
Instance Placement	Scene/Room/World selects	Edits instance spatial/scope owner.	Project gameplay placement	World reachability/persistence	Room placement must resolve a real authored Room.
Instance X / Y	numbers	Sets authored actor coordinates.	Project gameplay placement	Generated runtime	Coordinate interpretation depends on placement/runtime path.
Instance Facing	select	Sets authored initial facing.	Project gameplay data	Rendering/behavior inputs where supported	Current generic profile capabilities are bounded.
Overrides table	typed table	Overrides Actor Definition parameters for one instance.	Project gameplay data	Behavior/component consumers	Does not mutate definition/defaults or sibling instances.
Add binding	button	Adds explicit Actor Instance -> persistent-variable binding.	Project gameplay data	PersistenceBinding	Instance binding is authoritative; component mirror fields are not independent truth.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Persistence bindings table	table	Maps declared variable IDs to named purposes on selected Actor Instance.	Project gameplay data	Room/World persistence	Runtime Actor memory is not automatically persisted.
Add parameter	button	Adds typed default parameter to selected Actor Definition.	Project gameplay data	Behavior operation parameter references	Supported types: boolean, uint, int, enum, text, asset.
Parameter ID / Type / Default / Bounds-or-enum	typed row	Defines reusable bounded authoring parameter.	Project gameplay data	Instance overrides/ operations	Validation enforces type/range/reference rules.
Add component	button	Adds typed capability/data component to selected Actor Definition.	Project gameplay data	Compiler/runtime profile	Component presence does not guarantee selected runtime executes every capability.
Component Type	select	Chooses Transform, Spawn, Render, Animation, Physics, Collider, Input, Health, ContactDamage, Behavior, Pickup, Switch, Door, PersistenceBinding.	Project gameplay data	Runtime profile	1.9.1 component families are intentionally absent.
Component Enabled	checkbox	Enables/disables component capability.	Project gameplay data	Compiler/runtime	Corrected candidate treats disabled Behavior as inert rather than executing anyway.
Render: sourceSceneId / tile / palette / behind	typed fields	Defines simple generic Actor visual source in current profile.	Project gameplay data	Generated generic actor renderer	Generic actor rendering is not the same as retained multi-piece Player/metasprite path.
Collider: width / height	typed fields	Defines Actor collision dimensions.	Project gameplay data	Overlap/contact calculations	Current profile range 1-64.
Input: adapter=legacyPlayer	typed field	Marks retained Sideview Player compatibility binding.	Project compatibility data	Retained Player executor	Not generic-runtime Player unification.
Health: maximum	typed field	Sets bounded byte maximum health.	Project gameplay data	Runtime health array	Corrected validation rejects out-of-range >255 instead of byte wrapping.
ContactDamage values	typed fields/status	Mirrors/represents contact-damage capability; authoritative behavior action values must remain clear in UI.	Project gameplay data	contactDamage action	Avoid conflicting fields that look authoritative when compiler uses behavior action operands.
New Behavior	button	Creates canonical state-table Behavior Definition with initial state.	Project gameplay data	Actor Definitions	Behavior is separate reusable asset.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Behavior selector / Name / Remove	controls	Selects, renames, or deletes Behavior Definition.	Project gameplay data	Definitions	Deleting referenced behavior invalidates build.
Add behavior parameter	button	Adds typed parameter local to Behavior Definition.	Project gameplay data	Operation parameter references	Same bounded type model.
Add state	button	Creates canonical state record with ordered onEnter/onTick/onExit lists.	Project behavior data	Evaluator/ compiler	At least one state needed for useful behavior.
Initial state	select	Chooses Behavior state used when Runtime Actor initializes/reconstructs.	Project behavior data	Runtime actor lifecycle	Transient current state is not a persistent variable unless explicitly modeled.
State Name / Remove	controls	Renames/removes selected state.	Project behavior data	Transitions	Removing referenced state requires transition repair.
onEnter / onTick / onExit Add action	typed operation controls	Adds ordered actions executed at the corresponding state lifecycle point.	Project behavior data	Canonical evaluator/ runtime profile	Only operations supported by current generated profile may compile.
Add transition	button	Creates transition record with from/to state, priority, conditions, and actions.	Project behavior data	Deterministic evaluator	Default transition starts as same-state with always condition.
From / To state	selects	Chooses source/destination states.	Project behavior data	Evaluator	Stable state IDs underlie labels.
Priority	number -128..127	Orders transition evaluation; higher/defined priority is evaluated before authored-order tie break as model specifies.	Project behavior data	Determinism	At most one transition commits per actor tick in 1.9.0.
Add condition	button	Adds a typed canonical condition to transition.	Project behavior data	Transition evaluator	Unsupported generated-profile condition rejects executable build.
Add transition action	button	Adds typed actions executed during transition.	Project behavior data	Evaluator/ runtime	Unsupported profile action rejects executable build; never silently no-op.
Condition type: always	operation	Always true.	Project behavior data	Transitions	Supported by current NROM Gameplay Core profile.
Condition type: inputHeld / inputEdge	operation	Tests controller input state/edge.	Project behavior data	Input sources	Canonical; current profile supports specified input conditions.
Condition type: grounded / airborne	operation	Tests physics grounding state.	Project behavior data	Physics	Canonical authorable; current mapper-0 profile may reject if unsupported.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Condition type: timerDone	operation	Tests named behavior timer completion.	Project behavior data	setTimer	Supported by current profile.
Condition type: compare	operation	Compares a named/runtime field to value/operator.	Project behavior data	Behavior params/runtime fields	Canonical; current generated profile support is bounded.
Condition type: overlapPlayer	operation	Tests Actor overlap with retained Player using boundary-safe generated comparison.	Project behavior data	Pickup/hazard	Supported by current profile; corrected opposite-edge wraparound bug is specifically tested.
Condition type: healthCompare	operation	Compares health.	Project behavior data	Health	Canonical; generated profile support may reject if not in supported set.
Condition type: animationComplete / animationEvent	operation	Tests animation lifecycle/event.	Project behavior data	Animation	Canonical; current profile support is bounded.
Condition type: triggerReceived	operation	Tests typed trigger receipt.	Project behavior data	Trigger events	Canonical; current profile may reject.
Condition type: persistentCompare	operation	Compares declared Room/World variable to value.	Project behavior data	Persistence	Supported by current profile.
Action: setTimer	operation	Sets named behavior timer to bounded tick count.	Project behavior data	timerDone	Supported by current profile; missing ticks fails validation.
Action: persistentSet	operation	Assigns declared persistent variable.	Project behavior data	Room/World state	Supported by current profile.
Action: persistentChange	operation	Changes numeric persistent value by bounded amount.	Project behavior data	Persistence	Canonical; selected profile may reject if unsupported.
Action: despawn	operation	Deactivates/removes runtime actor according to generated profile semantics.	Runtime behavior	Pickups/etc.	Supported current profile; persistence must be explicit if disappearance should survive reconstruction.
Action: moveWithinBounds	operation	Moves Actor horizontally within authored bounds/speed and reverses as needed.	Runtime behavior	Ground Patrol	Supported current profile.
Action: contactDamage	operation	Applies bounded damage/cooldown when Actor overlaps retained Player.	Runtime behavior	Hazard/Patrol	Supported current profile.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Action: syncActiveFromPersistent	operation	Synchronizes active state from declared persistent variable.	Runtime behavior	Switch/Door alpha template	1.9.0 alpha behavior is one-way after deactivation until reconstruction; not a reversible general gate contract.
Canonical actions: selectAnimation / setFacing / setVelocity / accelerate / changeHealth / spawnActor / emitTrigger	operations	Authorable/preservable canonical operations for broader model.	Project behavior data	Future/profile-dependent	Current NROM Gameplay Core profile rejects unsupported operations before ROM generation.
New persistent variable	button	Declares Room- or World-scoped variable.	Project gameplay data	Persistence records	Current NROM profile supports max 64 one-byte values.
Variable ID / Name	text	Defines stable variable identity and display label.	Project gameplay data	Bindings/conditions/actions	Stable ID is reference identity.
Scope: Room / World	select	Declares persistence owner scope.	Project gameplay data	Owner selector	Game/Global scope is intentionally not in 1.9.0.
Owner	select	Chooses exact Room or World that owns variable.	Project gameplay data	Runtime persistence store	Cross-owner references fail validation.
Type: boolean / uint / enum	select	Sets persistent value type.	Project gameplay data	Default/bounds	Stored as one-byte profile representation where applicable.
Default / min / max / enum values	typed fields	Defines initial persistent state and allowed value domain.	Project gameplay data	Runtime reset/reconstruction	Power/reset starts from authored defaults; no cross-session save backend yet.
Remove persistent variable	button	Deletes declared variable.	Project gameplay data	Bindings/operations	References must be removed/repaired.

Current generated Gameplay Core profile

Capacity: 12 executable Actor Instances total including Sideview compatibility Player; 64 one-byte persistent values; no generic actor streaming.

Conditions executed by current profile: `always`, `inputHeld`, `inputEdge`, `timerDone`, `overlapPlayer`, `persistentCompare`.

Actions executed by current profile: `persistentSet`, `despawn`, `setTimer`, `moveWithinBounds`, `contactDamage`, `syncActiveFromPersistent`.

Other canonical conditions/actions may remain authorable/preservable, but the executable build must reject them for this runtime profile rather than silently treating them as no-ops.

Door alpha contract: Switch + Door in 1.9.0 demonstrates linked persistent state and active/inactive visual behavior. It is not physically solid, and `syncActiveFromPersistent` cannot reactivate an actor after that actor has deactivated itself until reconstruction. The original edition deferred richer Door/traversal semantics to a later milestone. That historical 1.9.1 target is not a current delivery promise.

AUDIO

AUDIO owns tracker songs, instruments, SFX, MIDI/MusicXML import, and the current NES runtime audio build options.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Compile Audio Runtime	checkbox	Includes NES audio runtime in generated supported gameplay ROMs.	Project build config	RuntimeCompiler	Required for authored music/SFX to execute in ROM.
Autoplay tracker order as music	checkbox	Starts tracker order as background music when runtime loads.	Project audio config	AudioCompiler	Requires Audio Runtime enabled.
Import MIDI	button/file	Parses supported Standard MIDI format 0/1 PPQN data and appends tracker patterns/instruments.	Project audio data	Tracker/AudioCompiler	Format 2 and SMPTE timing unsupported; later tempo changes flatten to initial tempo with warning.
Import MusicXML	button/file	Parses uncompressed score-partwise MusicXML into tracker data.	Project audio data	Tracker/AudioCompiler	Compressed .mxl unsupported; quantizes to sixteenth-note rows.
Play / Stop	buttons	Runs/stops browser tracker preview.	Editor preview/audio	Tracker	Browser preview is separate from proving ROM playback.
Row / Order	status	Shows current playback cursor/order.	Editor status	Transport	No project change.
Tempo 30-300	number	Sets tracker song tempo.	Project audio data	Runtime compilation/preview	Initial tempo is authoritative for imports with unsupported tempo-map complexity.
Speed 1-15	number	Sets tracker tick/row speed.	Project audio data	Preview/runtime	Runtime compiler uses supported tracker model.
Rows 16-128	number	Sets current pattern row count.	Project audio data	Pattern editing	Changing rows can affect existing pattern structure.
+ Add Instrument	button	Creates tracker instrument.	Project audio data	Notes	Pulse duty/envelopes apply where relevant.
Instrument list	list	Selects instrument for editing.	Editor selection	Tracker notes	No data change by selection.
Instrument Name	text	Renames selected instrument.	Project audio data	Tracker UI	ID/index remains internal reference.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Duty 12.5/25/50/75%	select	Sets pulse duty waveform.	Project audio data	Pulse channels	Triangle/Noise do not use pulse duty in same way.
Volume Envelope	canvas	Click/drag edits volume envelope.	Project audio data	Instrument playback	Runtime supports bounded current instrument model.
Arpeggio Envelope	canvas	Edits pitch-offset/arpeggio envelope.	Project audio data	Instrument playback	Current runtime feature support should be checked against Audio docs.
Pattern Order grid	grid	Assigns patterns to channels for each order row.	Project audio data	Song sequence	Click channel cell to choose pattern.
+ Add Order Row	button	Extends song order sequence.	Project audio data	Music playback	Undoable.
Tracker grid	canvas/grid	Enters notes/instruments in selected channel/row.	Project audio data	Preview/runtime	Keyboard note shortcuts Z-M/Q-U; channel capacity is NES-limited.
+ Add SFX	button	Creates sound-effect definition using one pattern/channel range.	Project audio data	Animation sound events/runtime	Current runtime plays one SFX at a time on one channel.
SFX Name / ID	fields	Names effect and shows stable ID used by frame-entry sound event reference.	Project audio data	ANIM events	ID is read-only/generated.
SFX Channel	select	Chooses Pulse1/Pulse2/Triangle/Noise channel for effect.	Project audio data	Audio runtime	DPCM runtime authoring not supported here.
SFX Pattern / Start row / End row	numbers	Chooses tracker pattern segment used as effect.	Project audio data	AudioCompiler	Rows must resolve in selected pattern.
Delete SFX	button	Deletes selected sound effect.	Project audio data	Animation sound references	Can create missing references if still used.

AUDIO import/runtime limits

- MIDI: Standard MIDI format 0/1 with PPQN timing; format 2 and SMPTE timing unsupported.
- MusicXML: uncompressed `score-partwise`; compressed `.mxl` unsupported.
- Imports quantize to sixteenth-note tracker rows.
- Current arrangement capacity is three simultaneous pitched voices plus one Noise/percussion voice; unsupported excess polyphony is rejected rather than silently dropped.
- DPCM authoring/runtime and general tracker FX commands are not part of the current 1.8/1.9 runtime.

COLLISION

COLLISION assigns per-CHR tile properties. METATILES can override/compose collision per quadrant. Current generated runtimes mainly execute Empty/Solid; other authored properties are preserved for later gameplay expansion.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
0 - Empty	Active Property option	Passable tile property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
1 - Solid	Active Property option	Blocks movement in current generated collision paths.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
2 - Platform	Active Property option	Authored one-way platform property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
3 - Ladder	Active Property option	Authored ladder property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
4 - Hazard	Active Property option	Authored hazard property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
5 - Water	Active Property option	Authored water property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
6 - Slope Left	Active Property option	Authored left-slope property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
7 - Slope Right	Active Property option	Authored right-slope property.	Project tile property data	Tile Assignments / METATILES	Current generated 1.9.0 World/single-room runtime primarily executes Empty/Solid; richer traversal waits for later tranche.
Tile Assignments grid	grid	Click tile index to assign current Active Property.	Project tile property data	CHR/Scene	Per-CHR tile property; metatile quadrant collision is edited in METATILES.
Legend	reference	Shows color code for tile property types.	Editor reference	Collision view	No project change.
Stats	status	Shows counts such as Solid/Platform/Hazard tiles.	Diagnostics	Collision planning	Informational.

CODE

CODE is the custom 6502 assembly path and ROM configuration/diagnostic view. Generated World/Gameplay/Audio runtimes are separate compiler paths and should not be mixed casually with custom assembly.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Assemble (Ctrl+Enter)	button	Assembles current 6502 source using NES Forge assembler.	Build/editor output	Custom assembly mode	Errors/symbols/hex output update.
Assembly Status	status	Shows Ready/error/code size/origin information.	Diagnostics	Assembler	No project change.
Insert template...	select	Inserts/replaces editor source with selected built-in template.	Project assembly source	Code editor	May prompt before replacing nonempty source.
Minimal (vectors + loop)	template	Creates minimal boot ROM skeleton.	Project assembly source	Assembler	Intentionally no graphics/gameplay.
Scene Viewer (working engine)	template	Generates working viewer assembly for current scene count.	Project assembly source	Scene packing	Regenerate if scene count changes.
Scene Constants (generated)	template	Inserts constants for packed scene layout.	Project assembly source	Custom code referencing packed data	Constants reflect current layout conventions.
Code editor	textarea	Edits 6502 assembly source.	Project assembly source	Assembler/build	Custom assembly path conflicts with generated World Runtime/current Audio runtime modes where documented.
Errors	list	Shows assembler errors; click entries where supported to navigate.	Diagnostics	Code editor	Build cannot proceed with errors.
Symbol Table	table	Shows resolved labels/addresses after assemble.	Diagnostics	Disassembly/custom code	No project change.
Hex Output	view	Shows assembled bytes.	Diagnostics	Build	No project change.
Mapper: 0 NROM	select	Chooses current custom ROM mapper configuration.	Project ROM config	Build	Current UI only exposes mapper 0 in this path; 2.0 plans mapper-aware linker expansion.
Mirroring Vertical / Horizontal	select	Sets NROM mirroring flag for custom/viewer build.	Project ROM config	PPU nametables	Generated runtime profiles may own their own requirements.
Battery-backed SRAM	checkbox	Sets battery/SRAM header/config for custom ROM path.	Project ROM config	Custom assembly	Does not create a Gameplay save system by itself.
Pack scene data at $D000	checkbox	Controls legacy scene-packing path for custom/viewer ROM.	Project build config	Custom assembly/viewer	Generated World/Game runtimes use their own compilers/link plans.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Memory Map	view	Shows packed/custom memory layout information.	Diagnostics	Build planning	Informational.
Build Log	log	Shows build/preflight/compiler messages.	Diagnostics	All builds	Primary place to inspect why Build failed.

EMULATOR

EMULATOR runs built/imported ROMs, exposes CPU/PPU/mapper diagnostics, and provides three distinct capture modes. Build & Run is the authoritative way to test current edits.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Load ROM	button/file	Loads a .nes directly into bundled emulator.	Emulator state	Run/Disasm	Separate from Import ROM into editor project.
Run Original ROM	button	Runs preserved ROM imported through Import ROM, ignoring current editor changes.	Emulator runtime	Import ROM	Explicitly different from Build & Run.
Run / Pause	button	Starts/pauses loaded emulator ROM.	Emulator runtime	Controller input	Button label/state changes with run status.
Stop	button	Stops playback or ROM initialization.	Emulator runtime	Audio/input	Releases transient emulator activity.
Frame	button	Advances exactly one emulator frame while paused.	Emulator runtime	Debugging	Keyboard input supports manual stepping; touch/gamepad is for running play.
Reset	button	Resets loaded ROM/emulated machine.	Emulator runtime	Current ROM	Resets session-level game state.
Capture Runtime Scene	button	Captures logical PPU/nametable/attribute/mapped CHR/OAM state with provenance-aware runtime representation.	Project capture data	SCENE/CHR	Not necessarily identical to visible scrolled/rasterized frame.
Bake Visible Frame	button	Converts currently rendered visible frame into constrained static background tiles and clears sprites.	Project capture data	Static Scene	May approximate/change pixels to fit tile capacity; loses dynamic/raster behavior.
Hybrid Capture	button	Uses frame-validated background plus editable OAM sprites to avoid doubled sprites.	Project capture data	SCENE/SPRITES	Still cannot canonically rebuild every raster effect.
Capture target: New Scene	select option	Creates new Scene from capture.	Project data	Scene list	Safest default.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Capture target: Replace Current	select option	Replaces current Scene fields with capture.	Project data	Active Scene	Destructive but undo/snapshot policies may help.
Capture target: Merge Fields	select option	Merges supported captured fields into current Scene.	Project data	Active Scene	Use only when you understand which fields will be retained/replaced.
Trace 20	button	Runs/records a short emulator trace window for debugging/RE diagnostics.	Diagnostics	CPU/emulator	Not full integrated RE workspace yet.
Audio	mute toggle	Mutes/unmutes emulator audio output.	Emulator presentation	APU playback	Does not modify ROM audio data.
Performance status	status	Shows paused/running state, timing/audio health, loaded ROM info.	Diagnostics	Emulator	Not an independent hardware-accuracy claim.
Emulator screen	canvas	Displays NES output and receives keyboard controller focus.	Runtime	Input	Click/focus before using keyboard if needed.
CPU register panel A/X/Y/SP/PC/P/CYC/FRM	status	Shows current CPU state/cycle/frame counters.	Diagnostics	Debugging	Live observation only.
PPU State sidebar	status	Shows PPUCTRL/PPUMASK/PPUSTAT/VRAM address/Fine X.	Diagnostics	Capture/RE	Useful for raster/scroll investigations.
Mapper sidebar	status	Shows mapper, PRG/CHR bank state, mirroring.	Diagnostics	RE/capture	Mapper implementation is experimental/not universal compatibility reference.
Palette RAM	status	Shows live NES palette RAM.	Diagnostics	Capture	Runtime values may differ mid-frame in raster-heavy games.
OAM Summary	status	Shows live sprite/OAM activity.	Diagnostics	Capture/RE	Hardware scanline rules still apply.
Emulator Log	log	Shows load/build/run/emulator messages.	Diagnostics	Emulator	Use with Build Log to distinguish compiler vs emulator issues.

Mobile Play controls

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Play view / ▶ Play view	button	Expands the existing emulator screen and play controls within the browser viewport.	Emulator presentation	EMULATOR; a loaded ROM for play	Preserves the same ROM and running/paused state; does not rebuild, reset or automatically resume.
Play Run / Pause	button	Starts or pauses execution of the loaded ROM.	Emulator runtime	Play toolbar	Separate from NES Start; Pause releases input.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Sound on / Sound off	toggle	Enables or mutes emulator sound output.	Emulator presentation	Play toolbar; existing Audio toggle	Does not enable authored Audio Runtime or change the ROM.
Fullscreen	button	Requests browser fullscreen for the play panel.	Emulator presentation	User tap/click; browser support	If unavailable or denied, expanded viewport play stays available; browser bars may remain.
Hide touch / Show touch	toggle	Hides or shows the on-screen NES controls.	Emulator presentation/input	Play toolbar	Hiding clears touch input; initial visibility depends on pointer/viewport.
Controller	button	Opens controller selection and remapping settings.	Local input settings	Browser-exposed gamepad	Opening pauses play and clears input; Done leaves it paused until Run.
Exit to editor	button	Closes expanded Play view and returns to the editor.	Emulator presentation/input	Expanded Play view	Releases held input; does not reset, rebuild or reload the ROM.
Touch D-pad: Up / Down / Left / Right	pointer control	Sends NES directional inputs; slide within the pad to change direction or hold a diagonal.	NES controller input	Running emulator; separate fingers can hold action buttons	Opposite directions cancel; canceled/released touches clear.
Touch A	pointer control	Sends NES A while held.	NES controller input	Running emulator; workshop jump	Action depends on the loaded ROM.
Touch B	pointer control	Sends NES B while held.	NES controller input	Running emulator; workshop attack animation	Action depends on the loaded ROM; does not add combat behavior.
Touch Select	pointer control	Sends NES Select while held.	NES controller input	Running emulator	Action depends on the loaded ROM.
Touch Start	pointer control	Sends NES Start while held.	NES controller input	Running emulator; workshop restart	Separate from emulator Run/Pause.
Controller device / No controller	select	Selects one exposed physical controller or disables that source.	Local input settings	Controller settings	OS pairing/connection occurs outside Forge; reconnect requires selection again; one local port.
Map A / B / Select / Start / Up / Down / Left / Right	eight mapping buttons	Select an NES action, release all inputs, then press the desired controller button or move one axis.	Local input settings	Selected controller; paused Controller settings	Session-only mappings; a nonstandard controller starts unassigned.
Reset mapping	button	Restores standard defaults or clears bindings for a nonstandard device.	Local input settings	Controller settings	Direction remapping otherwise replaces that direction’s default stick supplement.
Cancel mapping	button	Cancels capture of the next controller input.	Local input settings	Visible during a remapping capture	Does not restore other mappings.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Done	button	Closes Controller settings.	Local input settings	Controller settings	Release buttons/sticks, then choose Run to resume.
Play/controller status	status	Reports controller availability, selection, neutral-release requirement and fullscreen fallback.	Diagnostics	Play panel	An exposed controller is not a completed hardware compatibility test.

Using touch, fullscreen and a controller

Use **Build & Run** to test current edits, **Run Original ROM** to play retained original bytes, or **Load ROM** for an existing cartridge file. They use the same emulator. Open **Play view**, choose **Run** if paused, and touch the D-pad and A/B with separate fingers. Portrait and landscape layouts are provided; there is no forced orientation lock. **Fullscreen** requests the browser's fullscreen mode; the expanded Play view remains usable if the browser declines it.

Keyboard: arrows = D-pad; Z or A = NES A; X or S = NES B; either Shift = Select; Enter = Start. Keyboard still supports paused **Frame** stepping; touch/gamepad input is sampled during running play.

Connect a compatible USB/USB-C controller or pair a Bluetooth controller through the device's operating system, then press a controller button and open **Controller**. Forge uses the controller exposed by the browser; it does not pair Bluetooth or directly open USB devices. The connector alone does not prove compatibility. If controller access is unavailable, touch and keyboard remain alternatives.

NES input	Browser-standard controller default
A	South face button, browser button 0
B	East face button, browser button 1
Select	Back/Select, button 8
Start	Start/Menu, button 9
Up / Down / Left / Right	D-pad buttons 12–15 or left-stick axes 0/1

Printed letters vary between controller brands. A nonstandard device requires mapping. Select each of the eight NES actions to remap it: release all controller buttons/sticks, then press the desired button or move one axis. **Cancel mapping** ends that capture; **Reset mapping** returns to standard defaults or an empty nonstandard mapping. Mappings last for this page session only and are not saved in a project, recovery file or ROM. After **Done**, release controls and select **Run**. The left-stick dead zone is 0.35; there is no sensitivity slider in this candidate.

Only one physical controller feeds one local NES port. A disconnect clears selection; reconnect and explicitly select it again. There is no second-player assignment, netplay, input recording or persistent controller-profile editor in this follow-up.

Input stays with the emulator

Controls feed the game only in its active emulator context. Opening controller settings pauses playback; typing in a text field, focusing a player toolbar control, and opening Save As/project/palette dialogs blocks

game input. Expanded Play view keeps focus in its own controls; an existing editor dialog returns the presentation to the editor. Editor shortcuts keep their existing context rather than becoming game commands.

Held inputs are released on Pause, focus loss, backgrounding, leaving the Emulator tab, ROM reset/replacement, settings, and entering/exiting expanded play. Cancellation/lost pointer capture also releases a touch. After an interruption, release all buttons and sticks and press anew; a controller must be observed neutral during resumed play before it acts. Opposite horizontal or vertical directions cancel. Entering/exiting Play view preserves the running/paused state and loaded ROM; it is not a reset or automatic pause/resume command.

Mobile status and performance report — September 30

The owner reports working mobile touchscreen controls and audio/video lag. Treat this as an observation of the owner's session. The exact device, OS/browser versions, delivery method, ROM, orientation and timing/FPS/audio-health readings were not recorded, so the cause and scope remain undiagnosed. Physical controller compatibility and broad mobile acceptance remain pending. The 702 automated checks are regression evidence, not a mobile smoothness or listening test.

For a useful report, keep the same ROM and note the device/OS/browser versions, local file versus hosted/embedded page, portrait/landscape, normal versus expanded/fullscreen view, time until the issue appears, and emulator performance status. Distinguish slow motion, visual stutter, delayed controls, crackling/dropouts and gradual audio/video drift. Compare the same short section once with Sound on and once off, and—if available—on desktop. Sound off changes output gain; it does not stop emulated APU/sample processing. This comparison therefore cannot prove that audio processing caused a slowdown. Comparing view or sound settings is diagnostic observation, not a performance fix. Attach the native project or an independently shareable test ROM when possible.

Capture modes are different operations

Capture	Best description
Capture Runtime Scene	Logical/provenance-aware PPU state. Best for preserving editable NES structures when representable.
Bake Visible Frame	Converts what is visible into static background tiles. Useful when exact logical structure is less important than the rendered frame.
Hybrid Capture	Frame-validated background plus editable sprites, avoiding doubled OAM sprites.

A raster-dependent scene can be captured losslessly without being statically rebuildable by the current NROM builder. NES Forge should report that distinction rather than flattening it silently.

DISASM

DISASM is a mapped PRG analysis aid, not a recovered original source tree. It is useful for inspection and for feeding experiments into CODE.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Disassembly code view	view	Shows mapped PRG disassembly for loaded/built ROM.	Diagnostics/analysis	EMULATOR ROM	Not reconstructed original source code.
Vectors NMI / RESET / IRQ	status	Shows ROM vector addresses.	Diagnostics	ROM analysis	Address meaning depends on mapper/window.
ROM Info	status	Shows loaded ROM mapper/size/context information.	Diagnostics	Disassembly	No project change.
Labels list	list	Shows discovered/generated labels.	Diagnostics	Copy ASM	Not proof of original symbolic names.
Disassemble PRG	button	Runs disassembly over current mapped PRG window/data.	Analysis output	Loaded ROM	Bank-switched whole-game reconstruction is not automatic.
Copy ASM to Code Tab	button	Copies disassembly text into CODE editor for inspection/rebuild experiments.	Project assembly source	CODE	Copied disassembly may need manual adaptation; disable scene packing as appropriate.
Download .asm	button	Exports current disassembly text using Save As/download flow.	External file	Analysis	Does not export original developer source.
Statistics	status	Shows code/data/instruction/label/subroutine counts.	Diagnostics	Disassembly	Heuristic analysis.
Hardware Registers	reference	Lists common NES hardware addresses for reading disassembly.	Reference	RE/debugging	No data change.

TECH DOCS

TECH DOCS is a read-only, release-generated capability reference. It is not saved project data.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Current capability reference	read-only document	Displays runtime-generated documentation for current release capabilities, formats, limits, and historical notes.	Reference only	All tabs	Not project data and not an editor.
Historical sections	read-only document	Retains prior-version context where useful.	Reference only	Migration/history	Current `services/documentation.js` capability section should take precedence for current behavior.

SAVING / FILE FORMATS

The most important rule is: a runnable ROM is not automatically a complete editable backup. Keep native JSON/ZIP project backups.

Control / option	Type	What it does	What it affects	Used with / notes	Current limits / gotchas
Browser Save	storage path	Complete project to IndexedDB.	Editable project	Load	Browser-local; not portable.
Portable JSON	file format	Complete editable project from Save Project As.	Editable project	Open Project	Recommended authoritative portable editable backup.
Portable ZIP	file format	project.json plus binary assets from Export.	Editable/project package	Load .zip Pack	Recommended packaged backup/share format.
Built .nes ROM	file format	Compiled executable cartridge image.	Runtime artifact	EMULATOR /Open Forge ROM	Do not assume it is a full editable backup.
World WG17 Forge ROM	generated format	World Runtime ROM that can carry embedded project source for more complete reopen.	Runtime + source envelope	Open Forge ROM	Still validate current format/support on reopen.
Single-room Forge ROM	generated format	Single-room generated ROM.	Runtime artifact	Open Forge ROM	Current reopening is partial: Gameplay Core source is not a complete embedded backup; use JSON/ZIP.
Imported original ROM	preserved bytes	Original third-party/user-supplied ROM preserved for Run Original/capture/analysis.	Imported artifact	EMULATOR /RE	Edits are not automatically applied to Run Original.

Cross-tab effect matrix

Use this section when the question is not “what does this button do?” but “if I change this, where should I expect the result?”

Source edit	Direct owner	Downstream consumers	Common confusion
BG CHR pixel	Scene CHR	SCENE, METATILES, WORLD render via tileset, builds	One tile change can affect many placements because references are shared.
Sprite CHR pixel	Scene sprite CHR	SPRITES, METASPRITES, ANIM, retained Player	Changing source art updates every frame that references it.
Metatile definition	METATILES	Linked SCENE cells, WORLD map rendering, World Runtime collision	World cells store metatile IDs; a definition edit changes all cells using that ID.
Raw SCENE cell	SCENE	Scene viewer/build source	Does not automatically repaint an already-authored World.
World map cell	WORLD	World Runtime	Does not rewrite source Scene nametable.
Room	WORLD	Gameplay Core Room placement/persistence	Room scope requires stable authored Room ID.
Entrance/Exit target	WORLD	World Runtime transitions	Both target World and marker must be valid.
Metasprite frame	METASPRITES	ANIM metasprite frames	Metasprite is one pose, not timing/state logic.

Source edit	Direct owner	Downstream consumers	Common confusion
Animation frame/event	ANIM	ENTITY STUDIO, Audio sound-event consumer where supported	Entity Studio only logs events during preview; it does not execute gameplay there.
Legacy entity binding	ENTITY STUDIO	retained Player/single-room/World Player	Not a Gameplay Core Actor Definition/Instance.
Actor Definition	GAMEPLAY CORE	every Actor Instance referencing it	Instance overrides should not mutate definition or siblings.
Actor Instance placement	GAMEPLAY CORE	Gameplay Core plan/runtime reachability	World actors outside reachable World set should not be silently omitted.
Persistent variable	GAMEPLAY CORE	behavior conditions/actions, Switch/Pickup/etc.	Runtime Actor memory is separate/transient.
Tracker/SFX	AUDIO	AudioCompiler/runtime sound events	Browser preview is not the same as built ROM playback.
Custom assembly	CODE	custom/viewer ROM path	Conflicts with generated World/Gameplay/Audio paths where docs say so.
Imported ROM	Import/Emulator	Run Original, capture, disasm	Run Original ignores editor changes.

Build, run, import, and save: which button should I use?

Goal	Use	Why
Keep a portable editable project	**Save Project As…**	Complete JSON source backup.
Package editable project + binary assets	**Export...**	Produces `.nesforge.zip`.
Save only in this browser/profile	**Save**	IndexedDB convenience.
Reopen browser save	**Load**	Reads IndexedDB list.
Open portable JSON	**Open Project**	Restores saved project source.
Compile current edits	**Build .NES ROM**	Creates cartridge image.
Compile current edits and immediately test	**Build & Run**	Builds then launches the new ROM.
Preserve/analyze an existing ROM	**Import ROM**	Adds original ROM/capture context to project.
Run imported ROM unchanged	**Run Original ROM**	Explicitly ignores editor edits.
Reopen a supported NES Forge ROM as project	**Open Forge ROM**	Uses Forge metadata/source envelope when available.
Load a ROM only into emulator	**EMULATOR > Load ROM**	Does not import it into project.

Keyboard and mouse reference

Context	Input	Action
Global/editor	Ctrl/Cmd+Z	Undo
Global/editor	Ctrl/Cmd+Shift+Z	Redo where available
Tile contexts	Ctrl/Cmd+C / Ctrl/Cmd+V	Copy / paste tile
CHR	1-4	Select pixel color index
CHR	Arrow keys	Change selected tile
SCENE	Left click/drag	Paint
SCENE	Right click	Eyedrop tile + palette / linked metatile where brush supports it
SPRITES	Drag	Move selected OAM sprite
SPRITES	Arrow keys	Nudge selected sprite
METASPRITES	Arrow keys	Nudge selected piece 1 px; Shift = 8 px
ANIM frame areas	Arrow keys	Nudge selected area; Shift = 8 px
ANIM frame areas	Delete / Backspace	Remove selected area
ANIM frame areas	Escape	Cancel drag
AUDIO	Z-M / Q-U	Enter low/high octave notes
AUDIO	Space	Play/Stop
AUDIO	Arrow keys	Navigate tracker
AUDIO	Delete	Clear note
AUDIO	Backspace	Cut note
CODE	Ctrl+Enter	Assemble
EMULATOR	Arrows	D-pad
EMULATOR	Z	NES A
EMULATOR	X	NES B
EMULATOR	Shift	Select
EMULATOR	Enter	Start
Tabs	Middle-click	Open selected view in new browser tab

Limits that are easy to misread as bugs

- **World Runtime is screen-transition based in 1.9.0.** Smooth scrolling is a later runtime-profile milestone.
- **Generic Gameplay Core rendering is not the retained multi-piece Player rendering path.** Sideview Player remains a compatibility binding in 1.9.0.
- **Gameplay Core NROM profile limit:** 12 executable Actor Instances total and 64 one-byte persistent values.

- **Switch + Door is alpha state/persistence proof, not a solid/reversible final Door.** Physical blocking is deliberately deferred.
- **Single-room Forge ROM reopening is partial.** Keep JSON/ZIP as authoritative source backup. World WG17 source-envelope recovery is more complete.
- **Collision properties beyond Empty/Solid are authorable but not generally executed by the current World/single-room profile.**
- **Audio has no DPCM authoring/runtime expansion yet.** MIDI/MusicXML imports target the canonical tracker model.
- **Entity Studio frame-entry events are previewed/logged there; the preview does not execute gameplay/damage/sound itself.**
- **Raster capture can be exact even when static NROM rebuilding is unsupported.** Captured, represented, and compilable are separate claims.
- **DISASM is analysis, not decompilation back to original developer source.**

Troubleshooting by symptom

Symptom	Check first
WORLD metatile brush says no metatiles	Open METATILES on the chosen Tileset Scene; create/analyze definitions, or use the recovery button to choose a Scene with a library.
World looks empty after creating it	A blank World is not automatically populated unless seeded from compatible Scene/metatile data; paint it with WORLD tools.
Player starts somewhere unexpected	World Runtime start uses selected Start World + Start Marker, not the Player entity Scene X/Y.
Player invisible	Verify sprite CHR -> METASPRITE -> ANIM -> ENTITY STUDIO bindings -> World Player selection.
Build says unsupported Gameplay operation	The canonical model may contain an operation not implemented by current mapper-0 profile; change behavior or wait for an authorized runtime expansion.
Pickup/hazard behaves but custom state does not	Check whether each condition/action is in current executable vocabulary and all operands/reference IDs validate.
Room variable cannot be selected	Verify Actor/variable placement really resolves to the same authored Room owner.
Door does not block	Physical blocking remains outside the documented alpha contract. The original 1.9.1 milestone reference was a historical roadmap statement, not a current delivery promise.
Door deactivates but will not reactivate immediately	Current `syncActiveFromPersistent` stops ticking after deactivation; reactivation occurs after reconstruction, not as a general reversible gate loop.
Run Original ignores my edit	Correct: Run Original intentionally runs preserved imported bytes. Use Build & Run for edits.
Open Forge ROM loses Gameplay Core in a single-room build	Current single-room ROM source recovery is partial. Open the JSON/ZIP project backup instead.
Raster-captured Scene will not build statically	Exact capture and static compilation are different capabilities; use supported static copy/conversion or preserve capture for future raster-capable runtime.
Custom assembly blocks World/Audio generated build	Save custom source separately/return to compatible generated mode; the generated runtime and custom assembly paths are distinct.

Symptom	Check first
Touch controls visible but game does not move	Load/build a ROM, choose Run, close settings/dialogs, release and press the controls again. Start is a game button, not the emulator Run command.
Controller does not appear	Connect/pair through OS settings, press a button, then choose it in Controller. Browser exposure/compatibility is not guaranteed; physical testing remains pending.
Controller stops after an interruption	Release all inputs during resumed play. After disconnect/reconnect, explicitly select the device again.
Fullscreen leaves browser bars visible	Native fullscreen may be unsupported/denied. Expanded Play view is the viewport fallback.
Mobile sound/video lags or stutters	Known owner report, not yet measured or fixed. Record device/browser, ROM, delivery mode, view/orientation, timing and audio symptoms; compare the same section with Sound on/off.

Source and verification note

The original comprehensive reference was built from the corrected Gameplay Core application/source tree. This September 30 edition retains that coverage and adds the shipped Mobile Play input/presentation controls from `src/services/emulator-input.js`, `src/services/emulator-play-ui.js` and `docs/MOBILE_PLAY.md` in the application source package. The CPU/PPU/APU, authoring, build, capture and save contracts are not expanded by this documentation update.

- Historical 1.9.0 application SHA-256: `e7c75ccd43007c46b5e0336105f6551f4b6183cc39730802cd1fba226eb7fe12`.
- Original Mobile Play source ZIP SHA-256: `aa734c7e734adea8c4821ac57ec2297d105cb1a5e9813635a0a52ad9f2f77088`.
- Preserved pre-Mobile corrected reference SHA-256: `472c4eaa427c466e204a07f0c0c30d3ecfc24c318b5ee1566dddaa2bb4903e08`; this identifies a historical reference, not the included active application.
- Packaged September 28 regression evidence: 702/702 checks across 28 suites. That existing run is not a fresh run performed by this manual update.
- September 30 owner observation: touchscreen controls work on mobile; audio/video lag reported. Physical controllers remain untested. No device/browser compatibility matrix or measured performance result has been established by that observation.
- The earlier PDF completion claim was premature. PDF production/layout checking must be reported by this review kit's actual verification record, independently from application testing.
- This documentation edition does not promote the alpha candidate or authorize 1.9.1.

Saving, recovery and diagnostics

Save the editable project, not just the cartridge

Use **Save Project As…** or **Export…** to preserve a native schema-12 project JSON/ZIP. Browser **Save / Load** uses browser storage and should not be your only backup. Recovery protects interrupted edits, but it is not a replacement for an intentional portable backup. Keep an external copy before opening another project or older build. [S1]

For a native picker, choose a destination and verify the file exists. An embedded preview may use the Save As helper/fallback. Cancel is not a successful save. The browser-download fallback uses the browser's download behavior; check its downloads UI rather than guessing where a file went.

Operation	Editable recovery boundary
Open native JSON/ZIP	Complete schema-12 authoring backup, subject to validation.
Open Forge World ROM (WG17)	Restores its checked embedded project source. A previously imported ROM is excluded from that embedded source to avoid recursive payloads.
Open single-room GP16/layout-3 ROM	Partial: scenes/art/retained legacy settings recover, but Gameplay Core source reopens disabled/empty.
Import arbitrary ROM	Append/capture/inspection path; not recovery of arbitrary original actor/map/audio formats.
Run Original	Plays preserved opened/imported bytes independently of edits.

Use **Open Forge ROM**, not append-style Import ROM, for a WG17 World cartridge. Older editors may reject schema 12 before changing their workspace; do not remove the version guard to force a downgrade.

Troubleshooting by symptom

Symptom	Check first
Empty metatile brush	WORLD's Tileset Scene must have a Metatile Library. A raw runtime capture with zero definitions is not automatically a tileset.
New World contains sample blocks	New World seeded linked source Scene cells. Detach temporary samples or erase them in WORLD.
Player not visible	Sprite-bank art, source Scene, Metasprite pieces/palette, animation frame source, entity state bindings, World Player selection.
Player starts in the wrong place	World Start marker and feet origin, not the source entity's Scene X/Y.
Start intersects solid collision	Marker cell/feet conversion, movement body dimensions, and metatile quadrant collision.
Generic actor not visible	Gameplay Core enabled, reachable World/Room placement, Render source tile/palette, pixel coordinates, runtime active state, current camera.
Behavior works in records but cannot build	Canonical operations can exceed the mapper-0 executable subset. Read the profile rejection and operands.
Door can be walked through	Expected alpha limitation. Physical blocking is deferred.
Door does not reappear after reversing its flag	Expected one-way active-state limitation until reconstruction.
Room variable does not bind	Owner/scope must match the placement contract; similar names are not identical references.
No game music	Enable Audio Runtime, inspect Pattern Order and executable channels, rebuild, enable emulator Audio.
Music import rejects	Format, polyphony, percussion overlap and timing constraints; compressed MXL is not supported.

Symptom	Check first
Raster conversion fails at a coordinate	Current static backend cannot represent that region exactly; preserve the native capture/project. The coordinate is a failed static-region check, not proof of an IRQ at that scanline.
Reopened single-room ROM lost Gameplay Core	Backend is partial recovery. Reopen the native JSON/ZIP backup instead.
World build ignores Build Scene Set	Expected: World dependencies are selected from runtime start/reachability and required source assets.
Actor count overflow	12 executable instances across the runtime plan, not 12 per screen; compatibility Player counts.
Build succeeded but original game looks unchanged	You may be playing Run Original rather than the new build.

When reporting a problem

Keep the native project and candidate application hash together. Record the tab, build mode, selected source Scene/World, exact steps, expected behavior, actual behavior and Build Log message. Distinguish a blank preview, missing source, compile rejection and wrong runtime behavior; they are different failures.

For mobile/audio/video issues, also record device model, OS and browser versions, local/hosted/embedded delivery, ROM identity, view/orientation, duration until the issue, and any emulator timing/audio-health readings. Describe slow motion, stutter, input delay, audio crackling/dropout and audio/video drift separately. The September 30 report confirms symptoms from the owner's session but contains no such measurements yet. Do not describe that lag as fixed or presume a specific cause.

Keyboard reference

Context	Keys / operation
Editor outside text fields	Ctrl/Cmd+Z Undo; Ctrl/Cmd+Shift+Z Redo; tile Copy/Paste where the active editor supports it.
Text fields	Normal text editing shortcuts remain text editing, not arbitrary canvas actions.
Scene	Left-drag paint; right-click sample. Metatile brush changes the painting unit to 16×16.
World	Tool-specific pointer editing; selected-region Copy/Paste/Clear. Verify the tool before dragging.
CHR	Select palette pixel values with 1–4; arrows navigate tiles where handled by the CHR editor.
Tracker	Z–M / Q–U piano entry, arrows navigate, Delete clear, Backspace cut, Space play/stop in the tracker context.
Emulator	Arrows = D-pad; Z or A = NES A; X or S = NES B; either Shift = Select; Enter = Start. Touch/gamepad is active during running play; keyboard also supports paused Frame stepping.

The same physical key has different meanings in a focused tracker, text field and emulator. Input is released when leaving the relevant playback context; do not assume held keys follow you between tabs.

A practical acceptance checklist

After completing the workshop, save a native project and reopen it. Verify the tileset and map still match, the Player has the required state bindings, World Runtime references remain explicit, and Build & Run still creates the intended game. Then test a Room/World actor, a persistent pickup, the alpha switch state, and enabled runtime music separately.

Try one older native project only after backing it up. Exercise Save As and Runtime Capture in your actual browser. Inspect source recovery using a copy of a World ROM, while retaining the native backup. Record anything unverified rather than treating a generated test total as a manual usability pass.

For Play view, check portrait/landscape, simultaneous D-pad plus A/B, Show/Hide touch, native fullscreen or its fallback, and return to the editor. Confirm typing, Save As, other authoring tabs and controller settings do not also send game input. Background/refocus the page and confirm held inputs release. When controller hardware is available, test actual connection, all eight inputs, remapping, disconnect/reconnect and resume independently for each device/browser combination. Record the mobile performance report as open until a measured reproduction and bounded correction have been verified.

Do not treat the graph editor, projectiles, ladders, moving platforms, checkpoints, solid/reversible Doors, RE integration, smooth scrolling, LiveLink or hosted networking as completed 1.9.0 features. **Current update:** alpha.11 does include the bounded RE/recovery workflows and MIDI/MusicXML score exporters described in the current supplement; the historical list is not a current alpha.11 feature inventory.

Sources and verification status

This edition preserves the comprehensive reference and saved blank-project tutorial, updated against the delivered Mobile Play application/source package. Source paths below refer to `NES_Forge_1.9.0/` inside Developer/NES_Forge_1.9.0_Alpha_Mobile_Play_Candidate.zip. It uses the existing authoring controls and generated-profile contracts; it does not supply a prebuilt example in place of the workshop.

- **S1:** Reference/Release_Docs/CURRENT_GUIDE.md; current application authoring/build/recovery guide, copied from the candidate source package.
- **S2:** Reference/Release_Docs/WORLD_RUNTIME.md; retained World backend reference with historical headings and later updates.
- **S3:** Reference/Release_Docs/AUDIO_RUNTIME.md; tracker/runtime/import and SFX contracts.
- **S4:** Application source package `src/gameplay/gameplay-ui.js`, `gameplay-model.js`, `gameplay-compiler.js`, `gameplay-engine.js`; typed control labels, schemas and profile limits.
- **S5:** Application source package `src/services/documentation.js` and retained editor modules; tab and capture behavior.
- **S6:** Reference/Historical/From_Scratch_Tutorial_1.7.md; historical terrain/retained-Player workshop adapted here for the current Audio/Gameplay/recovery boundaries.
- **S7:** Reference/Release_Docs/MOBILE_PLAY.md, plus application source `src/services/emulator-input.js` and `src/services/emulator-play-ui.js`; current local input, presentation, mapping and interruption contracts. The copied release document retains its September 28 status; the September 30 owner report and documentation status in this manual supersede that historical status.
- **S8:** Delivered September 28 `test-results/candidate/Summary.json` and clean-extraction evidence: 702/702 automated checks across 28 suites for the historical 1.9.0 application hash. This existing evidence is not a new test run performed during documentation work.
- **S9:** Owner report in this conversation, September 30: mobile touchscreen controls work; mobile audio/video lags; physical controller hardware remains untested. Exact device/browser/ROM and timing information was not supplied.

Historical application statement: The original September 30 kit contained the Mobile Play candidate with SHA-256 `e7c75ccd43007c46b5e0336105f6551f4b6183cc39730802cd1fba226eb7fe12`. That is not the active application in this alpha.11 kit. Documentation/package assembly does not change emulator behavior. No fresh full browser replay of this workshop, audible listening pass, physical-controller test, mobile performance fix or candidate acceptance is claimed by this manual update.

An earlier manual said the PDF had been rendered and inspected before that work was complete. That statement is corrected here: PDF output and layout inspection are separate deliverables, whose completion is recorded in the review kit's verification record. Historical source documents retain their original dates and claims; they must not be read as fresh results for this review kit.