

Starter Edition Version 3.9

Notices



# **Important Information**Notices

#### **Topics:**

This section contains document notices.

- Legal Notices
- Document Information
- Service Support

▶ Notices



## Legal Notices

© 2018 HERE Global B.V. and its Affiliate(s). All rights reserved.

This material, including documentation and any related computer programs, is protected by copyright controlled by HERE. All rights are reserved. Copying, including reproducing, storing, adapting or translating, any or all of this material requires the prior written consent of HERE. This material also contains confidential information, which may not be disclosed to others without the prior written consent of HERE.

## **Trademark Acknowledgements**

HERE is trademark or registered trademark of HERE Global B.V.

Other product and company names mentioned herein may be trademarks or trade names of their respective owners.

#### **Disclaimer**

This content is provided "as-is" and without warranties of any kind, either express or implied, including, but not limited to, the implied warranties of merchantability, fitness for a particular purpose, satisfactory quality and non-infringement. HERE does not warrant that the content is error free and HERE does not warrant or make any representations regarding the quality, correctness, accuracy, or reliability of the content. You should therefore verify any information contained in the content before acting on it.

To the furthest extent permitted by law, under no circumstances, including without limitation the negligence of HERE, shall HERE be liable for any damages, including, without limitation, direct, special, indirect, punitive, consequential, exemplary and/or incidental damages that result from the use or application of this content, even if HERE or an authorized representative has been advised of the possibility of such damages.



## **Document Information**

Product		
Name:	HERE iOS SDK	
Version:	Starter Edition Version 3.9	
Document		
Name:	HERE iOS SDK Developer's Guide	
ID:	3eb329b-1538410270-f5a1ee71	
Status:	FINAL	
Date:	2018-Oct-01, 16:12 (GMT)	

## Service Support

If you need assistance with this or any other HERE product, select one of the following options.

- If you have a HERE representative, contact them when you have questions/issues.
- If you manage your applications and accounts through *developer.here.com*, log into your account and check the pages on the SLA report or API Health. If this does not clarify the issue, then check *stackoverflow.com/questions/tagged/here-api*.
- If you have an evaluation plan, check stackoverflow.com/questions/tagged/here-api.
- If you have questions about billing or your account, Contact Us.
- If you have purchased your plan/product from a HERE reseller, contact your reseller.



## **Contents**

Chapter 1: Overview	7
What is the HERE iOS SDK?	8
Feature List	8
Legal Requirements	8
Chapter 2: Quick Start	10
Run the Sample Application	11
Create a Simple App Using the HERE SDK	12
Chapter 3: User Guide	19
System Requirements	20
Authenticating Applications	20
Examples on GitHub	21
App Submission Requirements	21
Mapping	22
Maps	22
Gestures	24
Map Schemes	26
Objects and Interaction	28
Custom Raster Tiles	31
Positioning	35
Basic positioning	35
Directions	38
Route Calculation	39
Search	43
Geocoding and Reverse Geocoding	43
Search and Discovery	46
Offline Search	53
Chapter 4: Supplemental Information	55
Crosto a Simple HEDE SDK App Using Swift	56

## HERE iOS SDK Developer's Guide ▶ Contents

reve	,

Chapter 5: Coverage Information6
Supported Tiffedd Osage
Supported Thread Usage
Swift Support in HERE SDK

► Overview



## Chapter 1 Overview

## **Topics:**

- What is the HERE iOS SDK?
- Feature List
- Legal Requirements

The articles that follow introduce the HERE iOS SDK, explain essential concepts, and describe the common use cases it supports.



## What is the HERE iOS SDK?

The HERE iOS SDK provides a set of programming interfaces that enable developers to build immersive, geographically-aware iOS applications by leveraging a powerful and flexible mapping platform. Through this SDK, developers can add rich location features such as routing, interactive maps, and global place search to their applications. The powerful client-side HERE iOS SDK also includes a sophisticated engine for rendering map data and calculated routes.

## Feature List

The main features offered by the HERE iOS SDK are listed below.

## **Mapping:**

- Raster map tiles with high resolution support
- · Map styles: Normal, Satellite, Terrain, and more
- · Touch gestures such as tap, pan, and pinch
- · Overlay objects on the map such as polylines, polygons, icons, routes

#### **Search:**

- Search through a broad set of geographical content across the globe (including streets, address points, and categorized places)
- Search Places for somewhere specific or explore by categories
- Access rich details for a Point of Interest from third-party content sources (including images, ratings, reviews, and editorials)
- Perform geocoding and reverse geocoding lookups

#### **Directions:**

- Online Car and Pedestrian Route Directions
- Specify preferred route type (fastest or shortest) and route options (such as avoiding toll roads, motorways, and parks)
- · Alternate routes

## Legal Requirements

In addition to the applicable *terms and conditions* under which you have licensed the SDK, the following shall apply.

Components of the HERE SDK collect certain information from your application. Such information includes access credentials (App\_Id and App\_Code – see also *Authenticating Applications* on page 20) and the types of features utilized by your application when used by end users. The information does not identify an individual end user. However, your application's privacy policy must disclose to the end users that you have

► Overview



licensed products and services from HERE and that such information is collected from your application as it is being used by end users and that HERE collects and processes such information from the application.

Ouick Start



## **Chapter 2**Quick Start

#### **Topics:**

- Run the Sample Application
- Create a Simple App Using ...

This section provides information to help you start using the HERE iOS SDK.

#### Obtain the SDK via CocoaPods

You can obtain the HERE iOS SDK via CocoaPods. For more information, see *Run the Sample Application* on page 11.

#### Obtain the SDK via the Download Method

To obtain the HERE iOS SDK, follow these steps:

- 1. Visit developer.here.com and click on Get Started for Free.
- 2. Register or sign in to your HERE Account.
- 3. Agree to the HERE Terms and Conditions.
- 4. On the Platform Activiation screen, find the section for HERE iOS SDK Starter Edition and click on Generate App ID and App Code to obtain your app credentials and the SDK download link.
- 5. Follow the link to download the HERE iOS SDK as a Zip package.

After you have downloaded and extracted the Zip package, follow one of the next tutorials to begin using the SDK.

Ouick Start



## Run the Sample Application

This tutorial provides instructions on how to run the Objective-C and Swift sample applications to render a map on an iOS device. The tutorial assumes you are using Xcode 10 and the iOS 12 SDK. For more details, see *System Requirements* on page 20.

Tasks for this basic application include:

- Acquire HERE Credentials.
- Launch the sample project using CocoaPods or manually from the package.

## **Acquire HERE SDK Credentials**

Before working with with HERE SDK, you need to acquire a set of credentials by registering your application on <a href="http://developer.here.com">http://developer.here.com</a>. Each application requires a unique set of credentials.

## **Launch the Project Using Cocoapods**

You can start trying a sample HERE iOS SDK project by using Cocoapods. CocoaPods is an open source dependency manager for Objective-C and Swift Xcode projects. To get started with using CocoaPods on macOS, follow the instructions in the *Getting Started* guide on CocoaPods.org.

Once you have configured CocoaPods in your development environment, try the tutorial project by using the following command.

pod try HEREMapsStarter

■ **Note:** This command is only intended for product demonstration purposes. It only puts the HERE SDK in a tempoary location. For more information on using CocoaPods in a Xcode project, see *Create a Simple App Using the HERE SDK* on page 12.

After invoking this command, you are prompted to choose between an Objective-C or a Swift sample project. Make a selection, and the script opens a project in Xcode, with HERE SDK dependencies already configured. You can then follow the instructions in the project README.txt to add app credentials and run the app.

App credential strings are located in the HelloMapAppDelegate.m file with the following labels:

- kHelloMapAppID
- kHelloMapAppCode
- kHelloMapLicenseKey

#### Launch the Project from the Downloaded HERE iOS SDK Package

You can also open a sample project from the HERE iOS SDK package, which you can download from <a href="http://developer.here.com">http://developer.here.com</a>. The Xcode projects are available in the sample-apps folder. To run the project, double-click on HelloMap.xcodeproj or SwiftHelloMap.xcodeproj, then follow the instructions in the README.txt file.

▶ Ouick Start



## Create a Simple App Using the HERE SDK

This guide provides instructions on creating a simple HERE iOS SDK application to render a map on an iOS device. Users are able to navigate the map by way of touch gestures such as panning, rotating, tilting, and pinching. The contents of this guide apply to Xcode 10 and the iOS 12 SDK.

This tutorial applies to development using Objective-C. For information on how to perform the same tasks using Swift, see *Create a Simple HERE SDK App Using Swift* on page 56.

Note: The HERE iOS SDK is now distributed as a dynamic framework instead of a static library. Please review the following steps and update your Xcode project configuration if you are upgrading from an older versions of the HERE SDK. Also, ensure you first remove the old NMAKit.framework, NMABundle.bundle, and linked libraries from your Xcode project, before you add the new dynamic framework.

## **Acquire HERE SDK Credentials**

Before working with with HERE SDK, you need to acquire a set of credentials by registering your application on <a href="http://developer.here.com">http://developer.here.com</a>. Each application requires a unique set of credentials.

## **Create a New Single View Application**

- From XCode menu, select File > New > Project to open the New project dialog (or press Shift + Command + N).
- 2. Select iOS > Application > Single View Application as the application type you want to create. Press Next.
- In the next dialog, enter your Product Name (such as HelloMap) and Organization Identifier (such as edu.self).
- **4.** Next, choose "Objective-C" under **Language**, then click **Next**. Navigate to the directory where you want your project to be stored and then select **Create**.
- 5. The next step is to configure this project to use the HERE SDK.

#### **Add HERE iOS SDK**

The are two ways to add the HERE iOS SDK to your Xcode project:

- CocoaPods
- · Manually import the dynamic framework

To use CocoaPods to import the HERE SDK:

1. Create a Podfile in your project and add the following. Replace YourApp with your project name.

```
platform :ios, '9.0'
target 'YourApp' do
pod 'HEREMapsStarter'
end
```

2. Next, open a command-line terminal on your workstation. From your project's root folder, run this command:

```
pod install
```

► Quick Start



Alternatively, to manually import the HERE SDK dynamic framework:


- **1.** Download the HERE iOS SDK package from http://developer.here.com and extract it to somewhere in your local file system.
- 2. Add the NMAKit dynamic framework to your Xcode project. Click on your app target and choose the "General" tab. Find the section called "Embedded Binaries", click the plus (+) sign, and then click the "Add Other" button. From the file dialog box, select the "NMAKit.framework" folder. Ensure that the "Copy items if needed" and "Create folder reference" options are selected, then click Finish.

Figure 1: Adding NMAKit.framework

Choose options for adding these files:				
Destination: ✓ Copy items if needed				
Added folders: Create groups  • Create folder reference	es			

Ensure that NMAKit.framework appears in the "Embedded Binaries" and the "Linked Frameworks and Libraries" sections.

**Figure 2: Added Embedded Binaries** 




▶ Quick Start



#### Verify and Run the App

Next, ensure that modules are enabled. Click on the "Build Settings" tab and navigate to the "Apple LLVM 9.0 - Language" - Modules section. Ensure that the "Enable Modules (C and Objective-C)" has the value "YES".

Figure 3: Enable Modules



- 2. Run the application. From the Xcode menu bar, select **Product** > **Run**. Ensure that the project runs in the iOS Simulator without errors.
- 3. The HERE iOS SDK is now ready for use in your Xcode project. Now that you have your project configured to work with the HERE SDK, try extending the sample application to render a map.

## **Create the Map View**

In this section, we utilize the NMAMapView and NMAGeoCoordinates classes to render a Map.


- 1. Create an NMAMapView.
  - a. Select Main.storyboard in the navigator, then open the Utilities view by pressing the key combination Command + Option + Control + 3. Drag and drop a View object from the Object Library onto the View Controller. If necessary, resize the View so it takes up the entire viewable area.
  - **b.** In the Interface Builder, click on the created View and then open the Identity Inspector in the Utilities view by pressing the key combination Command + Option + 3. Change the class value from

► Quick Start



UIView to NMAMapView and press return. In the Document Outline, you should see that the name of the View has changed from to *View* to *Map View*.

#### Figure 4: MapView



- Create an outlet to NMAMapView in ViewController.
  - a. Select Main.storyboard in the navigator.
  - **b.** Press Command + Option + Return to open the Assistant Editor. It should show *ViewController.m.*
  - **c.** Add the following import statement to the top of this file:

@import NMAKit;


**d.** Hold the Control key on the keyboard and click to drag from the Map View to the interface block in *ViewController.m*. You should see a blue line and tooltip which says "Insert Outlet or Outlet Connection". Release the mouse button and a dialog appears, allowing you to create an outlet.

▶ Quick Start



e. Name the outlet mapView, keep the other default options and then select Connect.

Figure 5: Create an Outlet



3. Now an outlet to NMAMapView is set. The modified file should be as follows:

```
#import "HelloMapViewController.h"
@import NMAKit;
@interface HelloMapViewController ()
@property (weak, nonatomic) IBOutlet NMAMapView *mapView;
@end
@implementation HelloMapViewController
- (void)viewDidLoad
{
   [super viewDidLoad];
}
- (void)didReceiveMemoryWarning
{
   [super didReceiveMemoryWarning];
}
@end
```

4. Implement NMAMapView setup and lifecycle code by modifying the viewDidLoad method as shown:

```
- (void)viewDidLoad
{
[super viewDidLoad];
```

► Quick Start



```
//set geo center
NMAGeoCoordinates *geoCoordCenter =
  [[NMAGeoCoordinates alloc] initWithLatitude:49.260327 longitude:-123.115025];
[self.mapView setGeoCenter:geoCoordCenter withAnimation:NMAMapAnimationNone];
self.mapView.copyrightLogoPosition = NMALayoutPositionBottomCenter;

//set zoom level
self.mapView.zoomLevel = 13.2;
}
```

- 5. Add your HERE application credentials.
  - **a.** Open AppDelegate.m and import NMAKit by adding the following import statement to the top of the file

```
@import NMAKit;
```

**b.** Add the following in the didFinishLaunchingWithOptions method, replacing YOUR\_APP\_ID and YOUR\_APP\_CODE with the credentials that you received from <a href="http://developer.here.com">http://developer.here.com</a>.


```
[NMAApplicationContext setAppId:@"{YOUR_APP_ID}"
    appCode:@"{YOUR_APP_CODE}"];
```

► Quick Start



6. Build and run the application. If the build is successful, you now have an application that displays a map similar to the following screenshot and allows you to manipulate it using gestures.

Figure 6: Running the App



User Guide



## **Chapter 3**User Guide

#### **Topics:**

- System Requirements
- Authenticating Application...
- Examples on GitHub
- App Submission Requirement...
- Mapping
- Positioning
- Directions
- Search

The articles in this section provide a guide to using the HERE iOS SDK.

User Guide



## System Requirements

- HERE SDK supports iOS 11 or above. iOS 12 is recommended for optimal operation.
- HERE iOS SDK is designed and tested for use with iOS phones and tablets. Supported devices are:
  - iPhone 5 or newer
  - iPad 3 or newer
  - iPad Mini 2 or newer
  - Note: While the HERE iOS SDK supports both 32-bit and 64-bit devices, iOS 11 or newer is 64-bit only, and only these devices are supported:
    - iPhone 5s or newer
    - iPad Air or newer, including iPad (2017) and iPad Pro
    - iPad Mini 2 or newer
- Apps should be developed using XCode 10 or above, running on macOS 10.13.6 or above
- A minimum of 3.5MB per application should be made available for the storage of the HERE SDK libraries
- A minimum of 32MB should be made available for the storage of map data.
- Data connectivity (WiFi or Cellular) is required to download map data.

## **Authenticating Applications**

Developers using the HERE SDK with their app are required to register for a set of HERE credentials, and to specify these credentials (App\_Id and App\_Code) in their application. Failure to do so results in blocked access to certain features and degradation in the quality of other services.

To obtain these credentials, visit the developer portal at <a href="https://developer.here.com/plans">https://developer.here.com/plans</a> and register for a license. Once your project is created, you can generate these credentials on your Project Details page. If you already have a plan, you can also retrieve these credentials from your Project Details page.

Note: Credentials are unique to your application. Do not reuse credentials across multiple applications.

## **Adding Credentials**

Ensure that you have provided the app\_id and app\_code before using the HERE SDK. For example, set them in your app delegate:

```
- (BOOL)application:(UIApplication *)application
didFinishLaunchingWithOptions:(NSDictionary *)launchOptions
{
  [NMAApplicationContext setAppId:@"{YOUR_APP_ID}" appCode:@"{YOUR_APP_CODE}"];
  return YES;
}
```

User Guide



## Examples on GitHub

You can find more HERE SDK sample projects on GitHub: https://www.github.com/heremaps


## App Submission Requirements

This section contains important information on how to prepare your HERE iOS SDK-enabled app for App Store submission. Be sure to follow the advice here to avoid store rejections caused by the HERE SDK.

#### **Remove Simulator Architectures**

Apple rejects apps that are submitted to the App Store with simulator-specific architectures (x86\_64, i386). Similarly, Xcode also gives an error if you try to export these apps for other types of deployment. Prior to exporting your app, you must strip simulator-specific architectures from the NMAKit framework binary and rebuild your app.

Figure 7: Exporting According to Deployment Type



A script is provided with the HERE SDK to strip the simulator architectures from the NMAKit library. Before you build your app to upload to the store, make a copy of NMAKit.framework and run the script to create a framework that only contains ARM device architectures (arm64, armv7). This modified version of the framework should be included in any builds destined for the app store.

This script is located at the following location:

{SDK Root}/framework/strip\_sim.sh

▶ User Guide



To run the script, open a terminal and go to the directory containing the script and execute it from there.

You can also add a script as part of your Xcode build process to automatically strip unnecessary architectures from frameworks. Depending on your build environment, this may work better than managing separate versions of NMAKit.framework. For more details about this solution, see *this article on Stack Overflow*.

#### **Declare Private Data Access**

Starting with iOS 10, you must statically declare access to private user data, such as address book and device location, before submitting your app to the App Store. Each declaration requires adding a key and a purpose string in your app's Info.plist file.

The following shows the required HERE iOS SDK data access declarations. You can use the recommended <string> entries in your app's Info.plist, or you can choose strings that are appropriate to your app.

Note: All HERE iOS SDK apps must have these declaration entries for the App Store submission process. App users are only prompted for the appropriate data access if your app uses the relevant HERE SDK feature.

```
<key>NSLocationWhenInUseUsageDescription</key>
<string>This is needed to determine your current location</string>
```

You can find more information about these keys in the following article: https://developer.apple.com/library/content/documentation/General/Reference/InfoPlistKeyReference/Articles/CocoaKeys.html.

## Mapping

## Maps

The core feature of the HERE iOS SDK is Mapping. The key concepts covered in this section include adding a map to an iOS application, changing the location displayed by the map, and modifying its properties. The primary component of the mapping API is the NMAMapView, which is integrated with the Cocoa Touch framework as a UIView subclass. NMAMapView represents the view to display map and various properties. The NMAMapView is derived from UIView and part of iOS Cocoa Touch framework.

Note: To create a simple map application, refer to the *Quick Start* section.

The first step to integrate a map into an application is to insert a NMAMapView to your view controller's .xib file or the storyboard of the application using the Interface Builder. Alternatively, you can also add NMAMapView to your view controller programmatically as follows:

```
- (void)viewDidLoad
{
  mapView = [[NMAMapView alloc] initWithFrame:self.view.frame];
  [self.view addSubview:mapView];
}
```

The NMAMapView class handles all user interactions in the form of touch gestures. More details about the supported gesture types can be found in the *Map Gestures* section.

▶ User Guide



#### **Working with NMAMapView**

Once the NMAMapView is initialized, it can be manipulated and interacted in a variety of ways. Some key attributes of the NMAMapView are its geographical center (geoCenter) and zoom level (zoomLevel). These properties may be used to customize the NMAMapView display. For example, the following code demonstrates how to show a view of Vancouver, Canada.

```
NMAGeoCoordinates *geoCoordCenter = [[NMAGeoCoordinates alloc]
  initWithLatitude:49.260327 longitude:-123.115025];
[self.mapView setGeoCenter:geoCoordCenter withAnimation:NMAMapAnimationNone];
```

In the preceding code:

- The geographical location [NMAGeoCoordinates] for the new map center is created by a call to the -(id)initWithLatitude:(double)aLatitude longitude:(double)aLongitude method.
- When setting the center of a map, the transition can be animated by passing the NMAMapAnimationLinear enum value to the animation parameter. Animation can also be suppressed by using the NMAMapAnimationNone value.

The beginning and ending of these events may be observed by assigning an object to the NMAMapView's delegate property. The object should implement the methods of the NMAMapViewDelegate protocol corresponding to the events you wish it to receive. This delegate can also be used to detect *map object selection*.

Note: For optimum performance, avoid resizing a map after it has been created. If resizing is necessary, create the map at the largest size to be used and reduce it later.

#### **Resolution and Text Size**

By default, the HERE SDK uses high-resolution (512 x 512 pixels) map tiles. You can set the useHighResolutionMap property in NMAMapView to NO to use lower-resolution (256 x 256 pixels) map tiles instead.

You can also use the mapPPI property to change the map's pixel-per-inch setting. The default setting is NMAMapPPILow. Setting the property to NMAMapPPIHigh makes street labels and other text to be bigger.

#### **Properties of NMAMapView**

The following examples show how to work with some of the properties in NMAMapView:

#### **Map Center**

The center of the map determines the geographical area to be displayed. It can be read using the NMAMapView geoCenter property, and set using one of the setGeoCenter: methods. Its type is NMAGeoCoordinates.

```
// Move the map to London.
NMAGeoCoordinates *geoCoordCenter = [[NMAGeoCoordinates alloc]
initWithLatitude:51.51 longitude:-0.11];
[self.mapView setGeoCenter:geoCoordCenter withAnimation:NMAMapAnimationNone];
```

#### **Zoom Level**

▶ User Guide



The size of the geographical area displayed by the map can be controlled by changing the zoom level. The zoom level ranges from NMAMapViewMinimumZoomLevel to NMAMapViewMaximumZoomLevel, with a higher zoom value being closer to the ground. The following code sets the zoom level to the median zoom level:

```
// Set the zoom level to the median.
mapView.zoomLevel =
(NMAMapViewMinimumZoomLevel + NMAMapViewMaximumZoomLevel)/2.0f;
```

#### **Animations**

The NMAMapView supports the following animation settings to be used while changing properties, defined by the NMAMapAnimation enum:

- NMAMapAnimationNone
- NMAMapAnimationLinear

```
// Move to London using bow animation
NMAGeoCoordinates *geoCoordCenter = [[NMAGeoCoordinates alloc]
  initWithLatitude:51.51 longitude:-0.11];
[mapView setGeoCenter:geoCoordCenter withAnimation:NMAMapAnimationLinear];
```

#### **Setting Multiple Attributes**

An extended API is provided to change one or more attributes at the same time.

```
-(void) setGeoCenter:(NMAGeoCoordinates*) coordinates
    zoomLevel:(float) level
    withAnimation:(NMAMapAnimation) animation
```

To leave a map attribute unchanged, pass the NMAMapViewPreserveValue constant to the relevant method parameter.

```
// Move to Vancouver, preserving zoom level
NMAGeoCoordinates* coord = [[NMAGeoCoordinates alloc]
  initWithLatitude:49.0
  longitude:123.0];
[mapView setGeoCenter:coord
  zoomLevel:NMAMapViewPreserveValue
  withAnimation:NMAMapAnimationNone];
```

For more information about the APIs introduced and demonstrated in this section, refer to the API Reference documentation.

## Map Gestures

The NMAMapView class responds to a number of predefined touch gestures. The default behavior of the map for each gesture type may be used as-is, supplemented, or replaced entirely. The following table is a summary of the available gestures and their default behavior.

► User Guide





To select a visible map object, tap the screen with one finger.



**To zoom the map in a fixed amount,** tap the screen twice with one finger. Tap continuously to make a continuous zoom.



To zoom out a fixed amount, tap the screen with two fingers. Tap continuously to make a continuous zoom.



To move the map, press and hold one finger to the screen, and move it in any direction.



Press and hold two fingers to the screen and move them in the same direction. This gesture does not have a predefined map action.



To pan the map with momentum, press and swipe one finger on the screen. The map continues to move in the same direction, and gradually slow to a stop.



**To continuously zoom in or out,** press and hold two fingers to the screen, and increase or decrease the distance between them.



Pressing and holding one finger to the screen activates the long press gesture. This gesture does not have a predefined map action.

The time required to trigger a long press gesture can be customized using the NMAMapView longPressDuration property. The default value for this property is one second.

▶ User Guide



#### Controlling the NMAMapView Gesture Response

Any of the gestures listed above may be selectively enabled or disabled on an NMAMapView instance using the enableMapGestures: and disableMapGestures: methods. These methods take a single input parameter that is an "or" combination of NMAMapGestureType values, which are defined in NMAMapGesture.h. The state of a specific gesture may be checked with isMapGestureEnabled:.

The following code shows how to disable all panning gestures:

```
// mapView is a valid NMAMapView instance
[mapView disableMapGestures:NMAMapGestureTypePan];
```

## **Gesture Delegation**

To receive notifications of gestures, you can implement the NMAMapGestureDelegate and use the corresponding handler methods. For example:

```
@implementation MyGestureDelegate
// ...
-(void)mapView:(NMAMapView*)mapView didReceiveTapAtLocation:(CGPoint)location
{
    // a gesture was received
    // location is available through the "location" parameter
}
@end
```

Note: Implementing the handler method does not have any impact on how the map responds to the gesture. For example, the logic within mapView:didReceiveDoubleTapAtLocation: is called when the map has zoomed in.

## Map Schemes

Specific map schemes are available to offer your application users a choice among different kinds of map appearance.

## **Setting the Scheme**

The NMAMapScheme.h file defines schemes that the HERE map service supports. You can set a desired scheme by changing the mapScheme property of NMAMapView. For example:

```
mapView.mapScheme = NMAMapSchemeNormalDay;
```

▶ User Guide



## **Examples of Map Schemes**

All available schemes are defined as constant strings in the NMAMapScheme.h file. The string values that your application can use to set a map scheme include:

Figure 8: NMAMapSchemeNormalDay




Figure 9: NMAMapSchemeSatelliteDay



Figure 10: NMAMapSchemeHybridDay



Figure 11: NMAMapSchemeNormalNight





Figure 12: NMAMapSchemeTerrainDay




Figure 13: NMAMapSchemeReducedDay





Figure 14: NMAMapSchemeReducedNight



## Objects and Interaction

The HERE SDK allows the addition of a variety of objects, each with a specific purpose, to a map view. The types of available object include map markers, routes, polylines, and overlays. These objects are described in more detail below.

## The NMAMapObject Class

The NMAMapObject class provides a generic base class from which most types of specialized map object inherit. Functionality that is common to all these object types is encapsulated in NMAMapObject. The following is a list of the important properties and methods in NMAMapObject.

► User Guide



- zIndex determines the objects stacking order, which controls how the object is displayed on the map relative to other objects that may overlap it
- visible determines whether or not the object is drawn when the map is rendered
- type contains the type of the map object, such as marker, polyline, and route. For the full list, see the NMAMapObject API reference.
- parent the NMAMapContainer instance holding this object, if any
- uniqueId uniquely identifies the object for the duration of the application launch

#### ■ Note:

- NMAMapObject serves as a base class to other map object types and should not be instantiated directly.
- Any change in a map object's visual appearance causes the entire map view to be redrawn, since
  map objects are drawn as part of the map itself. For optimal performance, map objects should
  not be frequently updated unless it is necessary.

## The NMAMapContainer class

Map containers are a special type of map object that can be used to group together other map objects of certain types. The types of object allowed are NMAMapMarker, NMAMapCircle, NMAMapPolygon, and NMAMapPolyline. Containers provide a convenient way to control the stacking order and visibility of a large group of objects.

To use a map container, create one or more map objects and add them to the container using the addMapObject method. To show the objects on a map, add the map container to the map with the addMapObject method of NMAMapView.

Note: A container may also hold other instances of NMAMapContainer.

#### The NMAMapCircle class

An NMAMapCircle class is used to draw a circle on the map at a fixed geographical location; custom border and fill colors may be defined.

Figure 15: A MapCircle object




► User Guide



## The NMAMapPolyline class

The NMAMapPolyline class is used to draw one or more connected line segments on the map. The segment vertices are specified by a series of NMAGeoCoordinates. The visual appearance of the polyline can be customized.

Figure 16: A MapPolyline object



## The NMAMapPolygon interface

The NMAMapPolygon class is similar to NMAMapPolyline, but the first and last points of the line are automatically joined to create a closed shape. Polygon objects can have different border and fill colors.

Figure 17: A MapPolygon object with transparent fill and a border



Note: Polygons that have a path that crosses over itelf are not supported. For example, it is not possible to create a "bowtie" shape using four line segments, where one line segment crosses over another. However, you can create the shape using two triangles.


▶ User Guide



### The NMAMapMarker class

The NMAMapMarker class is used to display a custom icon at a fixed geographical position on the map. Custom icons can be provided as an UIImage.

Figure 18: A NMAMapMarker object



You can set NMAMapMarker to be draggable by setting the draggable property to YES. To listen for drag events, such as marker position changes, use the respondToEvents:withBlock: method in NMAMapView.

## **Map Object Selection**

All user-defined objects with a visual representation can be selected. Selection occurs when a visible object on the map is tapped. By default, the map does not take any action when objects are selected. To implement selection handling, a custom class must implement the NMAMapViewDelegate protocol and its onMapObjectsSelected method. The onMapObjectsSelected callback returns an array that contains instances of NMAViewObject, which is a superclass of NMAMapObject.

Object selection can also be programmatically invoked by using the objectsAtPoint: or visibleObjectsAtPoint: method. Each of these methods takes a CGPoint screen coordinate and returns an NSArray of NMAMapObject at that location. The visibleObjectsAtPoint method does not return any object that has the visible property set as NO.

For more information, see the NMAMapView API documentation.

## **Custom Raster Tiles**

You can use the HERE iOS SDK to enhance maps with the custom raster tiles API — NMAMapTileLayer.

Custom raster tiles are tile images that you can add to a map for enhancing the map with extra information over a large geographical area. If the application is set to display custom raster tiles, then users see them whenever they view a designated geographical area at a specified zoom level or range of zoom levels.

You can provide tile images in two ways:

▶ User Guide



- Store custom raster tile images on a remote server and return URLs via the NMAMapTileLayerDataSource mapTileLayer:urlForTileAtX:y:zoomLevel: protocol method.
- Provide raw bitmap data using the NMAMapTileLayerDataSource mapTileLayer:requestDataForTileAtX:y:zoomLevel: protocol method.

## **Dividing a Map and Using Tile Coordinates**


NMAMapTileLayer uses a scheme that divides the world map into tiles, specified by x, y and zoom level coordinates. This coordinate system is used by the NMAMapTileLayerDataSource protocol when it requests tiles.

At each zoom level, it is expected that the world map is rendered on  $(2^{zoomlevel})^2$  tiles:

- at level 3: 8 x 8 = 64 tiles
- at level 4: 16 x 16 = 256 tiles
- continuing on until zoom level 20

For example, at zoom level 2, the world map would be divided up as follows:

Figure 19: World Map at Zoom Level 2



The x and y parameters indicate which tile is being requested for the given zoom level.

You need to provide enough tile images to cover all the zoom levels you are supporting within a geographical area. You can restrict custom tile rendering to a specific NMAGeoBoundingBox using the boundingBox property of NMAMapTileLayer. You can restrict the zoom level using showAtZoomLevel: and related methods.

▶ User Guide



## Supplying Tiles from a Web Server

The steps for providing custom tiles from a web server to a map view are as follows:

- Host the appropriate number of tiles on a server according to the zoom levels and NMAGeoBoundingBox you are supporting. The tiles must be in either PNG or JPG format and should be sized at 256 x 256 or 512 x 512 pixels.
  - Note: As long as your tiles conform to 256 by 256 or 512 by 512 pixels, the NMAMapView can scale the image to fit the current map resolution. For example, if the useHighResolutionMap property is set to YES (512 by 512 pixels) but your tiles are 256 by 256 pixels, the NMAMapView enlarges your image tiles.
- 2. Create an object that derives from NMAMapTileLayerDataSource and implement the mapTileLayer:urlForTileAtX:y:zoomLevel:method to return a URL pointing to the specified tile on your server.
- 3. Create an NMAMapTileLayer object and set its properties to correspond with the tile data source server. At a minimum, set the boundingBox and zoomLevel properties to reflect the tiles hosted on your server. Set the dataSource property.
- 4. Add the NMAMapTileLayer object to the NMAMapView by calling the addMapTileLayer: method.

The following code snippet shows a class that renders the Queen Elizabeth Olympic Park in London. The park is displayed as a tile layer that is added to an NMAMapView, and the raster tiles are served from the HERE server. To use this class, call [OlympicParkTileLayer addOlympicParkTileLayerToMapView:myMapView].

```
@interface OlympicParkTileLayer : NMAMapTileLayer <NMAMapTileLayerDataSource>
aend
@implementation OlympicParkTileLayer
+(void)addOlympicParkTileLayerToMapView:(NMAMapView*)mapView
OlympicParkTileLayer *tileLayer = [OlympicParkTileLayer new];
 [mapView addMapTileLayer:tileLayer];
 [mapView setGeoCenter:tileLayer.boundingBox.center
   zoomLevel:14.0
   withAnimation:NMAMapAnimationNone ];
}
-(id)init
if (self = [super init]) {
  // Set the data source
  self.dataSource = self;
  // Limit the tiles to the bounding box supported by the server
  NMAGeoBoundingBox *olympicParkBoundingBox =
  [NMAGeoBoundingBox geoBoundingBoxWithTopLeft:[NMAGeoCoordinates
   geoCoordinatesWithLatitude:51.557000 longitude:-0.042772]
   bottomRight:[NMAGeoCoordinates geoCoordinatesWithLatitude:51.525941
   longitude: 0.028296]];
  self.boundingBox = olympicParkBoundingBox;
  // Enable caching
  self.cacheTimeToLive = 60 * 60 * 24;
                                         // 24 hours
  self.cacheSizeLimit = 1024 * 1024 * 64; // 64MB
```

▶ User Guide



## **Supplying Tiles as Bitmaps**

You can choose to supply tiles as bitmaps if your app uses bundled static tiles, dynamically-generated tiles, or if the server that you are using for tile images requires authentication. In the third case, since NMAMapTileLayer only uses simple HTTP GET requests to retrieve tile images, it is up to you to provide code that handles authentication and downloads the tiles. Once the tiles have been downloaded, you can use them as local bitmaps with the NMAMapTileLayer class.

The steps for providing custom tiles as local bitmaps to a map view are as follows:

- Create an object that derives from NMAMapTileLayerDataSource and implements the mapTileLayer:requestDataForTileAtX:y:zoomLevel: method.
- 2. Create an NMAMapTileLayer object and set its properties to correspond with the tile data source. Set the dataSource property.
- 3. Add the NMAMapTileLayer object to the NMAMapView by calling the addMapTileLayer: method.

#### **Caching Tiles**

Tiles can be cached to the disk to improve performance and reduce data traffic in the URL fetching case.

When you enable caching, you must provide a cache identifier. This identifier must be unique for each NMAMapTileLayer used within your application. Since the cache persists across app sessions, it is important to use the same identifier across sessions (by defining a constant, for example).

You can optionally limit the cache size and time-to-live for each cached tile. The cache can be cleared at any time by calling [NMAMapTileLayer clearCache]. To be sure the cache is completely cleared first remove the NMAMapTileLayer from the map view before calling [NMAMapTileLayer clearCache].

The following code enables disk caching with a 128MB maximum size and a tile time-to-live of 7 days:

```
NMAMapTileLayer *tileLayer = [[NMAMapTileLayer alloc]init];
tileLayer.dataSource = self; // Assuming self is a valid data source
[tileLayer setCacheEnabled:YES withIdentifier:@"MyUniqueTileCacheIdenfifier"];
tileLayer.cacheTimeToLive = 60 * 60 * 24 * 7; // 7 days
tileLayer.cacheSizeLimit = 1024 * 1024 * 128; // 128 MB
[mapView addMapTileLayer:tileLayer]; // NOTE: add to map view after setting tile properties
```

▶ User Guide



### **Performance Tips**

- IMPORTANT: Set NMAMapTileLayer properties before adding the tile layer to the map view. Most properties ignore attempts to set them after being added to the view.
- 2. Ensure the properties you set on the tile layer match the data you are supplying via the NMAMapTileLayerDataSource protocol.
- 3. Do not block NMAMapTileLayerDataSource methods for extended periods of time. For example, if it takes a while to generate tiles on the fly move the processing to a separate GCD queue.
- 4. If requesting a specific tile is constantly failing consider implementing mapTileLayer:hasTileAtX:y:zoomLevel:, returning NO.
- 5. Use the provided disk caching mechanism.

## Positioning

## **Basic Positioning**

An application created using the HERE iOS SDK can use information from the positioning capabilities of a user's device to display its position, and, optionally, provide real-time updates. Getting the current position requires an application to make use of the NMAPositioningManager interface from the HERE SDK. To receive position updates or position-lost notifications, an application should use NSNotificationCenter addObserver with the notification names found in NMAPositioningManager.h:

- NMAPositioningManagerDidUpdatePositionNotification
- NMAPositioningManagerDidLosePositionNotification

The user's current position can be easily displayed on the map using the NMAPositionIndicator class. Each instance of NMAMapView owns an instance of this class, accessed via the positionIndicator property.

## **NMAPositioningManager**

The NMAPositioningManager class provides information related to the device's geographical location, such as the current position and the average speed. NMAPositioningManager is a singleton class and thus should only be accessed through the sharedPositioningManager class method.

Note: Add NSLocationWhenInUseUsageDescription to your project's Info.plist so that CLLocationManager can properly access the user's location. The value of this key is displayed to the user when the system requests for permission to use location services. See *App Submission Requirements* on page 21 for recommended strings.

To start receiving real time positioning updates, the application needs to call NMAPositioningManager startPositioning, which uses the internal GPS as the update mechanism. This method returns a BOOL value, indicating whether or not positioning was successfully started.

While position updates are being received, the application can retrieve the current position of the client device through the NMAPositioningManager currentPosition property. This current position is equal

▶ User Guide



to the rawPosition property. rawPosition is a position value from the current data source that has not been modified by the HERE SDK engine. If the positioning manager is not active, or it has an invalid position, then the currentPosition method returns nil.

Note: Map matching is disabled by default. It can be enabled automatically through the use of any HERE SDK feature which requires map matching, such as navigation, or it can be manually enabled by setting mapMatchingEnabled to YES. When map matching is disabled, mapMatchedPosition returns nil, and currentPosition returns the raw position.

When the application no longer requires position updates, it should notify the NMAPositioningManager by calling stopPositioning. Position updates are then stopped, provided that no other SDK services (such as NMAPositionIndicator) that require position updates are in use.

## **NMAPositioningManager Notifications**

The NMAPositioningManager notifications can be used to track position updates of a client device as determined by its positioning mechanism (for example, its GPS). To register or unregister for these notifications, use the following methods:

```
[[NSNotificationCenter defaultCenter] addObserver:self
selector:@selector(methodName)
    name:NMAPositioningManagerDidUpdatePositionNotification
    object:[NMAPositioningManager sharedPositioningManager]];
```

```
[[NSNotificationCenter defaultCenter] removeObserver:self
  name:NMAPositioningManagerDidUpdatePositionNotification
  object:[NMAPositioningManager sharedPositioningManager]];
```

Applications can register for two types of notifications:

- NMAPositioningManagerDidUpdatePositionNotification
- NMAPositioningManagerDidLosePositionNotification
- Note: NSNotificationCenter does not limit how many times an object can register to the same notification. You should be careful not to register the same object more than once to a notification. Otherwise, the object receives duplicate notifications.

The following is an example of registering and handling these notifications in a UIViewController:

```
// Start positioning and register for position update notifications
- (void)viewDidLoad
{
...
if ([[NMAPositioningManager sharedPositioningManager] startPositioning]) {
// Register to positioning manager notifications
[[NSNotificationCenter defaultCenter] addObserver:self
selector:@selector(positionDidUpdate) name:NMAPositioningManagerDidUpdatePositionNotification
object:[NMAPositioningManager sharedPositioningManager]];

[[NSNotificationCenter defaultCenter] addObserver:self
selector:@selector(didLosePosition) name: NMAPositioningManagerDidLosePositionNotification
object:[NMAPositioningManager sharedPositioningManager]];
}
...
}
// Handle NMAPositioningManagerDidUpdatePositionNotification
```

► User Guide



```
- (void)positionDidUpdate
{
NMAGeoPosition *position = [[NMAPositioningManager sharedPositioningManager] currentPosition];
[_mapView setGeoCenter:position.coordinates
    withAnimation:NMAMapAnimationLinear];
}
// Handle NMAPositioningManagerDidLosePositionNotification
- (void)didLosePosition
{
...
}
```

To avoid unnecessary position updates while the application is in the background, you can stop positioning and restart it when the application returns to the foreground using UIApplicationDelegate protocol callbacks.

The following code snippet demonstrates how to stop positioning and unregister from the notifications:

```
- (void)viewWillDisappear:(BOOL)animated
{
   [[NMAPositioningManager sharedPositioningManager] stopPositioning];
   [[NSNotificationCenter defaultCenter] removeObserver:self
   name:NMAPositioningManagerDidUpdatePositionNotification
   object:[NMAPositioningManager sharedPositioningManager]];
   [[NSNotificationCenter defaultCenter] removeObserver:self
   name:NMAPositioningManagerDidLosePositionNotification
   object:[NMAPositioningManager sharedPositioningManager]];
}
```

Note: If you enable background location updates in the Xcode project, then NMAPositioningManager provides position updates even when your application is no longer in the foreground. To avoid this behavior, you can either stop the positioning manager before the app goes into the background, or you can disable this setting in Xcode.

## **Creating Position Logs**

You can also use the HERE SDK to create GPX logs that can be replayed by NMALoggedPositionSource. To do this, set the logType property in NMAPositionManager to the value NMAPositionLogTypeDataSource, indicating that the position received from the current data source should be logged. GPX logs are created in the Documents folder of your application. To disable position logging, set NMAPositionLogType to NMAPositionLogTypeNone.

Note: This feature is only intended for debugging purposes. Do not use Position Logging in a production application.

#### **NMAPositionIndicator**


The NMAPositionIndicator class provides a convenient way to add a map object that marks the user's current location as reported by the NMAPositioningManager. The position indicator is rendered as a circular object within a translucent circle, the diameter of which illustrates the accuracy of the indicated

▶ User Guide



position. The types of map objects can be used to customize NMAPositionIndicator are NMAMapMarker and NMAMapCircle.

Figure 20: An NMAPositionIndicator



Each NMAMapView instance has an NMAPositionIndicator instance which can be accessed from the NMAMapView positionIndicator property.

You can customize the accuracy circle's color and whether it is visible by using the accuracyIndicatorColor and accuracyIndicatorVisible properties.

```
// Display position indicator
mapView.positionIndicator.visible = YES;
```

Note: Setting NMAPositionIndicator to visible automatically enables NMAPositioningManager updates.

For the position indicator to stay in the center of the map and illustrate real-time updates of the device position, it is necessary to update the map's center whenever a new location update is received. Please note that frequently redrawing the map in this manner consumes device battery life. You should be aware of battery power implications while performing real-time updates. The following code can be used to update the map location when a position update is received:

```
- (void)positionDidUpdate
{
  NMAGeoPosition *position = [[NMAPositioningManager sharedPositioningManager] currentPosition];
  [_mapView setGeoCenter:position.coordinates
    withAnimation:NMAMapAnimationLinear];
}
```

For more information about the classes introduced and demonstrated in this section, refer to the API reference documentation.

# Directions

User Guide



# Car and Pedestrian Routing

The HERE iOS SDK supports route calculation with multiple waypoints, optimized for walking or driving.

A route describes a path between at least two waypoints, the starting point and the destination, with optional intermediate waypoints in between. Applications can provide route information to users in two ways:

- A line rendered on a map that displays a connecting path between all waypoints
- · Turn-by-turn directions in text format

#### **NMARouteManager**

The NMARouteManager class is responsible for calculating an NMARoute using a list of stops and an NMARoutingMode. It also provides an NMARouteManagerDelegate protocol for monitoring calculation progress and triggering appropriate callback methods upon completion. To calculate a route, the application needs to call the calculateRouteWithStops:routingMode: method. NMARouteManager only supports one routing request at a time. Making another request before completion of the current request is not supported.

### **NMARoutingMode**

The NMARoutingMode class is a model of the parameters required to calculate an NMARoute, such as:

- routingType the routing type, such as Fastest or Shortest
- transportMode the mode of transportation
- routingOptions the routing options (represented by the NMARoutingOption enums) that are applicable for this route
- departureTime the departure time for the route
- resultLimit the maximum number of alternate routes to calculate (the actual number of results may be less than this limit)
- **Note:** Routing type describes different optimizations that can be applied during the route calculation:
  - Fastest route calculation from start to destination optimized by travel time. In some cases, the route returned by the fastest mode may not be the route with the shortest possible travel time. For example, it may favor a route that remains on a highway, even if a shorter travel time can be achieved by taking a detour or shortcut through a side road.
  - Shortest route calculation from start to destination disregarding any speed information. In this mode, the distance of the route is minimized, while keeping the route sensible. This includes, for example, penalizing turns. Because of that, the resulting route will not necessarily be the one with minimal distance.
  - Balanced route calculation from start to destination optimizing based on combination of travel time and distance.
- Note: The HERE SDK allows for more than one route to be returned from a route calculation between two waypoints. You can use the NMARoutingMode class to set the desired number of routes, and the HERE SDK then returns different routes according to this limit. Note that the first element of the

User Guide



returned array is the best result based on the routing options, and the rest of the returned routes are not listed in any specific order.

#### **NMARoute**

The NMARoute class represents a distinct calculated path connecting two or more waypoints, and consists of a list of maneuvers and route links. A call to the calculateRouteWithStops:routingMode: method of NMARouteManager triggers a route calculation, while the NMARouteManagerDelegate implements callback methods to monitor the operation and process the resulting NMARoute objects.

An NMARoute object contains route information that can be accessed by calling one or more of the following methods:

- routingMode the NMARoutingMode for the route
- · waypoints the array of all waypoints for the route
- start the starting waypoint for the route
- destination the destination waypoint for the route
- maneuvers the array of maneuvers for the route
- length the length of the route, in meters
- tta the NMARouteTta indicating the estimated time to arrival
- boundingBox gets the smallest NMAGeoBoundingBox that contains the entire route
- routeGeometry gets the array of all NMAGeoCoordinates along the route
- mapPolyline gets the NMAMapPolyline representation of the route

#### **NMARouteTta**

The NMARouteTta ("time-to-arrival") class provides useful information about the route, such as duration and route details that impact travel duration, including car pool restrictions, turn restrictions, and blocked roads. For example, to retrieve a duration for a calculated route, use the tta property. For example,

```
NSTimeInterval duration = route.tta.duration;
```

You can also retrieve the duration for a subleg from a route by using the ttaForSubleg: method. For example,

```
if (myRoute.sublegCount > 0)
{
  NSTimeInterval duration = [myRoute ttaForSubleg:0].duration;
}
```

#### **NMAManeuver**

The NMAManeuver class represents the action required to go from one segment to the next within a calculated NMARoute. Each NMAManeuver object provides information such as:

- location of the maneuver
- action required to complete the maneuver
- distance between maneuvers

▶ User Guide



- · current road
- next road
- · estimated times of the maneuver
- highway signpost (if any) indicating entrance, exit, or merge information
- · a list of route elements representing portions of this maneuver

For more information, please consult the API Reference.

#### NMARouteElement and NMARoadElement

NMARouteElement and NMARoadElement represent portions within a maneuver. For example, a maneuver may ask the driver to turn left and then remain on a street, but this street may be comprised of multiple sections, including a tunnel, a dirt road, and a toll road. In this situation, the maneuver contains multiple NMARouteElement objects, with each element containing a NMARoadElement property that can provide your application with information about the individual section of the road.

#### **NMAMapRoute**

The NMAMapRoute class is a type of NMAMapObject that displays a calculated route on a map. Typically, an application creates a NMAMapRoute after a route calculation, and add the NMAMapRoute to the map by calling NMAMapView addMapObject:.

English Bay

E. M.

Vancouver

Lindian

Figure 21: An NMAMapRoute added to an NMAMapView

For example, if you want to render a route that connects two waypoints (start and destination), you can add the following application logic:

1. Adopt NMARouteManagerDelegate protocol and create a NMARouteManager

```
@interface ClassName : NSObject <NMARouteManagerDelegate>
{
   // Setup your class
```

▶ User Guide



```
{
    (void)setup
{
        // Create a NMARouteManager.
        NMARouteManager* routeManager = [NMARouteManager sharedRouteManager];

        // Setup delegate
        [routeManager setDelegate:self];
}
```

2. Create an NSMutableArray and add two NMAGeoCoordinates stops

```
NSMutableArray* stops = [[NSMutableArray alloc] initWithCapacity:4];
NMAGeoCoordinates* geoCoord1 = [[NMAGeoCoordinates alloc]
initWithLatitude:49.1966286 longitude:-123.0053635];
NMAGeoCoordinates* geoCoord2 = [[NMAGeoCoordinates alloc]
initWithLatitude:49.1947289 longitude:-123.1762924];
[stops addObject:geoCoord1];
[stops addObject:geoCoord2];
```

Create an NMARoutingMode and set its NMATransportMode, NMARoutingType and NMARoutingOption values

```
NMARoutingMode* routingMode = [[NMARoutingMode alloc]
  initWithRoutingType:NMARoutingTypeFastest
  transportMode:NMATransportModeCar
  routingOptions:0];
```

Calculate the route

```
[routeManager calculateRouteWithStops:stops routingMode:routingMode];
```

- To receive the results of the route calculation, implement the NMARouteManagerDelegate protocol method routeManager:didCalculateRoutes:withError:violatedOptions: in your delegate class.
  - Note: Routes are returned even if you receive the NMARouteManagerErrorViolatesOptions error. It is up to you to handle these route results that violate routing options.

## **Routing-related enumerations**

Route calculations make use of HERE SDK enumerations that include:

► User Guide



- The NMARoutingType enum represents values describing different routing types, such as NMARoutingTypeFastest or NMARoutingTypeShortest
- The NMATransportMode enum represents values describing different transport modes, such as NMATransportModeCar or NMATransportModePedestrian
- The NMARoutingOption enum represents values describing special conditions for route calculation, such as NMARoutingOptionAvoidBoatFerry or NMARoutingOptionAvoidTollRoad. Values from this enum are also returned after a route calculation to indicate the options that a route result violates.
- The NMARouteViolatedOption enum represents values describing special conditions that are violated in a route calculation in addition to NMARoutingOption. This enum contains values for blocked roads and turn restrictions. For example, after specifying a route calculation that avoids tolls and ferries, you may get a NMARoute with the NMARouteViolatedOptionBlockedRoad violated option. This indicates that although a route was found, this route goes through at least one blocked road —violating a condition of your route request.
- The NMARouteManagerError enum represents values describing possible route calculation errors, such as NMARouteManagerErrorNone or NMARouteManagerErrorViolatesOptions

## Search

# Geocoding and Reverse Geocoding

Geocoding and reverse geocoding APIs from the HERE iOS SDK allow application developers to offer search functionality for requesting NMAPlaceLocation information. Geocoding APIs resolve a free-formatted text query to an NMAGeoCoordinates, while reverse geocoding APIs resolve from an NMAGeoCoordinates to geographic data, such as NMAAddress.

NMAAddress provides textual address information including house number, street name, city, country, district and more. It encompasses everything about an address or a point on the map. The NMAPlaceLocation class represents an area on the map where additional attributes can be retrieved. These additional attributes include NMAAddress, unique identifier, label, location, access locations, and NMAGeoBoundingBox for the location.

#### The NMAGeocoder Interface

The NMAGeocoder interface represents a factory class used to instantiate location search requests. Two types of requests are available: NMAGeocodeRequest and NMAReverseGeocodeRequest.

### The NMAGeocodeRequest Interface

The NMAGeocodeRequest interface represents an extended NMARequest. The NMAGeocodeRequest can be created using a combination of a search area and a free text query string. This is known as a "one-box" request. It returns NMAPlaceLocation results according to the specified search area and text query. You can specify a search area by providing a NMAGeoBoundingBox or a location with a search radius.

► User Guide



The following shows the methods used to create one-box requests:

```
NMAGeocodeRequest* request = [[NMAGeocoder sharedGeocoder] createGeocodeRequestWithQuery:string
    searchArea:geoBoundingBox
    locationContext:geoCoordinates];

NMAGeocodeRequest* request = [[NMAGeocoder sharedGeocoder] createGeocodeRequestWithQuery:string
    searchRadius:radius
    locationContext:geoCoordinates];
```

The preceding methods return an NMAGeocodeRequest object. To perform the request, call its startWithListener: method. The parameter of this method is an object which receives the request results; the object must implement the NMAResultListener protocol. Once a request is invoked, it can be canceled using the cancel method of NMARequest, which returns a BOOL value indicating whether the result was canceled successfully. If the NMAGeocodeRequest is successful, a list of NMAGeocodeResult objects is returned to the listener.

The following code example demonstrates how to use a NMAGeocodeRequest:

```
// Implementation of NMAResultListener
@interface NMAGeocodeTest : NSObject<NMAResultListener> {
กend
aimplementation NMAGeocodeTest
// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
 didCompleteWithData:(id)data
  error:(NSError*)error
if ( ( [request isKindOfClass:[NMAGeocodeRequest class]]) &&
  ( error.code == NMARequestErrorNone ) )
  // Process result NSArray of NMAGeocodeResult objects
 [self processResult:(NSMutableArray *)data];
 }
else
  // Handle error
- (void) startSearch
NMAGeoCoordinates *topLeft =
  [[NMAGeoCoordinates alloc]
   initWithLatitude:52.537413 longitude:13.365641];
NMAGeoCoordinates *bottomRight =
  [[NMAGeoCoordinates alloc]
   initWithLatitude:52.522428 longitude:13.39345];
NMAGeoBoundingBox *boundingBox =
  [NMAGeoBoundingBox
   geoBoundingBoxWithTopLeft:topLeft bottomRight:bottomRight];
NMAGeocodeRequest* request = [[NMAGeocoder sharedGeocoder]
createGeocodeRequestWithQuery:@"100 INVALIDENSTRASSE"
      searchArea:boundingBox
      locationContext:nil];
// limit the number of results to 10
```

User Guide



```
request.collectionSize = 10;

NSError* error = [request startWithListener:self];
if (error.code != NMARequestErrorNone)
{
   // Handle request error
   ...
}

@end
```

#### The NMAReverseGeocodeRequest interface

The NMAReverseGeocodeRequest interface represents an extended NMARequest used to retrieve NMAPlaceLocation data. The request is created using an NMAGeoCoordinates as shown below:

```
NMAGeocodeRequest* request = [[NMAGeocoder sharedGeocoder]
  createReverseGeocodeRequestWithGeoCoordinates:geoCoordinates];
```

The above method returns an NMAReverseGeocodeRequest object. Reverse geocode requests are used in the same way as regular geocode requests (described in the previous section), but the results are returned as an array of NMAReverseGeocodeResult objects.

The following example shows how to create and use an NMAReverseGeocodeRequest:

```
// Implementation of NMAResultListener
@interface NMAReverseGeocodeTest : NSObject<NMAResultListener> {
}
@end
@implementation NMAReverseGeocodeTest
// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
didCompleteWithData:(id)data
error:(NSError*)error
if ( [request isKindOfClass:[NMAReverseGeocodeRequest class]]) &&
  ( error.code == NMARequestErrorNone ) )
  // Process result NSArray of NMAReverseGeocodeResult objects
  [self processResult:(NSMutableArray *)data];
else
  // Handle error
- (void) startSearch
{
// Instantiate an Address object
NMAGeoCoordinates* vancouver = [[NMAGeoCoordinates alloc] initWithLatitude:49.2849
longitude:-123.1252];
NMAReverseGeocodeRequest* request = [[NMAGeocoder sharedGeocoder]
createReverseGeocodeRequestWithGeoCoordinates:vancouver];
NSError* error = [request startWithListener:self];
if (error.code != NMARequestErrorNone)
 // Handle request error
```

▶ User Guide



```
} } aend
```

For more information about the APIs introduced and demonstrated in this section, refer to the API Reference documentation.

## Search and Discovery

The HERE iOS SDK includes a Places API which provides functionality to search, discover, and obtain more information about places in the real world.

HERE Places helps to determine whether a business meets your needs through reviews and photos from real people. In addition to basic information such as opening hours and contact details, HERE Places can also include editorials from popular guides to help identify the best Places for you to visit.

#### **Steps for Performing a Search**

- Implement the NMAResultListener protocol to handle the completion of the search
- 2. Create a request using the NMAPlaces factory
- 3. Invoke the request by calling NMARequest startWithListener:
- 4. The NMAResultListener request:didCompleteWithData:error: callback is triggered when the request is finished
- **Note:** Applications that use the Places API must honor the following prescribed workflow:
  - Search
  - 2. Request for Details
  - 3. Perform Actions

Do not preload results that are linked from a response in order to improve performance, as doing so violates HERE's guidelines. For more information about usage restrictions, consult the *API Implementation Check List* section in the Places RESTful API documentation.

#### **Discovery Requests**

The HERE Places API supports the following discovery requests. Requests are created through factory methods in NMAPlaces.

Request	NMAPlaces method	Purpose
Search	createSearchRequestWithLocation: query:	Finds places that match user-provided search terms.

► User Guide



Request	NMAPlaces method	Purpose
Explore	<pre>createExploreRequestWithLocation:searchArea:filters:</pre>	Finds interesting places nearby, or in the map viewport, sorted by popularity. Use this type of request if you are trying to answer the question "What are the interesting places near here?" The results may be optionally restricted to a given set of categories, which acts as a filter in terms of what places get returned.
Here	createHereRequestWithLocation:filters:	Helps users identify places at the given location by finding places of interest near a given point, sorted by distance. Use this type of request if you are trying to answer the question "What is near this location?" or "Where am I?" You can use this endpoint to implement features like "check-in" (by identifying places at the user's current position) or "tap to get more information about this place of interest".
		Note: Normally, the closest known places are returned with the Here Discovery request, but if the uncertainty in the given position is high, then some nearer places are excluded from the result in favor of more popular places in the area of uncertainty.

The following code example demonstrates how to perform a search discovery request. You need to implement the NMAResultListener protocol by implementing the request:didCompleteWithData:error callback method, and also initialize the request by calling request startWithListener::

```
// Sample Search request listener
@interface NMASearchTest : NSObject<NMAResultListener> {
   NMADiscoveryPage* _result;
}
@end
@implementation NMASearchTest

// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
   didCompleteWithData:(id)data
   error:(NSError*)error
{
   if ( ( [request isKindOfClass:[NMADiscoveryRequest class]]) &&
        ( error.code == NMARequestErrorNone ) )
   {
        // Process result NMADiscoveryPage objects
        _result = (NMADiscoveryPage*) data;
   }
else
```

▶ User Guide



```
// Handle error
 (void) startSearch
 // Create a request to search for restaurants in Vancouver
NMAGeoCoordinates* vancouver =
 [[NMAGeoCoordinates alloc] initWithLatitude:48.263392
     longitude:-123.12203];
NMADiscoveryRequest* request =
 [[NMAPlaces sharedPlaces] createSearchRequestWithLocation:vancouver
     query:@"restaurant"];
 // optionally, you can set a bounding box to limit the results within it.
NMAGeoCoordinates *boundingTopLeftCoords = [[NMAGeoCoordinates alloc] initWithLatitude:49.277484
longitude:-123.133693];
NMAGeoCoordinates *boundingBottomRightCoords = [[NMAGeoCoordinates alloc]
 initWithLatitude:49.257209 longitude:-123.11275];
NMAGeoBoundingBox \ *bounding = \hbox{\tt [NMAGeoBoundingBox alloc] in itWithTopLeft:} boundingTopLeftCoords
bottomRight:boundingBottomRightCoords];
 request.viewport = bounding;
// limit number of items in each result page to 10
 request.collectionSize = 10;
NSError* error = [request startWithListener:self];
 if (error.code != NMARequestErrorNone)
  // Handle request error
aend
```

To ensure that your application get the best search results, you can set a location context to your search request by setting a bounding box to the viewport property. In the previous example, you can also replace the NMAGeoBoundingBox with the viewport from NMAMapView.

The result of a search or explore discovery request is an NMADiscoveryPage. The NMADiscoveryPage represents a paginated collection of items from which the following can be retrieved:

- Next page request an NMADiscoveryRequest used to retrieve additional pages of search items
- Items for the current page an NSArray of NMALink, either NMAPlaceLink or NMADiscoveryLink

If NMADiscoveryPage.nextPageRequest is nil, no additional results are available.

The following is an example:

```
...
@interface NMANextPageTest : NSObject<NMAResultListener> {
   NMADiscoveryPage* _page; // valid NMADiscoveryPage instance
}
@end
@implementation NMANextPageTest
- (void)onNextPageAction
{
   NSError* error = [_page.nextPageRequest startWithListener:self];
   if ( error.code == NMARequestErrorNone )
{
```

▶ User Guide



```
// More data is available
}

// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
    didCompleteWithData:(id)data
    error:(NSError*)error
{
    if ( ( [request isKindOfClass:[NMADiscoveryRequest class]] ) &&
        ( error.code == NMARequestErrorNone ) )
    {
        // Process NMADiscoveryPage objects
    }
    else
    {
        // Handle error
     ...
    }
}
...
@end
```

The NMADiscoveryPage discoveryResults property contains an array of NMALink objects. The items are actually a collection of NMALink subclasses:

- NMAPlaceLink Represents discovery information about a NMAPlace. The NMAPlaceLink contains
  a brief summary about a place. Details about a place are available from the NMAPlace that the
  NMAPlaceLink references.
- NMADiscoveryLink Represents a discovery-related API link used to retrieve additional NMADiscoveryPage instances. This type of NMALink can be a result item in an Explore or Here type of search. The NMADiscoveryLink references refine discovery requests resulting in more specific results. For example, the NMADiscoveryLink may link to a discovery request to search for 'Eat & Drink', 'Going Out', 'Accommodation', and so on.

It is recommended that each type of NMADiscoveryPage be checked before it is used. In the following example, it is shown how an NMAPlace is retrieved through a NMAPlaceLink:

```
@interface NMASearchTest : NSObject<NMAResultListener> {
    NMADiscoveryPage* _result;
<del>aend</del>
aimplementation NMASearchTest
// Retrieve the place details when the user selects a displayed PlaceLink.
- (void)onPlaceLinkSelected:(NMAPlaceLink*)placeLink
NSError* error = [[placeLink detailsRequest] startWithListener:self];
if ( error.code == NMARequestErrorNone )
  // More data will available.
}
// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
  didCompleteWithData:(id)data
  error:(NSError*)error
{
    if ( ( [request isKindOfClass:[NMADiscoveryRequest class]]) &&
         ( error.code == NMARequestErrorNone ) )
```

▶ User Guide



```
result = (NMADiscoveryPage*) data;
  NSArray* discoveryResult = _result.discoveryResults;
  for ( NMALink* link in discoveryResult )
   if ( link isKindOfClass:[NMADiscoveryLink class] )
   NMADiscoveryLink* discoveryLink = (NMADiscoveryLink*) link;
   // NMADiscoveryLink can also be presented to the user.
   // When a NMADiscoveryLink is selected, another search request should be
   // performed to retrieve results for a specific category.
   else if ( link isKindOfClass:[NMAPlaceLink class] )
   NMAPlaceLink* placeLink = (NMAPlaceLink*) link;
   // NMAPlaceLink should be presented to the user, so the link can be
   // selected in order to retrieve additional details about a place
   // of interest.
   }
 }
else if ( ( [request isKindOfClass:[NMAPlaceRequest class]]) &&
            ( error.code == NMARequestErrorNone ) )
  NMAPlace* place = (NMAPlace*)data;
  // Access to additional details about a place of interest.
else
 // Handle error
}
}
@end
```

#### The NMAPlace Class

The NMAPlace class represents a detailed set of data about a physical place, acting as a container for various attributes, collections of media about a place, and key-value pairs of related places. An NMAPlace object can belong to a specific NMACategory, and has attributes such as:

- A unique identifier (ID)
- A name
- An NMAPlaceLocation object representing the physical location of the place. NMAPlaceLocation
  also contains a street address and a list of the geocoordinate positions to access this place.
- An array of NMACategory objects that link to the categories assigned to the place
- An NMALink object containing a link to the origin of supplied information, typically a website of the supplier
- An NSString representing a URL to an icon (optional)
- · Optional information, such as related places, user ratings, reviews, and other editorial media

▶ User Guide



#### **Category Filters**

A place of interest can be associated with categories such as museum, restaurant, and coffee shop. While creating an Explore or Here discovery request, you can choose to provide category filters to get a more specific set of results. For example, you may want to search for sushi restaurants near the Vancouver city hall.

To get a list of categories, call the topLevelCategories method in NMAPlaces. From this list of categories, you can then retrieve one or more level of sub-categories. For example, "Bars/Pubs" under the "Restaurant" category. Once you have the categories, you can then create an NMACategoryFilter object and call the addCategoryFilterFromUniqueId method. Note that each NMACategoryFilter object can represent multiple categories.

#### **Text AutoSuggestion Requests**

The HERE Places Search API also supports text autosuggestion requests. This type of request is used for retrieveing a list of suggested search terms (NMAAutoSuggestTypeQuery), instant results (NMAAutoSuggestTypePlace), and refined search links (NMAAutoSuggestTypeSearch) that are related to a specified location context and a partial search term. For example, if you make a request with the String "rest" in Berlin, the results then contain search terms such as "Restaurant", "Rest area", and "Restorf, Höhbeck, Germany".

To use text autosuggestions, implement a listener to handle a list of NMAAutoSuggest and call createAutoSuggestionRequestWithLocation:partialTerm: as follows:

```
// Sample Search request listener
@interface NMATextAutoSuggestionSearchTest : NSObject<NMAResultListener> {
    @end
@implementation NMATextAutoSuggestionSearchTest

// NMAResultListener protocol callback implementation
- (void)request:(NMARequest*)request
    didCompleteWithData:(id)data
    error:(NSError*)error
```

► User Guide



```
if ( ( [request isKindOfClass:[NMAAutoSuggestionRequest class]]) &&
   ( error.code == NMARequestErrorNone ) )
 // Results are held in an array of NMAAutoSuggest objects
 // You can then check the subclass type using the NMAAutoSuggest.type property
 NSArray* textAutoSuggestionResult = (NSArray*) data;
else
 {
  // Handle error
}
  (void) startSearch
NMAGeoCoordinates* vancouver =
   [[NMAGeoCoordinates alloc] initWithLatitude:47.592229
      longitude:-122.315147];
NMAAutoSuggestionRequest* request =
   [[NMAPlaces sharedPlaces] createAutoSuggestionRequestWithLocation:vancouver
      partialTerm:@"rest"];
 // limit number of items in each result page to 10
request.collectionSize = 10;
NSError* error = [request startWithListener:self];
if (error.code != NMARequestErrorNone)
  // Handle request error
@end
```

You can retrieve the results of NMAAutoSuggestionRequest by first checking the NMAAutoSuggest object type, as shown in the following example. If the object is NMAAutoSuggestTypeSearch, it contains additional paginated results through its NMADiscoveryRequest object. If the object is NMAAutoSuggestTypePlace, you can request for more details through its NMAPlaceRequest. NMAAutoSuggestTypeQuery contains additional results through the NMAAutoSuggestionRequest object.

```
+(B00L)checkAutoSuggestResults:(NSArray*)array
{
  for (id item in array) {
    NMAAutoSuggestType type = ((NMAAutoSuggest*)item).type;
    NSString *typeString;
    switch (type){
    caseNMAAutoSuggestTypePlace:
    {
        typeString = @"Place";
    }
        break;
    caseNMAAutoSuggestTypeSearch:
    {
        typeString = @"Search";
    }
        break;
    caseNMAAutoSuggestTypeQuery:
    {
        typeString = @"Query";
    }
        break;
}
```

► User Guide



```
NSLog(@"Type = %@", typeString);
 NMAAutoSuggest* suggestItem = (NMAAutoSuggest*)item;
 //Retrieve information such as suggestItem.title
 if (type == NMAAutoSuggestTypePlace) {
  NMAAutoSuggestPlace* suggestPlace = (NMAAutoSuggestPlace*)item;
  //Retrieve information such as suggestPlace.vicinityDescription
  NMAPlaceRequest* detailsRequest = suggestPlace.placeDetailsRequest;
  // Get NMAPlaceResult by calling detailsRequest startWithListener:
 } else if (type == NMAAutoSuggestTypeSearch) {
  NMAAutoSuggestSearch* suggestSearch = (NMAAutoSuggestPlace*)item;
  //Retrieve information such as suggestSearch.position
  NMADiscoveryPage* discoveryPage;
  NMADiscoveryRequest* discoveryRequest = suggestSearch.suggestedSearchRequest;
  // Get discoveryPage by calling [discoveryRequest startWithListener:]
 else if (type == NMAAutoSuggestTypeQuery) {
  NMAAutoSuggestionRequest* autoSuggestionRequest =
((NMAAutoSuggestQuery*)item).autoSuggestionRequest;
  // Call autoSuggestionRequest startWithBlock:^(NMARequest, id, NSError) {}
return YES;
```

## Offline Search

#### Force Online or Offline

You can launch online or offline searches without changing the device or HERE SDK connectivity by using the connectivity property on an NMARequest instance. This property is applicable to all NMARequest subclasses, except NMAAutoSuggestionRequest, which can only be used online.

Note: In HERE SDK v3.4, we have updated the behavior of the routing connectivity modes (NMARequestConnectivity) to be more consistent with other parts of the SDK.

The connectivity property can be set to three possible values:

If you launch a request using the NMARequestConnectivityDefault connectivity mode, the request
is performed according to the NMAApplicationContext connectivity setting. If the device is offline
while NMAApplicationContext is set to online mode, the request fails.

► User Guide



- If you launch a request using the NMARequestConnectivityOnline connectivity mode, an online request is performed, regardless of the NMAApplicationContext connectivity setting.
- If you launch a request using the NMARequestConnectivityOffline connectivity mode, an offline request is performed, regardless of the NMAApplicationContext connectivity setting.

In all cases, if the request fails, no fallback action is automatically performed.

To ensure that the connectivity mode is applied, set the connectivity property before executing an NMARequest.

Depending on your search request and the connectivity mode, you can get a few different errors:

- If an NMARequestConnectivityOnline search request fails due to connection issues, HERE SDK returns the NMARequestErrorUnknown error code.
- If an NMARequestConnectivityOnline Geocoding or Reverse Geocoding request fails due to connection issues, HERE SDK returns the NMARequestErrorNetworkCommunication error code.
- If an NMARequestConnectivityOffline search request fails due to not enough cached data, HERE SDK returns with zero results.
- If you attempt to start an NMAAutoSuggestionRequest with the NMARequestConnectivityOffline connectivity mode, HERE SDK returns the NMARequestErrorNotSupported error code, since auto suggestions are only supported online.

► Supplemental Information



# **Chapter 4**Supplemental Information

#### **Topics:**

- Create a Simple HERE SDK A...
- Swift Support in HERE SDK
- Supported Thread Usage

This section provides supplemental information for using the HERE iOS SDK.

► Supplemental Information



# Create a Simple HERE SDK App Using Swift

This tutorial provides instructions on how to create a simple application using the *Swift programming* language. It is equivalent to the Objective-C tutorial, which is located at *Create a Simple App Using the HERE SDK* on page 12.

Development tasks for this basic application include:

- Create a new Xcode project
- · Add necessary resources and a map view to the project
- Acquire credentials from HERE for accessing map services
- Initialize the map view such that a map instance is created for rendering on the client device

The contents of this guide apply to Xcode 10 and the iOS 12 SDK.

#### Sample Project in the HERE iOS SDK

A copy of the Xcode project described in this tutorial is available in the sample-apps folder in your HERE iOS SDK package. To run the project, double-click on SwiftHelloMap.xcodeproj and follow the instructions in the README.txt file.

### **Create a New Single View Application**

- From XCode menu, select File > New > Project to open the New project dialog (or press Shift + Command + N).
- 2. Select iOS > Application > Single View Application as the application type you want to create. Press Next.
- In the next dialog, enter your Product Name (such as HelloMap) and Organization Identifier (such as edu.self).
- 4. Choose "Swift" under Language, then click Next.
- 5. Navigate to the directory where you want your project to be stored and then select Create.
- 6. The next step is to configure this project to use the HERE SDK.

#### **Configure the Application**

- **1.** Extract the HERE iOS SDK archive to somewhere in your local file system.
- 2. Add the NMAKit framework to your Xcode project. To add the NMAKit framework to your Xcode project, click on your app target and choose the "General" tab. Find the section called "Embedded Binaries", click the plus (+) sign, and then click the "Add Other" button. From the file dialog box, select the

► Supplemental Information



"NMAKit.framework" folder. Ensure that the "Copy items if needed" and "Create folder reference" options are selected, then click **Finish**.

Figure 22: Add File to Target

Choose options for adding these files:			
Destination:  Copy items if needed  Added folders:  Create groups  • Create folder references			

3. Ensure that NMAKit.framework appears in the "Embedded Binaries" and the "Linked Frameworks and Libraries" sections.

Figure 23: Embedded Binaries

<b>▼ Embedded Binaries</b>	
	MMAKit.framework
	+ -

- **4.** Run the application. From the Xcode menu bar, select **Product** > **Run**. Ensure that the project runs in the iOS Simulator without errors.
- 5. The HERE iOS SDK is now ready for use in your Xcode project. Now that you have your project configured to work with the HERE SDK, try extending the sample application to render a map.

#### **Create the Map View**

In this section, we utilize the NMAMapView and NMAGeoCoordinates classes to render a Map.


- 1. Create an NMAMapView.
  - a. Select Main.storyboard in the navigator, then open the Utilities view by pressing the key combination Command + Option + Control + 3. Drag and drop a View object from the Object Library onto the View Controller. If necessary, resize the View so it takes up the entire viewable area.
  - **b.** In the Interface Builder, click on the created View and then open the Identity Inspector in the Utilities view by pressing the key combination Command + Option + 3. Change the class value from

► Supplemental Information



UIView to NMAMapView and press return. In the Document Outline, you should see that the name of the View has changed from to *View* to *Map View*.

Figure 24: MapView



- 2. Create an outlet to NMAMapView in ViewController.
  - a. Select Main.storyboard in the navigator.
  - b. Press Command + Option + Return to open the Assistant Editor. It should show ViewController.swift.
  - c. Add the following import statement to the top of this file:

import NMAKit


**d.** Hold the Control key on the keyboard and click to drag from the Map View to the interface block in *ViewController.swift*. You should see a blue line and tooltip which says "Insert Outlet or Outlet Connection". Release the mouse button and a dialog appears, allowing you to create an outlet.

► Supplemental Information



e. Name the outlet mapView, keep the other default options and then select Connect.

#### Figure 25: Create an Outlet



3. Now an outlet to NMAMapView is set. The modified file should be as follows:

Implement NMAMapView setup and lifecycle code by replacing the viewDidLoad() function with viewWillAppear(animated) and addMapCircle():

```
override func viewWillAppear(_ animated: Bool) {
   super.viewWillAppear(animated)
   mapView.useHighResolutionMap = true
   mapView.zoomLevel = 13.2
   mapView.set(geoCenter: NMAGeoCoordinates(latitude: 49.258867, longitude: -123.008046),
        animation: .linear)
   mapView.copyrightLogoPosition = NMALayoutPosition.bottomCenter
   addMapCircle()
}

func addMapCircle() {
   if mapCircle == nil {
    let coordinates: NMAGeoCoordinates =
        NMAGeoCoordinates(latitude: 49.258867, longitude: -123.008046)
        mapCircle = NMAMapCircle(coordinates: coordinates, radius: 50)
        mapView.add(mapCircle!)
```

► Supplemental Information



}


- 5. Add your HERE application credentials.
  - **a.** Open the *AppDelegate.swift* file and import *NMAKit* by adding the following import statement to the top of the file.

```
import NMAKit
```

b. Add the following in the application(\_:didFinishLaunchingWithOptions) function, replacing YOUR\_APP\_ID and YOUR\_APP\_CODE with the credentials that you received from your <a href="http://developer.here.com">http://developer.here.com</a>.

6. Build and run the application. If the build is successful, you now have an application that displays a map similar to the following screenshot and allows you to manipulate it using gestures.

Figure 26: Running the App



► Supplemental Information



# Swift Support in HERE SDK

This section provides information on the ways that HERE iOS SDK supports development using Swift 3 or above.

#### **Nullability Annotations**

Where appropriate, properties, method parameters, and return types are marked with nullability annotations. This provides more clarity on the generated Swift types and avoids implicitly unwrapped optionals.

For more information on this, read the blog post on "Nullability and Objective-C".

## **Designated Initializers**

Where appropriate, class header files have annotatations to indicate the designated initializer method.

For more information, see the documentation on initialization in Swift and initialization in Objective-C.

#### **Suggested Names for Swift**

The HERE SDK contains suggested Swift method names to better align with standard Swift naming conventions. For example, createGeocodeRequestWithQuery:searchArea:locationContext: is create(query:searchArea:locationContext:) in Swift.

**Attention:** An API Reference containing Swift method names is not currently available. You can find Swift method names in the header files.

For more information, see the blog post on Swift 3 API Design Guidelines.

### **Stronger Typing Using Lightweight Generics**

Where appropriate, the HERE SDK contains lightweight generics information for collection types. This provides stronger typing in the generated Swift code. For example, the referenceIdentifiers(forSource:) method in NMAPlace returns [String] rather than a [AnyObject].

For more information, see Importing Objective-C Lightweight Generics.

# Supported Thread Usage

Developers should be aware of the following threading guidelines while using the HERE iOS SDK:

- All NMA interface methods are designed to be called from the main thread.
- All NMA protocol callbacks and blocks are dispatched to the main thread.
- Any exceptions to this rule are clearly documented in the applicable protocol or block definition.

► Coverage Information



# **Chapter 5**Coverage Information

The following list provides coverage information for HERE iOS SDK features. Feature support in the HERE SDK may differ depending on the language and locale.

- Satellite Imagery
- Public Transit
- Routing
- Point Addresses (such as house numbers)
- Online Geocoding / Reverse Geocoding
- Online Places and Search