

G.E.T.S.

Installation Guide

Version 2.0.0

GreekSoft Technologies Pvt. Ltd.
Siddivinayak Arcade, 3rd floor,
Akruli Cross Road No. 1,
Kandivali (E),
Mumbai

Proprietary Notice

This document contains confidential information of GreekSoft Technologies Pvt. Ltd., which is provided for the sole purpose of permitting the recipient to application help document submitted herewith. In consideration of receipt of this document, the recipient agrees to maintain such information in confidence and to not reproduce or otherwise disclose this information to any person outside the group directly responsible for evaluation of its contents, except that there is no obligation to maintain the confidentiality of any information which was known to the recipient prior to receipt of such information from GreekSoft Technologies Pvt. Ltd., or becomes publicly known through no fault of recipient, or is received without obligation of confidentiality from a third party owing no obligation of confidentiality to GreekSoft Technologies Pvt. Ltd.

INDEX


- I. Installing VSFlex*
- II. Installing GMX Manager*
- III. Installing GMX Client*

GMX installation involves below steps.


- Installing VS Flex (both on server and client machines)
- Installing GMX Manager
- Installing GMX Client

Installing VSFlex


Extract the 'vsFlex.zip' file. There will be three files 'SETUP.EXE', 'README.TXT' & 'CSREADME.TXT'. Click on 'SETUP.EXE'




In welcome dialog, click on OK




Select destination directory and click on OK. Default installation directory is C drive.




Check VideoSoft VSFlexGrid Pro 6.0 and click OK in Select components to install dialog.



Installation will progress.




Click Yes on Add to Start Menu dialog.



You will be prompted for VideoSoft Product Registration.




Open the CSREADME.TXT file.



Copy the SERIAL NUMBER and paste in the VideoSoft Product Registration dialog. Click on REGISTER button. Below dialog will be displayed. Click on OK button.



VideoSoft Product Registration dialog will be prompted again. Click on FINISH button. Below dialog will be displayed. Click on OK button.



Installing GMX Manager

1. Create GMX Database

Go to SQL Enterprise Manager and create new database with name 'GMX'. Set the Data and Log files location in D drive.

2. Restore the GMX Empty DB

Restore the GMX empty database provided in the package

3. Verify the GMX DB

Verify whether all tables present in the DB and design of the DB tables

4. Extract the GMX Manager zip file to D drive & copy SER file to GMX Manager folder

5. Configure GMX DSN

Go to Control Panel -> Administrative tools. Click on Data Sources (ODBC) and select System DSN tab.

Clicking on Add will prompt 'Create a New Data Source'. Select SQL server and click on Finish button, which prompts you 'Create a New Data Source to SQL Server'. Fill the Name field with GMX, Server with GMX DB IP address. Click on Next

In the following dialog, select the SQL authentication mode as 'with SQL server authentication using a login ID and password entered by the user'. Enter the proper login ID (sa) and password. Click on Next button. In the following dialog, change the default database to GMX and click next. In the following dialog, click finish.

In ODBC Microsoft SQL server setup, Click on Test Data Source and confirm TESTS COMPLETED SUCCESSFULLY.

6. Configure the Database IP and Category in 'database.txt'

Open the extracted GMX Manager folder and open the 'database.txt' file. And make sure

InitialCatalog=GMX	<- Database Name
DataSource=192.168.0.32	<- Database IP
Uid=sa	<- SQL User Name
Pwd=	<- SQL Password
DSN=	<- DSN=Y, if DSN configured, else DSN=N
DBPROCESS = Y	<- DBPROCESS must be Y

7. Make folder 'GreekMasterFiles' in C drive and share the folder

8. Copy the latest scrip masters to C drive

9. Start 'CTCLManager.exe' from GMX Manager folder on D drive

Starting GETS Manager will open the Manager dialog from where all the actions in GETS Manager will be carried.


10. Stop Applications

If any sub application in the manager is started, the user can stop by calling Utility -> Stop Applications.

11. Configure the connection settings

The user can access the settings dialog from Tools -> Exchange Connection Setting. All exchange parameters (interactive and broadcast), CTCL / IML IDs to be defined here.

When the user calls the Connection settings, the dialog opens as below.



Select the exchange	NSE / BSE / MCX / NCDEX
Market Segment	Equity / Derivatives
Login by	Trader
User ID	CTCL ID of the respective market segment
Member ID	Trading Member ID
Password	CTCL ID password
New Password – In case, if the user wants to change the CTCL ID password, he needs to click on 'Set new Password' button -> enter the new password -> Click Modify -> Enter security password -> OK -> Setting is Modified -> OK -> Cancel -> Enter Password -> Modify -> Enter security password -> OK -> Setting is Modified -> OK.	

When the user clicks on details button, it will show all the connection parameters. He has to set the proper interactive and broadcast parameters.

Branch ID	CTCL Branch ID
Version No	Current NEAT Version
Work Station No	Not required in case of TAP
Port No	Not required in case of TAP
Local Address	Not required in case of TAP
EICON Card	Not required in case of TAP

Receive Broadcast Either X.25 Broadcast / NSE TAP Broadcast

 If X.25, input call data & host address

 If TAP, Enter

 Multicast address – Multicast IP configured on TAP

 Port – Input respective port to receive normal / fast broadcast, as per selected market segment

 IP Address – GMX Manager IP address

Interactive Either X.25 / TAP IP

 If X.25, input call data & host address

 If TAP, Enter

 Server IP – TAP Server IP

 Host Address – Interactive Port as per selected market segment

UDP Multicast Address If client selects ALL broadcast mode

 Multicast Address – Define at server level

 Port – Define at server level

UDP Portfolio If client selects Subscribed broadcast mode

 Multicast Address – Define at server level

 Port – Define at server level

Send to Client whether to send the broadcast to CTCL Client

 Yes – Sends the broadcast to client

 No – Do not send the broadcast to client

TCP/IP If client connects through internet

.

 Local IP Address – Define at server level

 Port – Define at server level

Connection Setting

NSE Setting | BSE Setting | MCX Setting | NCDEX Setting

Market Segment: EQUITY

Login by: ☐ Branch Manager ☒ Trader ☐ Corporate Manager

User Id: 26662 Member Id: 07782

Password: ***** New Password: Set new password

Modify Hide

Branch ID: 41 Version no: 90900 Work Station no: 1234567 Port no: 1

Local Address: 1234567 Eicon Card: 1

Receive Broadcast

☐ X25 BroadCast ☒ NSE Server BroadCast

Call Data: Unknown Multicast Address: 233 . 1 . 2 . 10

Host Address: Port: 4501 IP Address: 192.168.206.61

Send Broadcast

UDP UDP Portfolio

Multicast Address: 234 . 1 . 2 . 6 Multicast Address: 232 . 1 . 2 . 6

Port: 9901 Port: 9902

Interactive

☐ Only X25 ☒ IP

Call Data: unknown Host Address: Server IP: 192.168.206.61 Host Address: 9609

TCP/IP

Local IP Address: 192.168.206.61 Port: 50000

Close

12. Configure stored order response settings

Under Tools -> Stored Order Response, check all three options and click on OK.

13. Upload Scrip Masters

Upload the scrip master files from File -> Upload Contract / Security

14. Start Applications

Start all sub applications on Manager. Below are the sub applications.

- CTCL Client Communicator
- NSE Interactive, BSE Interactive

- NSE EQ Broadcast, NSE FO Broadcast, BSE Broadcast
- GATS
- Database Manager (Task Manager Process)
- NCDEX Broadcast and Interactive, MCX Broadcast and Interactive (as per setting in Style.txt)

15. Check broadcast receiving

In Broadcast dialogs confirm the increase in broadcast data packets

16. Login to exchange

Login to exchange from File -> Login. Make sure that you got the message 'System is Ready for Trading' on manager.

17. Broadcast connection settings in case of multiple managers

In case of multiple managers, you should make sure that the broadcast connection settings are unique. And configure 'Send to Client' as No in other managers.

Installing GMX Client

1. Install VSFlex

Before installing GMX client, install the VSFlex as explained above.

2. Extract the GMX client package

Extract the GMX client package to D drive

3. Copy the SER file to GMX client package

4. Start GMX Client and set the Connection Settings

Once you start the GETS CTCL.exe, it will prompt the user to enter the Manager Connection settings.

Server Settings

Local IP Add 192 . 168 . 0 . 18 Server IP Add 192 . 168 . 0 . 1

☒ Subscribed ☐ All UDP Settings

No. of UDP Ports 2

UDP Port 1 4560 IP Address 1 232 . 1 . 2 . 3

UDP Port 2 5678 IP Address 2 232 . 1 . 2 . 3

UDP Port 3 0 IP Address 3 . . .

UDP Port 4 0 IP Address 4 . . .

Subscribed Broadcast

No. of UDP Ports 2

UDP Port 4561 IP Address 232 . 1 . 2 . 3

UDP Port 5671 IP Address 232 . 1 . 2 . 3

TCP Settings

No. of TCP Ports 1

All TCP Port 50000 0 0 0

OK Cancel Restore Defaults

G.E.T.S Server Settings Local IP: \\192.168.0.18 Server IP: \\192.168.0.1

Enter the Local IP Address, Server IP Address and select the UDP settings for broadcast as mentioned below.

Subscribed – Get the broadcast for the symbols added in portfolio / market watch

All – Get the broadcast for all symbols, even if client not added to portfolio

In case of multiple managers, it is must that any one of the clients connecting to broadcast to the main server (where broadcast process is running) needs to keep the UDP settings as ALL. Remaining clients connecting to this main server can set as either Subscribed / ALL. The clients who are on other manager should keep the UDP setting as ALL.

5. Login to GMX Client

Login to GMX client; verify the broadcast and interactive channels.

-----**END OF DOCUMENT**-----