

G.E.T.S. Manager

FAQs

Version 2.0.0

GreekSoft Technologies Pvt. Ltd.
Siddivinayak Arcade, 3rd floor,
Akruli Cross Road No. 1,
Kandivali (E),
Mumbai

Proprietary Notice

This document contains confidential information of GreekSoft Technologies Pvt. Ltd., which is provided for the sole purpose of permitting the recipient to application help document submitted herewith. In consideration of receipt of this document, the recipient agrees to maintain such information in confidence and to not reproduce or otherwise disclose this information to any person outside the group directly responsible for evaluation of its contents, except that there is no obligation to maintain the confidentiality of any information which was known to the recipient prior to receipt of such information from GreekSoft Technologies Pvt. Ltd., or becomes publicly known through no fault of recipient, or is received without obligation of confidentiality from a third party owing no obligation of confidentiality to GreekSoft Technologies Pvt. Ltd.

GETS Manager Frequently Asked Questions

1. Where can I define the database IP address?
2. What is GreekDB.db file created in C drive? Why I need to delete this file everyday morning?
3. GETS Managers is not starting. What is the problem?
4. What are all the applications that will start when I do utility->start applications?
5. What are the actions carried out by client communicator?
6. How can I configure my CTCL IDs on Manager?
7. Where can I set the exchange broadcast and interactive parameters?
8. How can I verify the broadcast receiving from exchange?
9. How can I confirm the successful exchange login?
10. EQ broadcast / FO broadcast application is not coming up. What is the problem?
11. Security / Contract upload is taking much time. Why is it so?
12. After login to exchange, I am not getting message 'System is ready for trading'. What is the problem?
13. Why am I not getting broadcast in GETS client, even I see the broadcast receiving at manager?
14. I am getting double broadcast in GETS client. How can I resolve this?
15. When I do start applications, client communicator is not starting. Why is it so?
16. When I do start applications, NSE interactive is not starting. Why is it so?
17. How can I confirm that the data is getting stored in my SQL database?
18. When there is exchange disconnection, I am getting all messages downloaded (zero download) after reconnection. How to stop this?
19. When I disconnect the EQ broadcast / FO broadcast, the respective application is closing. How can I disconnect without closing?
20. I have multiple managers and the broadcast settings are same in all managers. Even then I am not getting broadcast in GETS client?
21. My database disk space utilization is high. How to reduce the utilization?
22. What is the location of GETS Manage log files?
23. What is the implication of doing 'Backup Database' from client communicator?
24. What is the implication of doing 'Restore Database' from client communicator?
25. How can I set new password for CTCL ID?
26. How can I switch to X.25 from TAP?
27. How can I disconnect any client from Manager?
28. Can I delete pending orders from Manager?
29. How can I delete all pending orders at once from Manager?
30. What is Stored Order Response?
31. Is the exchange connectivity automatically re-established after disconnection?
32. My Exchange connectivity lost and re-established. How to re-download the order and trade messages, which are submitted / received during this interval?

1. Where can I define the database IP address?

A. You need to define the database IP address in database.txt file present in the GETS Manager folder. The content of GETS Manager must be as below.

InitialCatalog=GETS	<- GETS Database
DataSource=192.168.0.32	<- Database IP
Uid=sa	<- User Name
Pwd=	<- Password
DSN=	<- DSN=Y, if configured, else leave blank
DBPROCESS = Y	<- DBPROCESS must be Y

2. What is GreekDB.db file created in C drive? Why I need to delete this file everyday morning?

A. GreekDB.db file is online resident database managed on daily basis which is created in C drive. This contains the activity messages for the trading day. So this needs to be deleted on daily basis.

3. GETS Managers is not starting. What is the problem?

A. GETS Manager does not get start in below cases.

- Verify in task manager that 'GETS Manager.exe' is not running. If it is running, end the process and restart.
- Take the backup of GreekDB.db from C drive and delete it. Restart Manager.
- If manager not starting during market hours, then take the backup of GreekDB.db from C drive and delete it. Restart Manager, upload master files and do 'Restore backup' from CTCL Client Communicator. After receiving message 'Restore Backup Completed', login to the markets.
- If you get the license expired message, you need to get the new license file from support team

4. What are all the applications that will start when I do utility->start applications?

A. All applications that run on G.E.T.S. Manager are listed below.

- CTCL Client Communicator
- NSE Interactive, BSE Interactive
- NSE EQ Broadcast, NSE FO Broadcast, BSE Broadcast
- GATS
- NCDEX Interactive, MCX Interactive, NCDEX Broadcast, MCX Broadcast (Optional as per setting in Style.txt)
- Database Manager (Task Manager)

5. What are the actions carried out by client communicator?

A. Various messages that are processed through client communicator include

- Login / Logoff requests from clients
- Validate for proper license
- Verify / Update the database
- Validate for risk limits
- Process exchange messages with respective interactive channel
- Backup the Database
- Restore the backup
- Disconnect any client
- Upload open position

6. How can I configure my CTCL IDs on Manager?

A. The user can access the settings dialog from Tools -> Exchange Connection Setting.

Select respective exchange

Market Segment – Equity / Derivatives

Login by – Trader

User ID – CTCL ID of the respective market segment

Member ID – Trading Member ID

Password – CTCL ID password

After setting all above parameters, click on Modify and enter the security password to save the settings.

7. Where can I set the exchange broadcast and interactive parameters?

A. The user can set the settings from Tools -> Exchange Connection Setting. When the user clicks on details button, it will show all the connection parameters. He has to set the proper interactive and broadcast parameters.

Branch ID	CTCL Branch ID
Version No	Running NEAT Version
Work Station No	Not required in case of TAP
Port No	Not required in case of TAP
Local Address	Not required in case of TAP
EICON Card	Not required in case of TAP
Receive Broadcast	Either X.25 Broadcast / NSE TAP Broadcast

If X.25, input call data & host address

If TAP, Enter

Multicast address – Multicast IP configured on TAP (e.g., 233.1.2.5)

Port – Input respective port to receive normal / fast broadcast, as per selected market segment (e.g., 6789 for CM and 6790 for FO)

IP Address – GETS Manager IP address (should be of TAP network IP, in case of multiple LAN cards)

Interactive Either X.25 / TAP IP

If X.25, input call data & host address

If TAP, Enter

Server IP – TAP Server IP

Host Address – Interactive Port as per segment (e.g., 9601-CM, 9602-FO)

UDP Multicast Address If client set UDP setting as “ALL”

Multicast Address – Define at server level (234.1.2.3)

Port – Define at server level (4567-CM and 5678-FO)

UDP Portfolio If client set UDP setting as “Subscribe”

Multicast Address – Define at server level (232.1.2.3)

Port – Define at server level (4560-CM and 5670-FO)

Send to Client whether to send the broadcast to CTCL client

Yes – Sends Broadcast

No – Do not send broadcast

TCP/IP LAN IP for GETS client connectivity with Manager

Local IP Address – Define at server level

Port – Port for GETS client connection (50000)

After setting all above parameters, click on Modify and enter the security password to save the settings.

8. How can I verify the broadcast receiving from exchange?

A. You can verify the broadcast statistics from respective broadcast processor dialog. By default the packets data will increase. If not, go to File -> Counter, which activates the counter.

9. How can I confirm the successful exchange login?

A. Once you send request for exchange login below messages will be displayed in time descending sequence.

09:55:00 System is ready for trading
09:25:59 Market is Close
09:25:59 Message Downloading Completed
09:25:59 Message Downloading Started
09:25:59 Local Database Downloading Completed
09:25:59 Local Database Downloading Started
09:25:59 System Information Downloaded
09:25:56 Login Successfully with Trader Id XXXXX & Broker Id XXXXX
09:23:20 CASH Market Login Request Send to Interactive wait for reply.....

And the market status will be updated in 'GREEN' color on Manager dialog.

10. Broadcast application is not coming up. What is the problem?

A. Broadcast does not get start in below cases.

- Verify in task manager that respective market broadcast processor application is not running. If it is running, end the process and restart from utility -> start applications.
- Verify whether the security / contract uploaded properly. If the security / contract file corrupted, delete all master files created in 'greekmasterfiles' folder in C drive

11. Security / Contract upload is taking much time. Why is it so?

A. Verify whether 'greekmasterfiles' folder exists in C drive and it is shared. If not do it. Verify in task manager whether Database Manager.exe is running. If it is, then end the process and upload the masters.

12. After login to exchange, I am not getting message 'System is ready for trading'. What is the problem?

A. If the message displayed before market open, you should get the message as 'Market is Close'. If the message displayed after market opens / during market hours, then logoff from exchange, close & restart the broadcast application and re-login.

13. Why am I not getting broadcast in GETS client, even I see the broadcast receiving at manager?

A. In case of single manager instance, verify the GETS client connection settings. In case of multiple manager instances, you should make sure that the broadcast connection settings across managers are unique. Connect to broadcast from only one manager and disconnect in all other managers.

In case of multiple managers, it is must that any one of the clients connecting to broadcast to the main server (where broadcast process is running) needs to keep the UDP

settings as ALL. Remaining clients connecting to this main server can set as either Subscribed / ALL. The clients who are on other manager should keep the UDP setting as ALL.

14. I am getting double broadcast in GETS client. How can I resolve this?

A. This case is observed in multiple manager instances. You should make sure that the broadcast connection settings across managers are unique. Connect to broadcast from only one manager and disconnect in all other managers. In only one manager you can configure the 'Send to Client' option as Yes; other managers you can configure it as No.

15. When I do start applications, client communicator is not starting. Why is it so?

A. Verify in task manager that 'Client Communicator.exe' & 'Database Manager.exe' are not running. If it is running, end the process and restart from start applications.

16. When I do start applications, NSE interactive is not starting. Why is it so?

A. Verify in task manager that 'NSE interactive.exe' is not running. If it is running, end the process and restart from start applications.

17. How can I confirm that the data is getting stored in my SQL database?

A. You can confirm the message storage in SQL database using below commands, which you can run in SQL Query Analyzer.

For order information,
select * from orderhistory where dordernumber like 'YYYYMMDD%'

For trade information,
select * from tradelog where dresponseordernumber like 'YYYYMMDD%'

You need to replace the YYYYMMDD with proper date value.

18. When there is exchange disconnection, I am getting all messages downloaded (zero download) after reconnection. How to stop this?

A. If the 'GreekDB.db' file gets corrupted / deleted / renamed and also there is disconnection from exchange, then delete / rename the existing GreekDB.db file and upload the existing trades from SQL database using restore database in client communicator. Then all orders and trades information will be recorded to GreekDB.db file upon which he can login to exchange. This rules out the zero download of messages from NSE.

19. When I disconnect the EQ broadcast / FO broadcast, the respective application is closing. How can I disconnect without closing?

A. This case is observed in multiple manager instances. You can set the broadcast port to any other non-interactive port and start the application.

20. I have multiple managers and the broadcast settings are same in all managers. Even then I am not getting broadcast in GETS client?

A. In case of multiple managers, it is must that any one of the clients connecting to broadcast to the main server (where broadcast process is running) needs to keep the UDP settings as ALL. Remaining clients connecting to this main server can set as either Subscribed / ALL. The clients who are on other manager should keep the UDP setting as ALL.

21. My database disk space utilization is high. How to reduce the utilization?

A. The recommended GETS database location is non-OS drive (other than C drive). If the disk utilization is still high, then from SQL Enterprise Manager, detach the GETS database and delete the existing LDF log file from database store and attach the database. And right click on GETS database -> Properties -> set the recovery mode as simple.

22. What is the location of GETS Manager log files?

A. All the log files of GETS Manager are stored under 'log files' folder in GETS Manager folder.

23. What is the implication of doing 'Backup Database' from client communicator?

A. Calling Backup Database will result in storing all orders and trades information from GreekDB.db file to SQL database.

24. What is the implication of doing 'Restore Database' from client communicator?

A. Calling Restore Database will result in storing all orders and trades information from SQL database to GreekDB.db file.

25. How can I set new password for CTCL ID?

A. If the user wants to change the CTCL ID password, he needs to open connection settings -> select the market segment -> click on 'Set new Password' button -> enter the new password -> Click Modify -> Enter security password -> OK -> Setting is Modified -> OK -> click cancel in connection settings dialog -> Enter Password -> Modify -> Enter security password -> OK -> Setting is Modified -> OK.

26. How can I switch to X.25 from TAP?

A. In the connection settings dialog, click on details button and configure the X.25 parameters (broadcast & interactive) for respective market segment.

27. Where can I view the client login details? Can I disconnect any client from Manager?

A. All client login status is displayed under CTCL client communicator dialog. You can select the logged in client and call utility -> disconnect client.

28. Can I delete pending orders from Manager?

A. You can delete the pending orders from manager, tools -> delete pending orders. You can select particular CTCL user.

29. How can I delete all pending orders at once from Manager?

A. You can delete the pending orders from manager, tools -> delete pending orders. If you select CTCL user as ADMIN1, all pending orders will be deleted.

30. What is Stored Order Response?

A. In manager, you have the option tools -> stored order response. Checking the options will store the order confirmation, modification and cancellation in SQL database.

31. Is the exchange connectivity automatically re-established after disconnection?

A. No. after the exchange disconnection, you need to re-login to the markets from GETS Manager.

32. My Exchange connectivity lost and re-established. How to re-download the order and trade messages, which are submitted / received during this interval?

A. For downloading messages from exchange after connection re-establishment, you need to set the NSESequenceNoDiff parameter under registry in seconds.

Go to Start -> Run -> Type regedit -> Registry Editor will be opened -> Under My Computer -> HKEY_CURRENT_USER -> Software -> GREEK CTCL -> CTCL Manager -> Connection Settings -> EiconCard No 1 -> Port No 1

On right side frame right click on the blank space -> New -> String Value -> Enter NSESequenceNoDiff -> Call Enter -> Select NSESequenceNoDiff and right click -> Modify -> Enter Value Data

The Value Data represents the seconds' count interval for which you wish re-download the messages from exchange from the time of exchange disconnection.