



Certified Penetration Testing Professional

Aircrack-ng Cheat Sheet

Aircrack-ng

Aircrack-ng is a network software suite consisting of a detector, packet sniffer, WEP and WPA/WPA2-PSK cracker, and analysis tool for 802.11 wireless networks. This program runs on both Linux and Windows.

Tools in Aircrack-ng Suite:

1. [Airbase-ng](#)
2. [Aircrack-ng](#)
3. [Airdecap-ng](#)
4. [Airdecloak-ng](#)
5. [Airdriver-ng](#)
6. [Airdrop-ng](#)
7. [Aireplay-ng](#)
8. [Airgraph-ng](#)
9. [Airmon-ng](#)
10. [Airodump-ng](#)
11. [Airolib-ng](#)
12. [Airserv-ng](#)
13. [Airtun-ng](#)
14. [Besside-ng](#)
15. [Dcrack](#)
16. [Easside-ng](#)
17. [Packetforge-ng](#)
18. [Wesside-ng](#)

1. Aircrack-ng

Syntax	
aircrack-ng <options> <replay interface>	
Options	
-a bssid	To set Access Point MAC address
-i iface	Capture packets from this interface
-w WEP key	Use this WEP key to encrypt/decrypt packets
-h MAC	Source mac for MITM mode
-f disallow	Disallow specified client MACs (default: allow)
-W 0 1	[Do not] set WEP flag in beacons 0 1 (default: auto)
-q	Quiet (do not print statistics)
-v	Verbose (print more messages) (long --verbose)
-M	M-I-T-M between [specified] clients and bssids
-A	Ad-Hoc Mode (allows other clients to peer) (long --ad-hoc)
-Y in out both	External packet processing
-c channel	Sets the channel the AP is running on
-X	Hidden ESSID (long --hidden)
-s	Force shared key authentication
-S	Set shared key challenge length (default: 128)
-L	Caffe-Latte attack (long --caffe-latte)
-N	Hirte attack (cfrag attack), creates arp request against wep client (long --cfrag)
-x nbpps	Number of packets per second (default: 100)
-y	Disables responses to broadcast probes
-O	Set all WPA,WEP,open tags. can't be used with -z & -Z
-z type	Sets WPA1 tags. 1=WEP40 2=TKIP 3=WRAP 4=CCMP 5=WEP104
-Z type	Same as -z, but for WPA2
-V type	Fake EAPOL 1=MD5 2=SHA1 3=auto
-F prefix	Write all sent and received frames into pcap file

-P	Respond to all probes, even when specifying ESSIDs
-I interval	Sets beacon interval value in ms
-C seconds	Enables beaconing of probed ESSID values (requires -P)
--help	Displays the usage screen (short -H)
Filter Options	
--bssid <MAC>	BSSID to filter/use (short -b)
--bssids <file>	Read a list of BSSIDs out of that file (short -B)
--client <MAC>	MAC of a client to accept (short -d)
--clients <file>	Read a list of MACs out of that file (short -D)
--essid <ESSID>	Specify a single ESSID (short -e)
--essids <file>	Read a list of ESSIDs out of that file (short -E)

Airbase-ng Commands

Commands	Description
<code>airbase-ng -c 9 -e teddy -N -W 1 rausb0</code>	Hirte Attack in Access Point mode
<code>airbase-ng -c 9 -e teddy -N -W 1 -A rausb0</code>	Hirte Attack in Ad-Hoc mode
<code>airbase-ng -c 9 -e teddy -L -W 1 rausb0</code>	Caffe Latte Attack in Access Point mode
<code>airbase-ng -c 9 -e teddy -s -W 1 wlan0</code>	Shared Key Capture
<code>airbase-ng -c 9 -e teddy -z 2 -W 1 rausb0</code>	WPA Handshake Capture
<code>airbase-ng -c 9 -e teddy -Z 4 -W 1 rausb0</code>	WPA2 Handshake Capture
<code>airbase-ng -e teddy -c 6 wlan0</code>	Basic Fake Access Point
<code>airbase-ng -e teddy -y wlan0</code>	Beacon Flood
<code>airbase-ng -e teddy -c 6 -W 1 -k 1234567890 wlan0</code>	Configure for WEP Encryption

2. Aircrack-ng

Syntax	
aircrack-ng [options] <capture file(s)>	
Options	
Common Options	
-a amode	Force attack mode (1 = static WEP, 2 = WPA/WPA2-PSK)
-e essid	If set, all IVs from networks with the same ESSID will be used
-b bssid	Long version --bssid Select the target network based on the access point's MAC address
-p nbcpu	On SMP systems: # of CPU to use
-q	Enable quiet mode
-C MACs	Long version --combine . Merge the given Aps
-l filename	logs the key to the file specified
Static WEP Cracking Options	
-c	Restrict the search space to alphanumeric characters only (0x20 - 0x7F)
-t	Restrict the search space to binary coded decimal hex characters
-h	Restrict the search space to numeric characters (0x30-0x39)
-d start	Long version --debug . Set the beginning of the WEP key (in hex), for debugging purposes
-m maddr	MAC address to filter WEP data packets
-n nbits	Specify the length of the key: 64 for 40-bit WEP, 128 for 104-bit WEP, etc
-i index	Only keep the IVs that have this key index (1 to 4)
-f fudge	By default, this parameter is set to 2 for 104-bit WEP and to 5 for 40-bit WEP
-k korek	There are 17 korek statistical attacks
-x/-x0	Disable last keybytes brute force
-x1	Enable last keybyte brute forcing (default)
-x2	Enable last two keybytes brute forcing
-X	Disable brute force multithreading (SMP only)

-s	Show the key in ASCII while cracking
-y	Experimental single brute force attack
-z	Invokes the PTW WEP cracking method
-P number	Long version --ptw-debug. Invokes the PTW debug mode: 1 Disable klein, 2 PTW.
-K	Invokes the Korek WEP cracking method.
-D	Long version --wep-decloak. Run in WEP decloak mode
-l	Long version --oneshot
-M number	Specify the maximum number of IVs to use for WEP cracking
-V	Long version --visual-inspection. Run in visual inspection mode
WEP and WPA-PSK cracking options	
-w words	Path to a wordlist or "-" without the quotes for standard in (stdin)
-N	Create a new cracking session and save it to the specified file
-R	Restore cracking session from the specified file
WPA-PSK options	
-E file>	Create EWSA Project file v3
-j file	Create Hashcat v3.6+ Capture file
-J file	Create Hashcat Capture file
-S none	WPA cracking speed test
-Z sec	WPA cracking speed test execution length in seconds
-r database	Utilizes a database generated by airolib-ng as input to determine the WPA key
SIMD Selection	
--simd optimization	Use user-specified SIMD optimization instead of the fastest one
--simd-list	Shows a list of the SIMD optimizations available
Other options	
-H	Long version --help
-u	Long form --cpu-detect

Aircrack-ng Commands

Commands	Description
<code>aircrack-ng -K 128bit.ivs</code>	To crack WEP Key
<code>aircrack-ng -w password.lst *.cap</code>	To crack WPA Key
<code>aircrack-ng --simd=avx wpa.cap -w password.lst</code>	To crack WPA/WPA2-PSK keys using a wordlist with the AVX SIMD optimization
<code>aircrack-ng --new-session current.session -w password.lst,english.txt wpa-01.cap</code>	Cracking session
<code>aircrack-ng --restore-session current.session</code>	It will keep updating the current session every 10 minutes.
<code>aircrack-ng --simd-list</code>	List all the available SIMD optimizations supported by Aircrack-ng

3. Airdecap-ng

Syntax	
<code>airdecap-ng [options] <pcap file></code>	
Options	
<code>-l</code>	Don't remove the 802.11 header
<code>-b bssid</code>	Access point MAC address filter
<code>-k pmk</code>	WPA/WPA2 Pairwise Master Key in hex
<code>-e essid</code>	Target network ascii identifier
<code>-p pass</code>	Target network WPA/WPA2 passphrase
<code>-w key</code>	Target network WEP key in hexadecimal

Airdecap-ng Commands

Commands	Description
<code>airdecap-ng -b <MAC Address> open-network.cap</code>	Removes the wireless headers from an open network (no WEP) capture
<code>airdecap-ng -w <hexadecimal WEP key>wep.cap</code>	Decrypts a WEP-encrypted capture using a hexadecimal WEP key

<code>airdecap-ng -e 'the ssid' -p passphrase tkip.cap</code>	Decrypts a WPA/WPA2 encrypted capture using the passphrase
---	--

4. Airdecloak-ng

Syntax	
<code>airdecloak-ng [options]</code>	
Options	
<code>-i <file></code>	Input capture file
<code>--ssid <ESSID></code>	ESSID of the network to filter
<code>--bssid <BSSID></code>	BSSID of the network to filter
<code>--filters <filters></code>	Apply filters (separated by a comma)
<code>signal</code>	Try to filter based on signal
<code>duplicate_sn</code>	Remove all duplicate sequence numbers for both the AP and the client.
<code>duplicate_sn_ap</code>	Remove duplicate sequence numbers for the AP only.
<code>duplicate_sn_client</code>	Remove duplicate sequence number for the client only
<code>consecutive_sn</code>	Filter based on the fact that IV should be consecutive
<code>duplicate_iv</code>	Remove all duplicate IV
<code>signal_dup_consec_sn</code>	Use signal duplicate and consecutive sequence number
<code>--null-packets</code>	Assume that null packets can be cloaked
<code>--disable-base_filter</code>	Do not apply base filter
<code>--drop-frag</code>	Drop fragmented packets
<code>--help</code>	Displays this usage screen

Airdecloak-ng Commands

Commands	Description
<code>airdecloak-ng <input.pcap> -o <output.pcap></code>	Filters out the cloaking attempts from the input capture file and writes the cleaned packets to the output file.
<code>airdecloak-ng <input.pcap> -v</code>	Enables verbose output to provide more detailed information about the filtering process.

5. Airdriver-ng

Syntax
<code>airdriver-ng <command> [driver number driver name]</code>

Airdriver-ng Commands

Commands	Description
<code>airdriver-ng supported</code>	Lists all supported drivers
<code>airdriver-ng kernel</code>	Lists all in-kernel drivers
<code>airdriver-ng installed</code>	Lists all installed drivers
<code>airdriver-ng loaded</code>	Lists all loaded drivers
<code>airdriver-ng load 34</code>	Loads a driver
<code>airdriver-ng unload 34</code>	Unloads a driver
<code>airdriver-ng reload 34</code>	Reloads a driver
<code>airdriver-ng install 34</code>	Installs a driver
<code>airdriver-ng remove 34</code>	Removes a driver
<code>airdriver-ng install_stack 0</code>	Installs a stack
<code>airdriver-ng remove_stack 0</code>	Removes a stack
<code>airdriver-ng details 34</code>	Prints driver details
<code>airdriver-ng detect</code>	Detects wireless cards

6. Airdrop-ng

Syntax	
airdrop-ng [options] <pcap file>	
Options	
-i	Wireless card in monitor mode to inject from
-t	Airodump txt file in CSV format NOT the pcap
-p	Disable the use of Psycho JIT
-r	Rule File for matched deauths
-u	Updates OUI list

-d	Injection driver. Default is mac80211
-s	Time to sleep between sending each packet
-b	Turn on Rule Debugging
-l	Enable Logging to a file
-n	Time to sleep between loops

Airdrop-ng Commands

Commands	Description
<code>airdrop-ng -i mon0 -t airodump.csv -r rulefile.txt</code>	Start airdrop-ng on mon0 reading from airodump.csv and kick on the rules in rulefile.txt

7. Aireplay-ng

Syntax	
<code>aireplay-ng <options> <replay interface></code>	
Options	
Filter Options	
-b bssid	MAC address, Access Point
-d dmac	MAC address, Destination
-s smac	MAC address, Source
-m len	Minimum packet length
-n len	Maximum packet length
-u type	Frame control, type field
-v subt	Frame control, subtype field
-t tods	Frame control, To DS bit
-f fromds	Frame control, From DS bit
-w iswep	Frame control, WEP bit
Replay options	
-x nbpps	Number of packets per second
-p fctrl	Set frame control word (hex)
-a bssid	Set Access Point MAC address

-c dmac	Set Destination MAC address
-h smac	Set Source MAC address
-e essid	For fakeauth attack or injection test, it sets target AP SSID
-j	arpreply attack: inject FromDS pkts
-g value	Change ring buffer size (default: 8)
-k IP	Set destination IP in fragments
-l IP	Set source IP in fragments
-o npckts	Number of packets per burst (-1)
-q sec	Seconds between keep-alives (-1)
-y prga	Keystream for shared key auth
"-B" or "-bittest"	Bit rate test
"-D"	Disables AP detection
"-F" or "-fast"	Chooses first matching packet
"-R"	Disables /dev/rtn usage
Source Options	
iface	Capture packets from this interface
-r file	Extract packets from this pcap file

Attack Modes

Mode	Description
- -deauth count	Deauthenticate 1 or all stations (-0)
- -fakeauth delay	Fake authentication with AP (-1)
- -interactive	Interactive frame selection (-2)
- -arpreply	Standard ARP-request replay (-3)
- -chopchop	Decrypt/chopchop WEP packet (-4)
- -fragment	Generates valid keystream (-5)
- -test	Injection test (-9)

Aireplay-ng Commands

Commands	Description
<code>aireplay-ng -0 1 -a 00:14:6C:7E:40:80 -c 00:0F:B5:34:30:30 ath0</code>	Deauthentication
<code>aireplay-ng -1 0 -e teddy <Access point MAC address> <Our card MAC address> -y sharedkeyxor ath0</code>	Fake authentication
<code>aireplay-ng -2 <filter options> <replay options> -r <file name> <replay interface></code>	Interactive packet replay
<code>aireplay-ng -3 -b 00:13:10:30:24:9C -h 00:11:22:33:44:55 ath0</code>	ARP request replay attack
<code>aireplay-ng -4 -h 00:09:5B:EC:EE:F2 -b 00:14:6C:7E:40:80 ath0</code>	Korek chopchop attack
<code>aireplay-ng -5 -b 00:14:6C:7E:40:80 -h 00:0F:B5:AB:CB:9D ath0</code>	Fragmentation attack
<code>aireplay-ng -6 -h 00:09:5B:EC:EE:F2 -b 00:13:10:30:24:9C -D rausb0</code>	Cafe Latte attack
<code>aireplay-ng -7 -h 00:09:5B:EC:EE:F2 -D rausb0</code>	Hirte attack
<code>aireplay-ng -8 -b 00:26:0B:2A:BA:40 -h 00:1f:3c:4e:88:46 mon0</code>	Crack WPA migration mode
<code>aireplay-ng -9 wlan0</code>	Injection test
<code>aireplay-ng --test -e teddy -a 00:14:6C:7E:40:80 ath0</code>	Hidden or Specific SSID
<code>airserv-ng -d wlan0</code>	Airserv-ng Test

8. Airgraph-ng

Syntax	
<code>python airgraph-ng -i [airodumpfile.txt] -o [outputfile.png] -g [CAPR OR CPG]</code>	
Options	
<code>-i</code>	Input File
<code>-o</code>	Output File
<code>-g</code>	Graph Type
<code>-a</code>	Print the about
<code>-h</code>	Print this help

Airgraph-ng Commands

Commands	Description
<code>airgraph-ng -i demo.csv -o demo.png -g CAPR</code>	To create a Client to Access point Relationship Graph
<code>airgraph-ng -i demo.csv -o demo.png -g CPG</code>	To create a Client to Probe Request Graph

9. Airmon-ng

Syntax	
<code>airmon-ng <start stop> <interface> [channel] or airmon-ng <check check kill></code>	
Options	
<code>--verbose flag</code>	It gives information about the system as well as details about the wireless card
<code>--debug flag</code>	It will give the same information as verbose and add more details
<code><start stop></code>	Indicates if you wish to start or stop the interface
<code><interface></code>	Specifies the interface
<code>[channel]</code>	Optionally set the card to a specific channel
<code><check check kill></code>	"Check" will show any processes that might interfere with the aircrack-ng suite. "Check kill" will check and kill off processes that might interfere with the aircrack-ng suite

Airmon-ng Commands

Commands	Description
<code>airmon-ng</code>	Check status and/or listing wireless interfaces
<code>airmon-ng check</code>	Checking for interfering processes
<code>airmon-ng check kill</code>	Killing interfering processes
<code>airmon-ng start wlan0</code>	Enable monitor mode
<code>airmon-ng stop wlan0mon</code>	Disable monitor mode

10. Airodump-ng

Syntax	
airodump-ng <options> <interface>[,<interface>,...]	
Options	
--ivs	Save only captured IVs
--gpsd	Use GPSd
--write <prefix>	Dump file prefix
-w	Same as --write
--beacons	Record all beacons in dump file
--update <secs>	Display update delay in seconds
--showack	Prints ack/cts/rts statistics
-h	Hides known stations for --showack
-f <msecs>	Time in ms between hopping channels
--berlin <secs>	Time before removing the AP/client from the screen when no more packets are received
-r <file>	Read packets from that file
-T	While reading packets from a file, simulate the arrival rate of them as if they were "live".
-x <msecs>	Active Scanning Simulation
--manufacturer	Display manufacturer from IEEE OUI list
--uptime	Display AP Uptime from Beacon Timestamp
--wps	Display WPS information
--output-format <formats>	Output format. Possible values: pcap, ivs, csv, gps, kismet, netxml, logcsv
--ignore-negative-one	Removes the message that says fixed channel
--write-interval <seconds>	Output file(s) write interval in seconds
--background <enable>	Override background detection
-n <int>	Minimum AP packets received before for displaying it

Filter Options	
<code>--encrypt <suite></code>	Filter APs by cipher suite
<code>--netmask <netmask></code>	Filter APs by mask
<code>--bssid <bssid></code>	Filter APs by BSSID
<code>--essid <essid></code>	Filter APs by ESSID
<code>--essid-regex <regex></code>	Filter APs by ESSID using a regular expression
<code>-a</code>	Filter unassociated clients
<code>--ht20</code>	Set channel to HT20 (802.11n)
<code>--ht40-</code>	Set channel to HT40- (802.11n)
<code>--ht40+</code>	Set channel to HT40+ (802.11n)
<code>--channel <channels></code>	Capture on specific channels
<code>--band <abg></code>	Band on which airodump-ng should hop
<code>-C <frequencies></code>	Uses these frequencies in MHz to hop
<code>--cswitch <method></code>	Set channel switching method
0	FIFO (default)
1	Round Robin
2	Hop on last
<code>-s</code>	Set channel switching method
<code>--help</code>	Displays this usage screen

Airodump-ng Commands

Commands	Description
<code>airodump-ng -c 8 --bssid <AP MAC address> -w capture ath0</code>	Limiting Data Capture to a Single AP
<code>airodump-ng -c 8 --bssid <AP MAC address> -w capture --ivs ath0</code>	Minimizing Disk Space for Captures
<code>airodump-ng -d <MAC Address> -m FF:FF:FF:00:00:00 wlan0</code>	Selecting all APs starting with similar BSSIDs
<code>airodump-ng -c 11 wlan0</code>	Captures data on channel 11
<code>airodump-ng -c 11,11 wlan0</code>	Sets the capture to repeatedly use channel 11
<code>airodump-ng -c 1,6,11 wlan0</code>	Captures data on channels 1, 6, and 11 using the wlan0 wireless interface

11. Airolib-ng

Syntax	
airolib <database> <operation> [options]	
Operations	Description
- -stats	Output some information about the database Example: airolib-ng testdb --stats
- -sql {sql}	Execute the specified SQL statement Example: airolib-ng testdb --sql 'update essid set prio=(select min(prio)-1 from essid) where essid="VeryImportantESSID";'
- -clean [all]	Perform steps to clean the database from old junk Example: airolib-ng testdb --clean
- -batch	Start batch-processing all combinations of ESSIDs and passwords Example: airolib-ng testdb --batch
- -verify [all]	Verify a set of randomly chosen PMKs Example: airolib-ng testdb --verify
- -export cowpatty {essid} {file}	Export to a cowpatty file Example: airolib-ng testdb --export cowpatty test cowexportoftest
- -import cowpatty {file}	Import a cowpatty file and create the database if it does not exist
- -import {essid passwd} {file}	Import a text flat file as a list of either ESSIDs or passwords and create the database if it does not exist Example: 1) airolib-ng testdb --import essid ssidlist.txt 2) airolib-ng testdb --import passwd password.lst

Airolib-ng Commands

Commands	Description
airolib-ng testdb --stats	Status Operation
airolib-ng testdb --sql 'update essid set prio=(select min(prio)-1 from essid) where essid="VeryImportantESSID";'	SQL Operation
airolib-ng testdb --clean	Clean Operation

<code>airolib-ng testdb --batch</code>	Batch Operation
<code>airolib-ng testdb --verify</code>	Verify Operation
<code>airolib-ng testdb --export cowpatty test cowexportoftest</code>	Cowpatty table Export Operation
<code>airolib-ng testdb --import ssid ssidlist.txt</code>	Import Operation (SSID)
<code>airolib-ng testdb --import passwd password.lst</code>	Import Operation (Password)

12. Aircserv-ng

Syntax	
<code>airserv-ng <opts></code>	
Options	
<code>-p <port></code>	TCP port to listen on
<code>-d <dev></code>	wifi device to serve.
<code>-c <chan></code>	Channel to start on
<code>-v <level></code>	debug level

Aircserv-ng Commands

Commands	Description
<code>airserv-ng -d ath0</code>	Local machine (It has all the components running on the same system)
<code>airserv-ng -d ath0</code>	Remote machine (It has the server running on one system with a specific IP address)

13. Airtun-ng

Syntax	
<code>airtun-ng <options> <replay interface></code>	
Options	
<code>-x nbpps</code>	Maximum number of packets per second
<code>-a bssi</code>	Set Access Point MAC address
<code>-i iface</code>	Capture packets from this interface

-y file	Read PRGA from this file
-w wepkey	Use this WEP-KEY to encrypt packets
-p pass	Use this WPA passphrase to decrypt packets
-e essid	Target network SSID
-t tods	Send frames to AP (1) or client (0) or tunnel them into a WDS/Bridge (2)
-r file	Read frames out of pcap file
-h MAC	source MAC address
-H	Display help. Long-form -help
-s transmitter	Set Transmitter MAC address for WDS Mode
-b	Bidirectional mode
- -repeat	Activates repeat mode. Short form -f
- -bssid <mac>	BSSID to repeat. Short form -d
- -netmask <mask>	Netmask for BSSID filter

Airtun-ng Commands

Commands	Description
<code>airtun-ng <Access point MAC address> -w 1234567890 ath0</code>	wIDS
<code>ifconfig at0 <Target IP> netmask 255.255.255.0 up</code>	WEP injection
<code>airtun-ng <MAC Address> -y fragment-0124-153850.xor ath0</code>	PRGA injection
<code>airtun-ng -a <MAC address used by packets injected> --repeat -bssid <MAC address used by packets injected> -i ath0 wlan0</code>	Repeater Mode
<code>airtun-ng <MAC address used by packets injected> -r ath0one-01.cap ath0</code>	Packet Replay Mode
<code>airtun-ng -t 1 ath0 -h BB:BB:BB:BB:BB:BB -a AA:AA:AA:AA:AA:AA -i ath0</code>	Tunneling traffic into WDS networks or WiFi Bridges

14. Besside-ng

Syntax	
besside-ng [options] <interface>	
Options	Description
-b	Specifies the target's BSSID
-s	Where to upload capture file for cracking
-c	Channel lock
-p	Packages per second to send
-W	Crack only WPA networks
-v	Verbos mode, -vv for even more and so on
-h	Help screen

Besside-ng Commands

Commands	Description
besside-ng mon0	To crack automatically all WEP networks in range and to get possible WPA handshakes
besside-ng -W -c 6 -b <Target MAC Address> mon0	To get WPA handshake from a specific target
cat besside.log	To check the log file

15. Dcrack

Commands	Description
./dcrack.py server	Server set-up
./dcrack.py client <SERVER_IP>	Client set-up
./dcrack.py cmd <SERVER_IP> cap <CAPTURE_FILENAME>	Upload capture file
./dcrack.py cmd <SERVER_IP> dict <WORDLIST_PATH>	Upload wordlist
./dcrack.py cmd <SERVER_IP> crack <BSSID>	Run cracking job
./dcrack.py cmd <SERVER_IP> status	Status

16. Easside-ng

Syntax	
easside-ng <options>	
Options	
-h	Displays the list of options
-v	MAC address of the Access Point
-m	Source MAC address to be used
-i	Source IP address to be used on the wireless LAN.
-r	IP address of the AP router.
-s	IP address of the “buddy” server
-f	Wireless interface name
-c	Locks the card to the specified channel

Easside-ng Commands

Commands	Description
easside-ng -f ath0 <MAC address of AP> -c 9 -s <Buddy server IP>	Specific AP Usage Example

17. Packetforge-ng

Syntax	
packetforge-ng <mode> <options>	
Options	
-p <fctrl>	Set frame control word
-a <bssid>	Set Access Point MAC address
-c <dmac>	Set Destination MAC address
-h <smac>	Set Source MAC address
-j	Set FromDS bit
-o	Clear ToDS bit
-e	Disables WEP encryption
-k <ip[:port]>	Set Destination IP Port

<code>-l <ip[:port]></code>	Set Source IP port
<code>-t ttl</code>	Set Time to Live
<code>-w <file></code>	Write packet to this pcap file
<code>-r <file></code>	Read packet from this raw file
<code>-y <file></code>	Read PRGA from this file

Packetforge-ng Commands

Commands	Description
<code>packetforge-ng -0 -a <AP MAC> -h <Source MAC> -k <Source IP> -l <Destination IP> -y <PRGA XOR file> -w <Output file></code>	Generating an arp request packet
<code>packetforge-ng --null -s 42 -a BSSID -h SMAC -w short-packet.cap -y fragment.xor</code>	Generating a null packet
<code>packetforge-ng -9 -r input.cap -y keystream.xor -w output.cap</code>	Generating a custom packet

18. Wesside-ng

Syntax	
<code>wesside-ng <opts> -i <wireless interface name></code>	
Options	
<code>-h</code>	Displays the list of options
<code>-i</code>	Wireless interface name
<code>-n</code>	Network IP as in “who has destination IP (netip) tell source IP (myip)”
<code>-m</code>	MY IP “who has destination IP (netip) tell source IP (myip)”
<code>-a</code>	Source MAC address
<code>-c</code>	Do not start aircrack-ng
<code>-f</code>	Allows the highest channel for scanning to be defined
<code>-k</code>	Ignores ACKs since some cards/drivers do not report them
<code>-p</code>	Determines the minimum number of bytes of PRGA which are gathered
<code>-t</code>	For each number of IVs specified, restart the aircrack-ng PTW engine
<code>-v</code>	Wireless access point MAC address

Wesside-ng Commands

Commands	Description
<code>wesside-ng -i wlan0</code>	Initiate the wesside-ng tool with a specific wireless interface