



Certified Penetration Testing Professional

SMBeagle Cheat Sheet

SMBeagle

Source: <https://github.com>

SMBeagle is a cross-platform (SMB) fileshare auditing tool that hunts out all files it can see in the network and reports if the file can be read and/or written. All these findings are streamed out to either a CSV file or an elasticsearch host. SMBeagle can scan an entire network to discover all accessible SMB shares.

Syntax
<code>SMBeagle.exe -e [Target network]</code>

Options	
<code>-c, --csv-file</code>	Outputs results to a CSV file by providing the file path.
<code>-e, --elasticsearch-host</code>	Outputs results to Elasticsearch by providing the Elasticsearch hostname.
<code>--elasticsearch-port</code>	Specifies a custom port for Elasticsearch if required.
<code>-f, --fast</code>	Enumerates only one file's permissions per directory for a faster scan.
<code>-l, --scan-local-shares</code>	Scans the local shares on the machine where SMBeagle is run.
<code>-D, --disable-network-discovery</code>	Disables network discovery, requiring manual specification of networks to scan.
<code>-n, --network</code>	Manually adds a network to scan. Multiple networks can be specified.
<code>-N, --exclude-network <network></code>	Excludes specified networks from scanning. Multiple networks can be specified.

-h, --host <host>	Manually adds a host to scan.
-H, --exclude-host <host>	Excludes specified hosts from scanning.
-q, --quiet	Disables unnecessary output for a quieter run.
-S, --exclude-share <share>	Excludes shares with the specified name from scanning. Multiple shares can be specified.
-s, --share <share>	Only scans shares with the specified name. Multiple shares can be specified.
-E, --exclude-hidden-shares	Excludes hidden shares (shares ending with \$).
-v, --verbose	Provides more detailed output during the scan.
-m, --max-network-cidr-size	Sets the maximum network size (in CIDR notation) to scan for SMB hosts. Default is 20.
-A, --dont-enumerate-acls	Skips the enumeration of file ACLs for a faster scan.
-d, --domain <domain>	Specifies the domain for connecting to SMB.
-u, --username <username>	Specifies the username for connecting to SMB. This is mandatory on Linux.
-p, --password <password>	Specifies the password for connecting to SMB. This is mandatory on Linux.
--help	Displays the help screen with all available options.
--version	Displays version information for SMBeagle.

SMBeagle Commands

Command	Description
SMBeagle.exe -e [Target network]	Starts network scanning and directories' enumeration on the hosts present in the target network
SMBeagle.exe -l -c output3.csv	Scans the local shares and output to a CSV file
./SMBeagle.exe -c out.csv -f	Output to a CSV file with fast enumeration
./SMBeagle.exe -n 1.0.0.1/32	Public IP scanning by declaring manually
SMBeagle -e 127.0.0.1	Outputs the results of the scan to an Elasticsearch instance running at the specified IP address (127.0.0.1)
SMBeagle -c out.csv -e 127.0.0.1	Output to Elasticsearch and CSV

SMBBeagle -D -e 127.0.0.1 -n 192.168.12.0/23 192.168.15.0/24	Disable network discovery and provide manual networks
SMBBeagle -A -e 127.0.0.1	Skips the enumeration of Access Control Lists (ACLs) to speed up the scan