

14-DAY FREE TRIAL GUIDE — REVISION 2

14-Day Free Trial Guide

Try ODRE PQC for 14 days without purchasing a paid license or entering a License ID or License Key.

02

DOCUMENT SUMMARY

Summary

PRODUCT SCOPE

14-day free trial guide. Starts without payment, email, or Paid Key; covers the Trial period and 1 Device 1 Trial.

TRUST BOUNDARY

The existing client is unchanged. See PQC Trust Boundary in Product Overview.

CUSTOMER DATA PLANE

Application request/response traffic remains inside customer infrastructure.

ODRE CONTROL PLANE

Outbound HTTPS 443 is used only for Trial activation and status.

VERIFIED

Official PS1/SH installer entry points on all 6 supported OS; Trial start, expiry, and Fail-Closed contract.

NOT VERIFIED

Performance/throughput and Container/Kubernetes deployment.

CUSTOMER RESPONSIBILITY

Application logic, authentication/authorization, protected routes, and actual integration testing.

KNOWN LIMITATION

verify is an independent self-test, not a customer business integration test.

This document records ODRE PQC self-verification. It is not independent third-party certification.

03

DATA PLANE / CONTROL PLANE

Customer Data Plane

Customer Client -> HTTPS/TLS -> Customer FastAPI Application -> ODRE PQC Security Boundary -> Protected Handler

Customer application traffic does not pass through ODRE servers.

ODRE Control Plane

Customer ODRE PQC Installation -> Outbound HTTPS 443 -> ODRE Control Services (Trial activation)

No customer application request/response body is sent to the ODRE license/control service.

04

QUICK START

Free download · No email · Download does not start Trial · 14 days from first successful activation · 1 Device
1 Trial · Reinstall cannot reset it · Protected Route fails closed after expiry · Convert to Paid without
reinstalling.

1. Verify Manifest signature and SHA-256 of the official installer (Windows: PS1 / Linux: SH).
2. Run the installer for the OS; platform is detected automatically.
3. On a new installation run init once, then doctor and verify once.
4. Connect FastAPI with install(app).
5. Run Trial and confirm status, start, and expiry. No payment, email, or Paid Key is required.
6. Start the server and verify Gateway -> Core -> Handler. Status alone is not proof of integration.

Direct Wheel installation is not the current customer installation contract.

05

WHEEL / PYTHON VENV

0. Before you begin

This guide is for server operators and developers starting a free trial. A payment confirmation email is not a prerequisite.

Requirement

Condition

OS / CPU

Windows Server 2022 AMD64 or Ubuntu 24.04 AMD64

Python

CPython 3.12

Permissions

Permission to install and create protected state paths. The service and CLI must access the same state path.

Network

Access to pip dependency downloads and the official HTTPS activation service

Time

Maintain a trustworthy system clock. Do not roll it back.

Backup

An approved recovery point for application code and configuration

Components

Core 0.2.9, Commercial 0.2.9.post4, and Gateway integration appropriate for the customer application

The software manages the Trial ticket, installation private key and local state. Customers are not asked to enter a paid License Key.

06

WHEEL / PYTHON VENV

1. Trial terms and behavior

Free download · No email required · Downloading does not start the Trial · 14 days from the first successful activation · 1 Device, 1 Trial · Downloading again or reinstalling does not reset the period · Protected Routes fail

closed after expiry · Convert to Paid without reinstalling.

Term

Behavior

Free download / no email

The Trial-start request sends no email, payment details or Paid credentials.

Not started by download

The download session is separate from Trial activation.

14 days from activation

14 days from the server's issued_at to expires_at

1 Device, 1 Trial

One Trial bound to device identity. Retries retain the existing period.

Download again / reinstall

Does not create another free period for the same device.

Expiry

Blocks new protected requests. Authorized public routes retain their existing policy.

Convert after purchase

Approve on the web using the same installation identity, then use Paid entitlement.

“Without a license” means a trial without proof of a paid purchase. The period and device binding are still verified against a server-signed Trial entitlement.

07

WHEEL / PYTHON VENV

2. Download and integrity verification

Obtain the official bundle and the Manifest, signatures and installation instructions for that same release. Downloading does not consume any of the 14 days.

1. Verify the Release Manifest signature against an independent official trust anchor.
2. Compare file names, sizes and SHA-256 hashes, including installers, verifiers and trust configuration.
3. Confirm that the approved installer enforces verification before installation, then run it. Stop on any mismatch.

Check file SHA-256

```
Get-FileHash -Algorithm SHA256 -LiteralPath "<ARTIFACT_PATH>"
```

```
sha256sum -- "<ARTIFACT_PATH>"
```

<ARTIFACT_PATH> is the downloaded file path. Hash equality alone does not authenticate a publisher.

Successful pip

installation, ZIP readability or CRC checks do not prove integrity either.

The existing verifier on page 9 is for Core 0.2.9 only. It does not verify the complete Commercial post4, Gateway or Native bundle. Each component needs its own official Manifest and approved installation path.

This guide does not invent a final bundle hash. Do not reuse Commercial post3 hashes for post4. If the verifier or trust material is

missing, obtain the correct distribution; do not bypass verification with ordinary pip.

08

WHEEL / PYTHON VENV

3. Pre-installation checks

Check

PASS condition

If it fails

OS / CPU / Python

Exact supported combination

Stop installation; contact support.

System time

NTP synchronized; no significant drift

Resolve the clock issue.

HTTPS egress

Outbound 443 to the official service

Obtain approval for firewall changes.

Permissions / ACL

Administrator/root and restricted state-path

permissions

Correct the permissions design.

Integrity

Manifest signature and every hash match

Discard the artifact; download again.

Backup

Application rollback point available

Back up before making changes.

A backup may include approved copies of application code and configuration. Do not clone an existing installation identity, device private key, refresh credential or Offline Lease to a new VM or container.

09

04 — INSTALLATION

Official entry point

After the integrity check on page 7, run only the command for the OS.

Windows Server 2022 AMD64

```
.\install-odre-pqc.ps1
```

Linux AMD64

Ubuntu 22.04 / Ubuntu 24.04 / Debian 12 / Rocky Linux 9.8 / AlmaLinux 9.8

```
sudo ./install-odre-pqc.sh
```

The installer detects the platform and executes the approved flow. Do not manually wire Core, Native, Gateway, policy, or pins. Preserve output and stop if signature, hash, platform, permission, or prerequisite checks fail.

10

WHEEL / PYTHON VENV

4.1 init -> doctor -> verify

Continue only after the official installation procedure has prepared the complete Wheel configuration and customer .venv, with dependency and version checks complete. The Core-only installation on page 9 does not

meet that condition by itself.

Windows PowerShell - new installations only

& .\venv\Scripts\odre-pqc.exe init

& .\venv\Scripts\odre-pqc.exe doctor

& .\venv\Scripts\odre-pqc.exe verify

Ubuntu Bash - new installations only

.venv/bin/odre-pqc init

.venv/bin/odre-pqc doctor

.venv/bin/odre-pqc verify

init prepares a new installation identity, configuration and state. Do not repeat init on an existing installation or

update with config/keys/runtime/state. Never delete state or keys to bypass this restriction.

doctor diagnoses the installation environment; verify is an independent Core self-test, not a customer Gateway/Handler integration test. It need not be repeated after Trial activation or Gateway integration.

Rerun a

failed check only after correcting its cause.

11

WHEEL / PYTHON VENV

5. Diagnostics, self-test and status

Command / check

Meaning

pip check

Checks for Python dependency conflicts

odre-pqc doctor

Diagnoses the installation environment before Gateway integration

odre-pqc verify

Independent Core self-test using temporary keys and a temporary DB

odre-pqc-commercial trial

Starts the device Trial; 14 days from first successful activation

Commercial status

Checks signature, device binding, Trial period and installation integrity

odre-pqc status

Checks authenticated runtime evidence from the running Core

Gateway integration test

Separately verifies the real request path to the business Handler

verify PASS does not automatically prove the state of a running server. Core status checks HMAC, nonce, freshness, and provider/key/security/worker state, among other runtime evidence.

If the server is not running or the correct authenticated target cannot be reached, the result may be Runtime UNKNOWN / PQC PROTECTION: BLOCKED. Do not substitute the healthy status of another Core for Gateway Private Core integration evidence.

12

WHEEL / PYTHON VENV

6. Start the Trial - no payment or email

After the Core self-test and the Gateway entitlement gate integration on page 14, run the command for your OS

under the same account and state path that the service will use.

Windows PowerShell

```
& .\venv\Scripts\odre-pqc-commercial.exe trial
```

Ubuntu Bash

```
./venv/bin/odre-pqc-commercial trial
```

The CLI creates and stores the installation identity and handles download/Trial tickets and the device challenge.

It submits signed proof of device possession; it does not send the private key to the server. No License ID, License Key or email input is required.

Expected result: ACTIVATION: ACTIVE / LEASE: TRIAL_VALID / INTEGRITY: PASS. TRIAL_STARTED_AT and TRIAL_EXPIRES_AT define the server-issued period. Do not relabel the Wheel Trial state as Paid LEASE_VALID.

Running the same command again does not restart the period. If the server approved activation but its response was not received, recover the same Trial using the preserved identity and ticket. Do not delete existing state.

13

```
from fastapi import FastAPI
from odre_pqc import install
```

```
app = FastAPI()
install(app)
```

WHEEL / PYTHON VENV

7. Check status -> start servers -> runtime

1) Commercial status

```
& .\venv\Scripts\odre-pqc-commercial.exe status
```

Ubuntu

```
./venv/bin/odre-pqc-commercial status
```

For the Trial, check ACTIVE / TRIAL_VALID / INTEGRITY: PASS. After expiry, EXPIRED / TRIAL_EXPIRED is displayed. The absence of a License ID or Paid Key is normal for the Trial.

2) Start the customer server + Gateway Private Core

Use the approved start command for the customer application. Bind Private Core to loopback only and route Nginx's public paths through the Gateway. No customer module name or port is assumed here.

3) Check the running Core

```
& .\venv\Scripts\odre-pqc.exe status
```

Ubuntu

```
./venv/bin/odre-pqc status
```

The Core status target and authentication settings must match the actual Gateway Private Core. Then verify the real business request path on page 15.

14

WHEEL / PYTHON VENV

8. FastAPI / Server Gateway integration

External HTTPS Client -> Nginx -> FastAPI / ODRE Server Gateway -> Python PQC Client -> ODRE v3 ->

Private Core -> Protected Handler

Add the following call using host and private_core returned by your existing build_host(...) integration. Run it once before starting the two ASGI servers.

```
from odre_pqc_commercial import install_gateway_license_gate
```

```
install_gateway_license_gate(host, private_core)
```

Integration item

Required check

host

GatewayDispatch returned by the existing build_host; forwards designated

protected routes to the Gateway

private_core

The actual Private Core FastAPI object for this Gateway

Entitlement gate

Checks entitlement on each new request at both Gateway and Private Core

entry

identity / key / trust

Retain existing ODRE v3-specific configuration. Do not confuse Trial

installation identity with cryptographic protocol keys.

Public paths

Existing host health and activation control-plane paths retain their policies.

This call does not create a Gateway or automatically protect every customer API. Your existing integration must define protected

routes, prevent Handler bypass, and configure startup/shutdown.

15

WHEEL / PYTHON VENV

9. Verify Gateway / Core / Handler

Check the running customer application in an isolated validation environment. This is not another run of the independent verify command.

Check

Expected behavior

Normal request

Preserves existing HTTPS API semantics and executes the Handler

v3 path

Actual Gateway handshake and encrypted requests/responses

Session reuse

Trial entitlement checked on every request, even with an existing session

Expiry

New protected requests rejected from expiry onward; no increase in Handler

execution count

Private Core

Direct entry also applies the entitlement gate; never publicly exposed

Public health

Existing response retained independently of Trial expiry

Integration status

Record Core status and actual Handler verification separately

A Handler already admitted and running before expiry is not forcibly interrupted. The contract blocks new protected requests entering after expiry.

Retain existing security regressions and customer-specific business correctness checks. HTTP success counts alone do not prove load performance or coverage of every security path.

16

WHEEL / PYTHON VENV

10. Normal operation during the Trial

The Trial remains valid until the absolute expiry time issued at first activation. Restarting a server or job does not create another 14 days.

Item

Operational guidance

Period

Check TRIAL_STARTED_AT / TRIAL_EXPIRES_AT in Commercial status.

Renewal

No renew operation extends the Trial period. Distinguish this from Paid renew.

Connectivity loss

Valid local signed entitlement is verified without an online call for every request.

State protection

Retain Windows DPAPI and restricted ACLs, or Linux encrypted state and restricted permissions.

Updates

Keep identity and state; verify new release hashes and dependencies.

Errors

Keep protected paths blocked while resolving the cause.

Fail-closed applies if system time is untrustworthy or entitlement, device binding or installation integrity verification fails. Adjusting the clock to extend the Trial is not supported.

17

WHEEL / PYTHON VENV

11. 1 Device, 1 Trial

A Trial is bound to the server's device-identity record. Deleting an installation folder or venv does not delete that record.

Situation

Result

Retry on the same installation

Retains the original Trial start and expiry times

Download again

A new download creates no new Trial entitlement

Reinstall

Does not reset the same device's free period

Copy state to another device

Rejected because signed device/identity binding does not match

Concurrent start

No duplicate Trial issued for the same device

Run trial after expiry

Returns the existing expired/already-used state, not a new free period

Purchase

Activate separate Paid entitlement on the same installation

No claim is made of complete protection when an administrator/root attacker controls OS identity and the trust

store. Do not clone devices/state or alter identifiers to bypass Trial policy.

18

WHEEL / PYTHON VENV

12. Troubleshooting

Error / state

Customer action

TRIAL_ALREADY_USED

Check the device's Trial history. Do not try to reset it by downloading or installing again.

TRIAL_EXPIRED

Keep protected paths blocked; convert to Paid to continue.

CLOCK_TAMPER_DETECTED

Check time synchronization and change history. Do not delete state.

ENTITLEMENT_BINDING_INVALID

Check for mixed state from another device, identity or key.

ENTITLEMENT_SIGNATURE_INVALID

Check the official entitlement response and file integrity. Do not edit it.

RUNTIME_INTEGRITY_FAILURE

Verify the official Core and installation integrity.

AUTHORITY_UNREACHABLE

Check DNS, TLS and official-service connectivity, then retry the same command.

OPERATION_IN_PROGRESS

Complete the active activation/renewal CLI operation first.

PAID_INSTALLATION_EXISTS

Do not revert an existing Paid installation to Trial.

Do not disable the gate or expose a Handler directly to eliminate protected-path 503 responses. Retain error codes from the CLI, not secret state in support tickets.

19

WHEEL / PYTHON VENV

13. Expiry, clock rollback and fail-closed

Protected Routes fail closed after Trial expiry. No new request is admitted at or after signed expires_at; there is

no additional Trial grace period.

Wheel Trial verification

The signed entitlement binds device, installation identity, key, product and period. The last checked time is retained in encrypted state; a monotonic clock reference is also used while running so clock rollback cannot extend expiry.

Install the entitlement gate at both Gateway and Private Core. Even an existing session requires entitlement checks for new requests. Missing/corrupt entitlement files, time inconsistency, expiry and integrity failure are reasons to block.

Preserving existing Native protection

The Phase 3B Native EXE has a separate monotonic deadline, key removal at expiry, Named Pipe IPC and broker controls. Do not delete that EXE or replace it with the Wheel gate. Historical Native PASS results are not

reused as PASS evidence for this Wheel path.

Do not fall back to plaintext/classical transport after entitlement verification fails. The customer's normal HTTPS

connection is distinct from such fallback.

20

WHEEL / PYTHON VENV

14. Updates, reinstallation and state

Do not rerun init on an existing installation. Preserve Core config/keys/runtime/state and the Commercial installation identity.

Operation

Precaution

Commercial update

Use the approved new Wheel; retain the protected state path.

Trial retry

Recover the existing server record with the same trial command.

App restart

No period reset. Install the gate before server startup.

Restore

Do not import another device's Trial, Lease or keys.

Paid conversion

Approve activate on the web for the same installation; no venv/Core/Gateway reinstall.

Device replacement

Not a Trial-period reissuance process; check support policy.

Deleting state files to make an error disappear is not a valid recovery procedure. Do not manually edit private

keys, Trial tickets or signed entitlements.

21

WHEEL / PYTHON VENV

15. Requesting technical support

Customer support and inquiries: odreai2025@gmail.com

Safe to send

Do not send

Core / Commercial / Python / OS versions

Private keys or state encryption keys

UTC time and error codes

Trial tickets; access/refresh/poll tokens

Redacted installation ID and start/expiry times

Complete local state files

Redacted doctor / verify / status results

Customer business request/response bodies

Official filenames and SHA-256 hashes

Full environment-variable, configuration or DB dumps

Starting the Trial requires no email. This address is an optional support channel if a problem occurs, not a mandatory step in Trial activation.

22

17 — QUICK INSTALLATION CHECKLIST

- [] Verify official Manifest signature and SHA-256
- [] Confirm supported OS, time, HTTPS 443, permissions, backup
- [] Run `.\install-odre-pqc.ps1` or `sudo ./install-odre-pqc.sh`
- [] New installation: `odre-pqc init`
- [] Run `odre-pqc doctor` and `odre-pqc verify`
- [] Connect FastAPI with `from odre_pqc import install and install(app)`
- [] Start Trial without License ID or License Key
- [] Confirm ACTIVE / TRIAL_VALID / INTEGRITY: PASS and expiry
- [] Start customer server and confirm running Core status
- [] Test Gateway -> Core -> Handler
- [] Confirm replay, bypass, and fallback are blocked
- [] Preserve installation identity/state during update or reinstall
- [] Approve Production only after all required gates PASS

23

WHEEL / PYTHON VENV

17. Installation checklist

For the Wheel path. Native users follow pages 28-31; the same integrity, state-preservation and real Handler-verification principles apply.

- [] Select the bundle's installation path; verify Manifest signatures and SHA-256 hashes
- [] Use the approved installer to configure Core, Commercial, Gateway, dependencies and CLI
- [] Do not mistake successful Core-only installation for complete bundle installation
- [] Complete pip check and version checks; run init once for new installations only
- [] doctor -> verify succeeds; distinguish self-tests from business integration tests
- [] Connect entitlementment gates to Gateway host and Private Core
- [] Commercial trial: check ACTIVE / TRIAL_VALID / INTEGRITY: PASS
- [] Retries do not reset start or expiry times
- [] Start the customer server and Private Core; check the actual runtime target
- [] Verify Gateway -> v3 -> Private Core -> Handler
- [] In isolation, confirm zero new Handler executions after expiry and preserved public routes
- [] Preserve existing identity and state during updates and Paid conversion

RELEASE AUTHORITY

ODRE PQC 0.3.1 RC1 | Release 63 | Final Closure g269 | Official Supported OS 6/6 PASS | Negative Gate 18/18 PASS

Sealed Core odre_pqc 0.2.9 is an independent component version.