ALPHA MICROSYSTEMS
RIGHT. FROM THE START.

AlphaWRITE â
Installation Instructions

DSM-00151-03

© 1995 Alpha Microsystems

REVISIONS INCORPORATED	
REVISION	DATE
00	March 1990
01	April 1991
02	May 1992
03	July 1993

AlphaWRITE Installation Instructions.

To re-order this document, request part number DSO-10151-00.

This document applies to AlphaWRITE 2.1C and later

The information contained in this manual is believed to be accurate and reliable. However, no responsibility for the accuracy, completeness or use of this information is assumed by Alpha Microsystems.

This document may contain references to products covered under U.S. Patent Number 4,530,048.

The following are registered trademarks of Alpha Microsystems, Santa Ana, CA 92799:

AMIGOS
AMOS
Alpha Micro
AlphaACCOUNTING
AlphaBASIC
AlphaCALC
AlphaCOBOL
AlphaDDE
AlphaFORTRAN 77
AlphaLAN
AlphaLEDGER
AlphaMAIL
AlphaMATE
AlphaNET
AlphaPASCAL
AlphaRJE
AlphaWRITE
CASELODE
OmniBASIC
VER-A-TEL
VIDEOTRAX

The following are trademarks of Alpha Microsystems, Santa Ana, CA 92799:

AlphaBASIC PLUS
AlphaVUE
AM-PC
AMTEC
DART
ESP
MULTI
*in*Sight/am
*in*Front/am

All other copyrights and trademarks are the property of their respective holders.

ALPHA MICROSYSTEMS
2722 S. Fairview St.
P.O. Box 25059
Santa Ana, CA 92799

TABLE OF CONTENTS

PRODUCTION NOTES..... v

CHAPTER ONE - INTRODUCTION
HOW THIS MANUAL IS ORGANIZED..... 1-1
CONVENTIONS USED IN THIS MANUAL..... 1-2
THE AlphaWRITE DOCUMENTATION LIBRARY..... 1-3
OTHER ALPHA MICROSYSTEMS DOCUMENTATION..... 1-4

CHAPTER TWO - INSTALLATION OVERVIEW
INSTALLATION POSSIBILITIES..... 2-1
UPGRADING FROM AlphaWRITE PRE-1.2A..... 2-2
INSTALLATION PREREQUISITES..... 2-2
Disk Space Requirements..... 2-2
Ersatz Accounts..... 2-3
Operating System Version..... 2-3
User Memory Partition Size..... 2-3
POSTSCRIPT LASER PRINTING..... 2-3
THE PREVIEW COMMAND AND AMIGOS..... 2-4
AlphaWRITE SOFTWARE PATCHES..... 2-4

CHAPTER THREE - FIRST TIME AlphaWRITE INSTALLATION..... 3-1
INSTALLATION STEPS: SUMMARY..... 3-1
STEP ONE: DEFINE THE WRT: ERSATZ NAME..... 3-2
STEP TWO DEFINE FWT: ERSATZ NAME (OPTIONAL)..... 3-2
STEP THREE: RESET YOUR COMPUTER..... 3-2
STEP FOUR: LOG TO WRT:..... 3-2
STEP FIVE: DOWNLOAD THE AlphaWRITE SOFTWARE..... 3-3
STEP SIX: VERIFYING THE SOFTWARE FILES IN WRT:..... 3-3
STEP SEVEN: COPY AlphaWRITE FILES TO SYSTEM ACCOUNTS..... 3-4
STEP EIGHT: ACTIVATE AlphaWRITE'S INITIALIZATION FILE..... 3-4
STEP NINE: CALL UP AlphaWRITE..... 3-5
WHAT'S NEXT?..... 3-6

CHAPTER THREE - UPGRADE INSTALLATION
INSTALLATION STEPS: SUMMARY..... 4-1
UPGRADES FROM AlphaWRITE 2.X - PRODUCT INSTALLATION CODE..... 4-2
STEP ONE: DEFINE THE WRT: ERSATZ NAME..... 4-2
STEP TWO DEFINE FWT: ERSATZ NAME (OPTIONAL)..... 4-2
STEP THREE: MODIFY YOUR SYSTEM INITIALIZATION COMMAND FILE..... 4-3
STEP FOUR: RESET YOUR COMPUTER..... 4-3
STEP FIVE: LOG TO WRT:..... 4-3
STEP SIX: DOWNLOAD THE AlphaWRITE SOFTWARE TO YOUR COMPUTER 4-3
STEP SEVEN: VERIFYING THE SOFTWARE FILES IN WRT:..... 4-4
STEP EIGHT: COPY AlphaWRITE FILES TO SYSTEM ACCOUNTS..... 4-5

STEP NINE: MODIFY AlphaWRITE'S INITIALIZATION FILE.....4-5
STEP TEN: CALL UP AlphaWRITE.....4-6
STEP ELEVEN: REMOVE OLDER VERSION AlphaWRITE FILES.....4-6
STEP TWELVE: REINSTATE SYSTEM COMMANDS.....4-7
WHAT'S NEXT?.....4-7

CHAPTER FIVE - AlphaWRITE'S MEMORY REQUIREMENTS
RULES FOR MEMORY ALLOCATION.....5-1
Loading WRITE.LIT & WRT000.OVR.....5-1
Initialization Overlay.....5-2
Command Line Processing.....5-2
Printer Definitions.....5-2
Function Key Translation Tables.....5-2
Message Files.....5-3
Main Menu.....5-3
Loading Documents.....5-3
ESTIMATING MEMORY USE.....5-3
LOADING FILES INTO SYSTEM MEMORY.....5-3
Configuration Example.....5-4
DETERMINING USER MEMORY PARTITION SIZE.....5-4
AlphaWRITE 2.1A and Later Memory Use Chart.....5-5
AlphaWRITE'S MEMORY SEARCH PATH.....5-5

CHAPTER SIX - COMPATIBILITY ISSUES AND UPGRADE TIPS
DOCUMENT CONVERSION TIPS.....6-1
CONVERTING OLDER AlphaWRITE DOCUMENTS.....6-1
AlphaWRITE DICTIONARY COMPATIBILITY.....6-2
HARDWARE HANDSHAKING.....6-2
FIRST TIME LASER PRINTING TIPS.....6-2
UPGRADES TO AlphaWRITE 2.X FROM AlphaWRITE 1.2A.....6-3
System Level Enhancements introduced in AlphaWRITE 2.0.....6-3
Publishing Features.....6-3
Editing Features.....6-4
OPERATIONAL CHANGES FROM AlphaWRITE 1.2A.....6-4
UPGRADE TIPS ESPECIALLY FOR AlphaWRITE 1.2A USERS
UPGRADING TO AlphaWRITE 2.X.....6-6
End of Paragraph Markers.....6-7
Using the Menu Key.....6-7
Upgrading Documents and First Time Laser Printing.....6-7
Text Display Ruler.....6-7
Instructions in Command Line Processing Script Files.....6-8
Lines Per Inch Setting.....6-8

APPENDIX A - AlphaWRITE'S FILES

APPENDIX B - AlphaWRITE's SAMPLE INITIALIZATION FILE: WRITE.NEW

APPENDIX C - AlphaWRITE's PRINTER DRIVER

APPENDIX E - USING THE SYSDCT UTILITY
USING THE SYSDCT UTILITY.....D-1
Characteristics..... D-1
Format.....D-1
Defaults.....D-1
Operation..... D-2
Messages.....D-2

DOCUMENT HISTORY

INDEX

READERS' COMMENTS

PRODUCTION NOTES

We maintain AlphaWRITE's documentation—including all of its on-line help files—using the current version of the AlphaWRITE software. All pages for this edition were edited using AlphaWRITE 2.1C.

We print AlphaWRITE's documentation using an HP LaserJet 4 printer and the LASWRT printer driver.

We print on-line help files to a disk file using a custom printer driver capable of outputting terminal display codes. This custom printer driver is a modified version of AlphaWRITE's Miscellaneous printer driver (MISC.PDV).

The title and first edition pages were generated by a PostScript program file.

The text body is set in 11 point Helvetica with some examples appearing in 10 point Courier.

Other special print emphasis features we use are described in Chapter 1 - "Introduction."

CHAPTER ONE
INTRODUCTION

These *Installation Instructions* give you step-by-step information for putting the AlphaWRITE Word Processing software on your computer and getting it up and running.

HOW THIS MANUAL IS ORGANIZED

The instructions are divided into chapters to make the various installation possibilities easier to follow. Supplemental information in the appendices provide detailed information about AlphaWRITE's software. The chart below describes the contents of each chapter and appendix.

CHAPTER /APPENDIX	DESCRIPTION
TWO	"Installation Overview." Describes the level of experience you should have and the topics you need to be familiar with in order to successfully install AlphaWRITE. This chapter also gives general information on the two types of installation: first time and upgrade.
THREE	"First Time AlphaWRITE Installation." Gives step-by-step instructions for first time AlphaWRITE software installation.
FOUR	"Upgrade Installation." The step-by-step instructions show you how to upgrade your existing AlphaWRITE software to the current version.
FIVE	"AlphaWRITE's Memory Requirements." Provides technical information and guidelines to help you make the most efficient use of your computer resources.

CHAPTER /APPENDIX	DESCRIPTION
SIX	"Compatibility Issues and Upgrade Tips." This section is especially for customers upgrading from AlphaWRITE 1.2A to the current version of AlphaWRITE. It describes document conversion issues and some compatibility issues.
A	"AlphaWRITE's Files." This appendix lists AlphaWRITE file names, their destination accounts, and a brief description of their purpose.
B	"AlphaWRITE's Sample Initialization File: WRITE.NEW." This appendix contains a listing of the sample initialization file accompanying your AlphaWRITE software.
C	"AlphaWRITE's Printer Drivers." The chart in this section shows the current AlphaWRITE version's printer driver file names and the printers each supports.
D	"Using the SYSDCT Utility." SYSDCT load the index component of certain AlphaWRITE dictionaries into system memory. This appendix gives the information on SYSDCT's operation.

CONVENTIONS USED IN THIS MANUAL

In order to make this document as easy as possible to understand, we use several conventions in layout and type style. This helps you recognize whether we are talking about a command or key, when you're to type an entry, and so on.

CONVENTION	EXPLANATION
COMMAND	AlphaWRITE command names are shown in all capitals, bold type and in a smaller point size than main text.
COMMAND	AMOS command names and AlphaWRITE file names are shown in all capitals, non-bold type and in the same point size as main text.

CONVENTION	EXPLANATION
AlphaWRITE Main Menu	AlphaWRITE screen names are printed like the example: no bold, initial capitals.
What You Type	Text you are expected to type is shown in bold Courier type.
`Your Terminal Displays`	Text displayed on your terminal is shown in non-bold Courier type.
[KEY]	Keys you need to press are shown in a keycap box.
[CTRL]-[KEY]	Indicates a control-key sequence.
[ESC] [KEY]	Indicates an escape-key sequence.
	The halt symbol denotes an important piece of information you should read carefully before continuing. Usually, text next to this symbol contains instructions for something you MUST or MUST NOT do, so please read carefully.
	The hint symbol denotes a helpful bit of information. It is often used to point out a short cut which may save you time or trouble.
	The remember symbol denotes information you need to keep in mind while you follow instructions.

THE AlphaWRITE DOCUMENTATION LIBRARY

The *AlphaWRITE Installation Instructions* is just one document in the AlphaWRITE Documentation Library. The other documents are:

- The *AlphaWRITE Release Notes* - this document describes enhancements or changes in the current version of AlphaWRITE from the previous version.

- The *AlphaWRITE Reference Guide* - DSO-00078-00: AlphaWRITE's main reference document contains step-by-step operating instructions for end users. Its appendices contain technical information especially for System Operators.

- The *Reference Guide Addendum for AlphaWRITE 2.1C* - DSS-10485-00 is a brief document describing operation changes introduced with the AlphaWRITE 2.1C software.

- *AlphaWRITE Keyboard Commands Reference Booklet* - DSS-10316-00: This reference booklet lists the keys on your terminal you use to work with AlphaWRITE features.

- *AlphaWRITE Programmer's Information* - DSO-00076-00: describes international language support issues, the extended printer driver standard, international character sets, AlphaWRITE 's command line processing features and more.

To order an AlphaWRITE Documentation Library and receive the slip case and binder too, please use part number PDB-00004-03.

OTHER ALPHA MICROSYSTEMS DOCUMENTATION

Other documents may be helpful while installing AlphaWRITE on your computer. You may find you need to refer to one or more of the following reference manuals:

Systems Operator's Guide to the AMOS System Initialization Command File - DSO-00002-00. See this book for information about working with your system initialization file, specifically the SYSTEM commands.

AMOS Systems Operator's Guide - DSO-00001-00. See this book for information about defining ersatz locations, language definition files, and centralized printer definition files.

AMOS Systems Commands Reference Manual - DSO-00043-00. See this book for information about using AMOS commands during AlphaWRITE's installation.

AMOS Laser Printer Support Software Installation Guide - DSO-00037-00. If you are installing the laser printer support software which is prerequisite to using a PostScript™ laser printer with AlphaWRITE, refer to this book for information about defining the printer on your computer.

AMIGOS Reference Guide - DSO-00059-00 and current *AMIGOS Release Notes*. AMIGOS is **A**lpha **Mi**cro's **G**raphics **O**perating **S**ystem software which must be installed if you want AlphaWRITE to make use of PREVIEW's graphical rendering capabilities on graphics terminals, such as the AM-72. Both the *AMIGOS Reference Guide* and *AMIGOS Release Notes* contain information about installation and setup which might be helpful to ensure AMIGOS is up and running correctly on your computer.

CHAPTER TWO
INSTALLATION OVERVIEW

- Installation scenarios.
- Upgrading from AlphaWRITE version pre-1.2A.
- Installation prerequisites.
- PostScript laser printing.
- AMIGOS - **A**lpha **Mi**cro **G**raphics **O**perating **S**ystem.
- AlphaWRITE Software Patches.

The information in this overview will help you determine that your computer meets AlphaWRITE's requirements before you install the software.

INSTALLATION POSSIBILITIES

There are eight possible scenarios for AlphaWRITE's software installation. Each is listed below along with the chapter where you can find that installation's instructions.

- First time AlphaWRITE software installation; see Chapter Three.
- Upgrade from AlphaWRITE versions 2.1 or later, to the current version; see Chapter Four.
- Upgrade from AlphaWRITE version 2.0 to the current version; see Chapter Four.
- Upgrade from AlphaWRITE version 1.2A to the current version; see Chapter Four.
- Upgrade from AlphaWRITE version pre-1.2A to the current versions; see Chapter Four.

The installation scenarios have been grouped into two chapters; each holding a complete set of instructions for that scenario. In this way, you can identify the installation scenario for your computer, turn to the appropriate chapter and follow its installation steps.

UPGRADING FROM AlphaWRITE PRE-1.2A

If your existing AlphaWRITE installation is earlier than version 1.2A, you must first upgrade to version 1.2A before upgrading to the current version of AlphaWRITE. Dealers should call their Alpha Microsystems Sales Order Administrators to order the upgrade. End users, please call your dealer for information on this intermediate upgrade.

INSTALLATION PREREQUISITES

The installation instructions in this document assume you have System Operator expertise, are familiar with using AlphaVUE and with modifying your AMOS system initialization command file. These instructions also assume you have experience installing new software on your computer and are aware of the precautions you should take before doing so.

Whether you are installing AlphaWRITE for the first time or upgrading from an earlier AlphaWRITE version, the prerequisites below are important and apply to all types of installations.

The *AlphaWRITE Release Notes* contain important information about the current release of AlphaWRITE. You should review the current *Release Notes* before continuing with installation so you are made aware of differences between this version of AlphaWRITE and the previous version. Requirements can change between versions; be sure you review the *Release Notes* specifically for that information.

The next sections provide information on these topics:

- Disk space requirements.
- Ersatz accounts.
- Operating system version.
- User memory requirements.
- Additional prerequisites for co-resident AlphaWRITE versions.
- PostScript laser printing.
- AMIGOS and the **PREVIEW** command.

Disk Space Requirements

You need adequate disk space to hold AlphaWRITE's program files. All this disk space does not have to reside on DSK0: because AlphaWRITE supports an ersatz name. The current version of AlphaWRITE requires less than 5950 blocks of free disk space. Approximately 800 blocks are required on DSK0: to hold .LIT, .HLP, .M68, .BAS, and .PDV files.

Ersatz Accounts

You should be familiar with setting up ersatz accounts. AlphaWRITE has two ersatz names associated with it: WRT: and FWT:. The current version of AlphaWRITE's program files must be located in WRT: which can be located on a device other than DSK0:. AlphaWRITE's Font Width Tables (.FWT files) can be relocated to their own

ersatz account named FWT:.

For information on setting up ersatz accounts, see your *AMOS System Operator's Guide*.

Operating System Version

The current version of AlphaWRITE requires a minimum revision of the operating system be present on your computer. The current AlphaWRITE is supported and compatible with these versions of AMOS:

AMOS/L 1.4 and later	AMOS/L 2.1 and later
AMOS/32 1.4 and later	AMOS/32 2.1 and later
AMOS/LC 1.4 and later	AMOS/LC 2.1 and later

AlphaWRITE's extended characters and 8-bit support are not dependent on having AMOS 2.2. See the *AlphaWRITE Programmer's Information Manual* for more information.

User Memory Partition Size

Chapter Six - "AlphaWRITE's Memory Requirements" provides detailed information about determining the memory assignments appropriate for your computer configuration.

POSTSCRIPT LASER PRINTING

If you intend to use the current AlphaWRITE's extensive laser printing capabilities on PostScript laser printers, you must have the Alpha Microsystems Laser Printer Support Software installed on your computer. However, AlphaWRITE's laser printing features on Hewlett-Packard printers do not require the presence of the Laser Printer Support Software unless you are using a PostScript cartridge in your HP Laser printer. (See the Appendix in the *AlphaWRITE Reference Guide* discussing HP Laser printing for more information.)

If you already have the Laser Printer Support Software installed for your PostScript printer, all you need to do is define the printer to AlphaWRITE. Instructions in the installation chapters describe how.

If you do not have the Laser Printer Support Software installed, and intend to use a PostScript printer with the new AlphaWRITE, you must install the support software prior to AlphaWRITE's installation so you do not overwrite AlphaWRITE's version of the printer drivers. Or, you must retain a copy of AlphaWRITE's printer drivers before installation of the Laser Printer Support Software to prevent overwriting the printer drivers.

Dealers can order the Laser Printer Software Support Product by ordering MLP-90581-00 from their Sales Administrator. If you are an end user, contact your Alpha Microsystems dealer to order this product.

THE PREVIEW COMMAND AND AMIGOS

PREVIEW is operational and fully supported on computers where AMIGOS is up and running using and AMIGOS compatible graphics terminal such as an AM-72.

The *AMIGOS Reference Guide* (DSO-00059-00) and current *AMIGOS Release Notes* for instructions on its installation and set-up. Dealers can order the AMIGOS software from their Alpha Micro Sales Order Administrator.

AlphaWRITE SOFTWARE PATCHES

Alpha Micro's electronic bulletin board, AMTEC+, has a library devoted to **S**oftware **P**atch **N**otices (SPNs). Patches may exist for the current version of AlphaWRITE you are about to install. When you complete the installation steps described in this document, install any patches applicable to this version of AlphaWRITE. Please refer to the current edition of the *AlphaWRITE: Important Notice for Dealers* document, DSS-10362-00, for more information about using AMTEC+ to obtain SPNs.

CHAPTER THREE
FIRST TIME AlphaWRITE INSTALLATION

The instructions in this chapter are only for computers where AlphaWRITE has never been installed. Before continuing with these instructions, please be sure you have read Chapter Two - "Overview" and understand the installation prerequisites for:

- AMOS version requirements.
- Disk space requirements.
- Memory requirements.
- Ersatz Accounts
- Laser Printing Support Software requirements for PostScript printing.
- AMIGOS software requirements for **PREVIEW** command.

INSTALLATION STEPS: SUMMARY

The installation process is straightforward:

1. Define WRT: ersatz name.
2. Define FWT: ersatz name (optional).
3. Reset your computer to put ersatz names into effect.
4. Log to WRT:.
5. Download the AlphaWRITE software to your computer.
6. Verify the software files in WRT:.
7. Copy AlphaWRITE files to system accounts.
8 Activate AlphaWRITE's initialization file.
9. Call up AlphaWRITE and enter its **P**roduct **I**nstallation **C**ode.

1 STEP ONE: DEFINE WRT: ERSATZ NAME

AlphaWRITE looks in WRT: for its overlays, message files, and translation files. It also looks in WRT: for its new dictionaries, unless you define another location via a command in AlphaWRITE's initialization file. (See the *AlphaWRITE Reference Guide* for more information on dictionary files and their location.) WRT: is the account where you will download the software from the release media. The Alpha Micro account reserved for WRT: is DSK0:[7,12]; however, you can choose another account.

Choose the device and account where you want to keep the AlphaWRITE software. The only restriction is the device and account must be on a traditional disk not an extended disk; otherwise, you will not be able to restore AlphaWRITE's software files from the VCR tape. Once the software is downloaded, however, you can relocate WRT: to an extended disk.

Log to SYS:. Use AlphaVUE to edit your ersatz definition file to define WRT: with the device and account you selected.

Defining WRT: on a device other than DSK0: conserves system disk space.

2 STEP TWO: DEFINE FWT: ERSATZ NAME (OPTIONAL)

AlphaWRITE versions 2.1A and later support an ersatz location for the **F**ont **W**idth **T**ables (file with extension .FWT) associated with various typefaces available on laser and impact printers. The Alpha Micro account reserved for FWT: is DSK0:[7,47]; however, you can choose another account.

Choose the device and account where you want to keep AlphaWRITE's .FWT files. It may be on an extended disk.

Log to SYS:. Use AlphaVUE to edit your ersatz definition file to define FWT: with the device and account you selected. In Step 7 you'll relocate the .FWT files to this FWT: location.

Defining FWT: on a device other than DSK0: conserves system disk space.

3 STEP THREE: RESET YOUR COMPUTER

After you define the ersatz accounts, reset your computer to put the changes into effect.

4 STEP FOUR: LOG TO WRT:

All of AlphaWRITE's software files will be downloaded to WRT:. You will then relocate files to system accounts from this central location. Log to WRT: now by typing:

```
LOG WRT: RETURN
```

5 STEP FIVE: DOWNLOAD THE AlphaWRITE SOFTWARE

Once you are logged into WRT:, download all the AlphaWRITE software files into this account with one command:

`VCRRES =ALL:[]*.*` RETURN

6 STEP SIX: VERIFYING THE SOFTWARE FILES IN WRT:

Before moving software files to the system disk, you must use the VERIFY command on the WRITE.DIR file to confirm all files were downloaded properly and that none were damaged.

VERIFY does not recognize ersatz names and since the WRITE.DIR file cannot be previously customized with the account location you selected for WRT:, you must customize the WRITE.DIR file with the device and account specification you are using for WRT:.

Customizing is a three step process:

- Make a working copy of WRITE.DIR.
- Use AlphaVUE to change device and account numbers.
- Use the VERIFY command on the working copy.

A. First, make a working copy. Be sure you are logged into WRT:, then type:

`COPY WRTVER.DIR=WRITE.DIR` RETURN

B. Next, use AlphaVUE to edit WRTVER.DIR. Change the device and account numbers listed to the device and account number you assigned to WRT:. Finish from WRTVER.DIR.

VERIFY relies on directory file information being organized into specific columns. Be careful when altering the directory file. Keep the file names in column 1, any version number in column 38, and the hash total in column 56.

C. Run VERIFY from WRT: by typing:

`VERIFY WRTVER.DIR` RETURN

As VERIFY processes the file list, it reports its findings. You see the word VERIFIED when the corresponding file on disk matches with the file name and hash total in WRTVER.DIR. When VERIFY is successfully complete you see the messages:

```
Total errors - 0
Not found ----- 0
```

If there are problems during the verification, VERIFY reports the nature of the error and its summary gives the total number of errors it has encountered. Before checking the *AMOS Command Reference Manual*'s section on VERIFY, check that your

TVER.DIR directory's columns are aligned correctly after having been edited. Confirm the WRTVER.DIR file's information is in the correct columns given in step B and try again.

If VERIFY encounters valid errors, let your Alpha Micro Dealer know. Alpha Micro Dealers will contact Technical Support for further assistance.

7 STEP SEVEN: COPY AlphaWRITE FILES TO SYSTEM ACCOUNTS

When all the files are verified, you need to relocate some of them to system accounts from WRT:. The chart below lists the files you need to relocate.

First, log to the account shown in the right column. Then, relocate the file shown in the left column. Use this format for the AMOS COPY command:

COPY =WRT:*filename* RETURN

MOVE FILENAME	TO ACCOUNT
*.LIT	SYS:
*.PDV	DVR:
*.M68	DSK0:[10,12]
DICSRT.CMD	CMD:
DICSRT.RUN	BAS:
AWREAD.SBR	BAS:
WRTHED.OBJ	MAC:
PDVSYM.M68	MAC:
MSGSYM.M68	MAC:
FWTSYM.M68	MAC:
*.HLP	HLP:
*.FWT	FWT:[1]

[1] Optional.

All of AlphaWRITE's files are now in their proper accounts.

You can conserve disk space. After you complete the software installation, you can erase files from WRT: that have been relocated to the system disk or other ersatz location. However, retaining all AlphaWRITE software files in WRT: can help in troubleshooting.

8 STEP EIGHT: ACTIVATE AlphaWRITE'S INITIALIZATION FILE

The AlphaWRITE software comes with a pre-set initialization file, WRITE.NEW (see Appendix C for a listing).

AlphaWRITE relies on its initialization file for operating settings. To make it usable, you copy it with the name WRITE.INI—or WRITE.*lng*—where *lng* represents the extension for the language currently set on your job.

To customize for the printers on your computer, use AlphaVUE to edit the AlphaWRITE initialization file and modify its PRINTER commands.

If you define your printers in a PRTDEF.INI (or PRTDEF.*lng*) file, you do not need to modify PRINTER commands in the AlphaWRITE initialization file since they are commented out and not in effect. However, you may need to modify your PRTDEF file's PRINTER commands to be sure they specify the correct AlphaWRITE printer drivers.

Minimally, you need to know the following about the PRINTER command's syntax whether it is in AlphaWRITE's initialization file or the printer definition file:

```
PRINTER printer-definition,printer-driver,"Text Name",,,0
```

`printer-definition` is the AMOS system level name for this printer. Type PRINT or PRNT from command level; the name displayed in the upper left corner when you view the printer queue is the name used to define this printer to AMOS and AlphaWRITE.

`printer-driver` represents AlphaWRITE's printer driver file name for this printer. You can find a complete list of the printer drivers accompanying the AlphaWRITE software in Appendix D - "AlphaWRITE's Printer Drivers."

The *AlphaWRITE Reference Guide* appendix describing the initialization file contains complete information for its setup, valid command syntax, and location.

9 STEP NINE: CALL UP AlphaWRITE

The last installation step is to call up the AlphaWRITE software and then enter its **P**roduct **I**nstallation **C**ode (PIC).

To call up AlphaWRITE, from AMOS command level type:

`WRITE` [RETURN]

You are then prompted to enter AlphaWRITE's PIC.

Type the PIC at the prompt requesting it and press [RETURN]. Your computer system will pause briefly while it records the PIC information.

When installing the PIC, all jobs on your computer will be temporarily locked. After a brief system pause, all jobs will be unlocked and the AlphaWRITE Main Menu will appear.

After installation, the command WRITE/P from AMOS command level will show you how many users your version is enabled for and the PIC used.

WHAT'S NEXT?

AlphaWRITE's software installation is now complete. However, you might choose to optimize AlphaWRITE's system resource use. Chapter Five - "AlphaWRITE's Memory Requirements" describes methods you can employ to reduce AlphaWRITE's overall requirements.

CHAPTER FOUR
UPGRADE INSTALLATION

The following list summarizes the steps you must follow to upgrade to the current AlphaWRITE software when it will be the only version of AlphaWRITE on your computer.

If the AlphaWRITE installation you are upgrading is earlier than version 1.2A, you must first upgrade to version 1.2A before upgrading to the current version of AlphaWRITE. Otherwise, pre-1.2A documents will not convert properly. Dealers should call their Alpha Microsystems Sales Order Administrators to order the upgrade. End users, please call your dealer for information on this intermediate upgrade.

Before continuing with these instructions, please be sure you have read Chapter Two - "Overview" and understand the installation prerequisites for:

- AMOS version requirements.
- Disk space requirements.
- Memory requirements.
- Ersatz accounts.
- Laser Printing Support Software requirements for PostScript printing.
- AMIGOS software requirements for the **PREVIEW** command.

INSTALLATION STEPS: SUMMARY

The upgrade installation is straightforward.

If you are upgrading from AlphaWRITE 2.x, have your Product Installation Code on hand.

1. Define the WRT: ersatz name.
2. Define the FWT: ersatz name (optional).
3. Modify your system initialization file to remove SYSTEM commands which load AlphaWRITE files into system memory.
4. Reset the computer.
5. Log to WRT:.
6. Download the AlphaWRITE software to your computer.
7. Verify the software files in WRT:.

8. Copy AlphaWRITE files to system accounts.
9. Modify AlphaWRITE's initialization file.
10. Call up AlphaWRITE and enter its **P**roduct **I**nstallation **C**ode (PIC).
11. Remove older version AlphaWRITE program files from system (optional).
12. Modify your system initialization file to reinstate SYSTEM commands deactivated in Step 3. Reset your computer.

UPGRADES FROM AlphaWRITE 2.X - PRODUCT INSTALLATION CODE

If you are upgrading your AlphaWRITE installation, no new **P**roduct **I**nstallation **C**ode (PIC) is required. However, you must still enter a PIC at the completion of installation. Determine your PIC now. From AMOS command level, type:

`WRITE/P` RETURN

Write down the code shown on your screen. You will need to enter it when you call up AlphaWRITE at the end of these installation steps.

1 STEP ONE: DEFINE WRT: ERSATZ NAME

AlphaWRITE looks in WRT: for its overlays, message files, and translation files. It also looks in WRT: for its new dictionaries, unless you define another location via a command in AlphaWRITE's initialization file. (See the *AlphaWRITE Reference Guide* for more information on dictionary files and their location.) WRT: is the account where you will download the software to from the release media. The Alpha Micro account reserved for WRT: is DSK0:[7,12]; however, you can choose another account.

If WRT: is not already defined on your computer, choose the device and account where you want to keep the AlphaWRITE software. The only restriction is the device and account must be on a traditional disk, not an extended disk. Otherwise, you will not be able to restore AlphaWRITE's software files from the VCR tape. Once the software is downloaded, however, you can relocate WRT: to an extended disk.

Log to SYS:. Use AlphaVUE to edit your ersatz definition file to define WRT: with the device and account you selected.

Defining WRT: on a device other than DSK0: conserves system disk space.

2 STEP TWO DEFINE FWT: ERSATZ NAME (OPTIONAL)

AlphaWRITE versions 2.1A and later support an ersatz location for the **F**ont **W**idth **T**ables (files with extension .FWT) associated with various typefaces available on laser and impact printers. The Alpha Micro account reserved for FWT: is DSK0:[7,47]; however, you can choose another account.

Choose the device and account where you want to keep AlphaWRITE's .FWT files. It may be on an extended disk.

Log to SYS:. Use AlphaVUE to edit your ersatz definition file to define FWT: with the device and account you selected. In Step 8 you'll relocate the .FWT files to this FWT: location.

Defining FWT: on a device other than DSK0: conserves system disk space.

3 STEP THREE: MODIFY YOUR SYSTEM INITIALIZATION COMMAND FILE

If you are upgrading your computer from an earlier version of AlphaWRITE, check your AMOS system initialization command file now.

Never modify your system initialization command file directly. Make your changes to a copy of it and test it first.

Look for any SYSTEM commands loading AlphaWRITE files into system memory. These commands will cause a conflict when you first call up the new AlphaWRITE software, so you must comment out or remove these SYSTEM commands. You can reinstate them and have them take effect after you complete the upgrade installation.

Your *System Operator's Guide to the System Initialization Command File* describes the proper way to work with and modify your computer's initialization file. Please refer to this document for more information.

4 STEP FOUR: RESET YOUR COMPUTER

After you define the WRT: ersatz account ***and*** are sure no SYSTEM commands are in your computer's initialization file that load AlphaWRITE files into system memory, reset your computer so the changes take effect.

5 STEP FIVE: LOG TO WRT:

All of AlphaWRITE's software files will be downloaded to WRT:. You will then relocate files to system accounts from this central location. Log to WRT: now by typing:

```
LOG WRT: RETURN
```

6 STEP SIX: DOWNLOAD THE AlphaWRITE SOFTWARE TO YOUR COMPUTER

Next, copy AlphaWRITE's files from the release tape to your computer.

```
VCRRES =ALL:[]*.* RETURN
```

After the software is downloaded to your computer, use the VERIFY command with WRITE.DIR to ensure the software transfer was successful.

7 STEP SEVEN: VERIFYING THE SOFTWARE FILES IN WRT:

Before moving software files to the system disk, you must use the VERIFY command on the WRITE.DIR file to confirm all files were downloaded properly and that none were damaged.

VERIFY does not recognize ersatz names and since the WRITE.DIR file cannot be previously customized with the account location you selected for WRT:, you must customize the WRITE.DIR file with the device and account specification you are using for WRT:.

Customizing is a three step process:

- Make a working copy of WRITE.DIR.
- Use AlphaVUE to change device and account numbers.
- Use the VERIFY command on the working copy.

A. First, make a working copy. WRT:, type:

COPY WRTVER.DIR=WRITE.DIR RETURN

B. Next, use AlphaVUE to edit WRTVER.DIR. Change the device and account numbers listed to the device and account number you assigned to WRT:. Finish from WRTVER.DIR.

VERIFY relies on directory file information being organized into specific columns. Be careful when altering the directory file. Keep the file names in column 1, any version number in column 38, and the hash total in column 56.

C. Run VERIFY from WRT: by typing:

VERIFY WRTVER.DIR RETURN

As VERIFY processes the file list, it reports its findings. You see the word VERIFIED when the corresponding file on disk matches with the file name and hash total in WRTVER.DIR. When VERIFY is successfully complete you see the messages:

```
Total errors - 0
Not found ----- 0
```

If there are problems during the verification, VERIFY reports the nature of the error and its summary gives the total number of errors it has encountered. Before checking the *AMOS Command Reference Manual*'s section on VERIFY, check that your WRTVER.DIR directory's columns are aligned correctly after having been edited. Confirm the WRTVER.DIR file's information is in the correct columns given in step B and try again.

If VERIFY encounters valid errors, let your Alpha Micro Dealer know. Alpha Micro Dealers will contact Technical Support for further assistance.

8 STEP EIGHT: COPY AlphaWRITE FILES TO SYSTEM ACCOUNTS

When all the files are verified, you need to relocate some of them to system accounts from WRT:. The chart below lists the files you need to relocate.

First, log to the account shown in the right column. Then, relocate the file shown in the left column. Use this format for the AMOS COPY command:

COPY =WRT:*filename* RETURN

MOVE FILENAME	TO ACCOUNT
*.LIT	SYS:
*.PDV	DVR:
*.M68	DSK0:[10,12]
DICSRT.CMD	CMD:
DICSRT.RUN	BAS:
AWREAD.SBR	BAS:
WRTHED.OBJ	MAC:
PDVSYM.M68	MAC:
MSGSYM.M68	MAC:
FWTSYM.M68	MAC:
*.HLP	HLP:
*.FWT	FWT:[1]

[1] Optional.

All of AlphaWRITE's files are now in their proper accounts.

You can conserve disk space. After you complete the software installation, you can erase files from WRT: that have been relocated to the system disk or other ersatz location. However, retaining all AlphaWRITE software files in WRT: can help in troubleshooting.

9 STEP NINE: MODIFY AlphaWRITE'S INITIALIZATION FILE

The AlphaWRITE software comes with a pre-set initialization file, WRITE.NEW (see Appendix B for a listing).

AlphaWRITE relies on its initialization file for operating settings. To make WRITE.NEW usable, you copy it with the name WRITE.INI—or WRITE.*lng*—where *lng* represents the extension for the language currently set on your job.

Older versions of the AlphaWRITE initialization file are functional under the current AlphaWRITE software. If you choose to retain an older intialization file, please refer to the *AlphaWRITE Release Notes* for compatibility information.

To customize for the printers on your computer, use AlphaVUE to edit the AlphaWRITE initialization file and customize the PRINTER commands for your computer.

If you define your printers in a PRTDEF.INI (or PRTDEF.*lan* file, you do not need to change the PRINTER commands in the AlphaWRITE initialization file since they are commented out.

Minimally, you need to know the following about the PRINTER command's syntax whether it is in AlphaWRITE's initialization file or the printer definition file:

```
PRINTER printer-definition,printer-driver,"Text Name",,,0
```

`printer-definition` is the AMOS system level name for this printer. Type PRINT or PRNT from command level; the name displayed in the upper left corner when you view the printer queue is the name used to define this printer to AMOS and AlphaWRITE.

`printer-driver` represents AlphaWRITE's printer driver file name for this printer. You can find a complete list of the printer drivers accompanying the AlphaWRITE software in Appendix C - "AlphaWRITE's Printer Drivers."

The *AlphaWRITE Reference Guide* appendix describing the initialization file contains complete information for its setup, valid command syntax, and location.

10 STEP TEN: CALL UP AlphaWRITE

In this installation step you call up the AlphaWRITE software and then enter its **P**roduct **I**nstallation **C**ode (PIC).

To call up AlphaWRITE, from AMOS command level type:

`WRITE` [RETURN]

You are then prompted to enter AlphaWRITE's PIC.

Type the PIC at the prompt requesting it and press [RETURN]. Your computer system will pause briefly while it records the PIC information.

When installing the PIC, all jobs on your computer will be temporarily locked. After a brief system pause, all jobs will be unlocked and the AlphaWRITE Main Menu will appear.

After installation, the command WRITE/P from AMOS command level will show you how many users your version is enabled for and the PIC used.

11 STEP ELEVEN: REMOVE OLDER VERSION AlphaWRITE FILES (OPTIONAL)

To optimize your disk resources, you may choose to remove the older version AlphaWRITE files from your computer. Erase the older version of AlphaWRITE now.

Some files belonging to an older AlphaWRITE version are no longer necessary and may be present on your system. The files are terminal printer drivers and AM-72 .FWT files which AlphaWRITE no longer requires. You should erase these terminal printer driver files: AM72.PDV, AM62N.PDV, AM62A.PDV; and erase the AM-72 .FWT (72????.FWT) files from the AlphaWRITE software account.

12 STEP TWELVE: REINSTATE SYSTEM COMMANDS

If you modified your system initialization file to remove AlphaWRITE program files from system memory, reinstate the SYSTEM commands deactivated in Step 3. Reset your computer.

WHAT'S NEXT?

AlphaWRITE's software installation is now complete. However, you might choose to optimize AlphaWRITE's system resource use. Chapter Five - "AlphaWRITE's Memory Requirements" describes methods you can employ to reduce AlphaWRITE's overall requirements.

CHAPTER FIVE
AlphaWRITE'S
MEMORY REQUIREMENTS

This chapter discusses AlphaWRITE's rules for memory allocation and its requirements. Following this discussion are guidelines for steps you can take to reduce AlphaWRITE's overall requirements and accurately determine the user memory partitions required.

RULES FOR MEMORY ALLOCATION

AlphaWRITE is a complex software application and its memory requirements are important. AlphaWRITE systematically loads and allocates memory in this order:

- WRITE.LIT and WRT000.OVR
- Initialization Overlay
- Command Line Processing
- Printer Definitions
- Terminal Printer Drivers
- Function Key Translation Tables
- Message Files
- Main Menu Display
- Document Loading

The memory requirements for each of these activities are given below. Armed with this information and the Memory Use Chart at the end of this chapter, you can make efficient memory assignments for your particular computer.

Loading WRITE.LIT & WRT000.OVR

AlphaWRITE 2.1C's WRITE.LIT is 71K in size; if not in system memory, it is loaded into user memory when it is invoked. Once invoked, AlphaWRITE immediately allocates a 16K memory module for its variables.

An additional 16K of AMOS memory is reserved for the loading of device drivers. All remaining user memory is allocated into a single AMOS memory module, WRITE.MEM. If the available memory for WRITE.LIT is less than 150K, AlphaWRITE shows the following error message and exits back to AMOS command level:

```
You do not have enough memory to run AlphaWRITE
```

All subsequent references to the loading of memory modules and their sizes takes place *within* the single AMOS memory module WRITE.MEM.

Once WRITE.LIT is successfully invoked, the WRT000.OVR overlay is loaded into memory and remains in memory until you exit AlphaWRITE. WRT000.OVR's size is 3K.

Initialization Overlay

Next, the AlphaWRITE initialization overlay (WRT080.OVR) is located on disk, is loaded, executed, and is deallocated from memory. WRT080.OVR performs the memory management related tasks described below.

Command Line Processing

If command line processing is being used, a module is created to hold the text of the command line. The size of this module is usually less than 1K.

Printer Definitions

For each printer defined in AlphaWRITE's initialization file or the printer definition file, the specified printer driver is loaded. If the printer driver is already in system or user memory, no loading takes place. If a printer driver specified a PRINTER command was already specified in an earlier PRINTER command no loading takes places. Printer driver sizes vary; the sizes of the printer drivers that come with AlphaWRITE 2.1C are:

DRIVER	SIZE
MISC	2K
AM301	2K
AM302	2K
AM306C	2K
AM306D	2K
AM306L	2K
LASJET	24K
LASII	24K
LASIID	23K
LASIII	23K
LASWRT	32K
PSCART	32K

Function Key Translation Tables

If a function key translation table for your terminal driver exists in WRT:, it is loaded into memory. The function key translation table is named *driver*.WRX and is optional. If the function key translation table is already in user or system memory, no loading takes place. The typical size of an AlphaWRITE function key translation table is 1K.

Message Files

WRT400.*lng*, the main AlphaWRITE message file, is loaded into memory. WRT400.USA,the American English version of this file, is 15K.

Main Menu

After performing the memory steps above, the AlphaWRITE Main Menu is displayed and you can enter commands.

Loading Documents

A major memory event occurs the first time AlphaWRITE needs to load a document into memory. The first **CREATE**, **EDIT**, or **PRINT** command triggers such a situation. AlphaWRITE then decides how much memory should be allocated to the text editing buffer, the largest of all modules AlphaWRITE allocates.

AlphaWRITE's goal is to give you as much memory for editing as possible, but to put aside enough memory for its own purposes. In making the decision about how much memory to withhold from the editing buffer, AlphaWRITE focuses on the two largest overlays: WRT190.OVR (the main printing overlay) and WRT200.OVR (the spell check overlay). AlphaWRITE makes enough memory for all AlphaWRITE commands and functions available, yet leaves you with as much memory as possible for text editing. The text buffer module is called WRTEDT.MEM and is never deallocated.

ESTIMATING MEMORY USE

The previous sections describe how and when AlphaWRITE uses memory. With this understanding of its memory needs, you can make informed decisions for managing your computer's resources.

You can reduce the amount of memory required for each user's memory partition by loading AlphaWRITE files into system memory. After you've selected the files to load, you can easily determine the minimum user memory partition required. The next sections describe each step in the process.

LOADING FILES INTO SYSTEM MEMORY

Every AlphaWRITE program file that you select to load into SYSTEM memory reduces the requirement for each user's memory partition.

It makes sense to load the files AlphaWRITE most frequently uses, along with the printer drivers and terminal function key translation tables applicable to your computer's configuration.

Further, by loading the index component of AlphaWRITE dictionaries into system memory via SYSDCT (see Appendix D), you can reduce user memory partition requirements. By taking advantage of system resources, you can make significant reductions in the amount of user memory required for running AlphaWRITE.

The table below shows the effect of loading specific AlphaWRITE files into system memory.

The files are listed in priority; ones giving the most effective memory benefit appear first.

FILENAME	MEMORY
WRITE.LIT	71K
WRT190.OVR (print)	40K
WRT200.OVR (spell)	12K
SPELL.DCT via SYSDCT	45K
prof.DCT via SYSDCT	15K
VERB.DCT via SYSDCT	15K
WRT400.*lng*	15K
tdv.WRX	1K

You can load .PDV files in system memory; memory savings will vary depending on the number of and which printer drivers loaded.

If WRT: is on a disk other than DSK0:, that disk must be mounted prior to the first SYSTEM command loading AlphaWRITE program files held on WRT:. See your *AMOS System Operator's Guide* for more information.

Configuration Example

For example, this system has three dictionaries: SMALL.DCT, a professional dictionary, and verb dictionary. It also has three printers: an AM-302, a PostScript printer, and a LaserJet. Three terminals are in use. In addition, AlphaWRITE program files shown on the Memory Usage Chart (next page) are loaded into system memory. In this configuration, memory savings adds up to nearly 300K.

DETERMINING USER MEMORY PARTITION SIZE

The following chart shows how to calculate the memory required to run AlphaWRITE. Enter the amount of memory you require for each item and total them at the bottom. Remember, if an item is loaded into system or user memory it does not figure into the total.

AlphaWRITE 2.1C and Later Memory Use Chart

The chart below can help you calculate the amount of user memory needed for running AlphaWRITE 2.1C and later.

WRITE.LIT (71K if not in system memory)	_____K
WRITE.LIT variable and AMOS workspace	16 K
WRT000.OVR (security overlay)	3 K
Command Line Processing (1K if used)	_____K
Function Key translation File (1K if not in system memory)	_____K
WRT400.*lng* (15K if not in system memory)	_____K
Minimum memory for text buffer requirements	105 K
WRT190.OVR (40K if not in system memory)	_____K
WRT200.OVR (12K if not in system memory)	_____K
WRT210.OVR (15K if not in system memory)	_____K
WRT300.OVR (15K if not in system memory)	_____K
Standard Dictionary - add 45K if used; none if loaded via SYSDCT; none if dictionary not present	_____K
Professional Dictionary - add 15K if used; none if loaded via SYSDCT; none if dictionary not present	_____K
Verb Dictionary - add 15K if used; none if loaded via SYSDCT; none if dictionary not present	_____K
Include all Printer Drivers that you define in WRITE.INI or PRTDEF.INI	
MISC.PDV (2K if used and not in system memory)	_____K
AM301.PDV (2K if used and not in system memory)	_____K
AM302.PDV (sK if used and not in system memory)	_____K
AM306C.PDV (2K if used and not in system memory)	_____K
AM306D.PDV (2K if used and not in system memory)	_____K
AM306L.PDV (2K if used and not in system memory)	_____K
LASJET.PDV (24K if used and not in system memory)	_____K
LASII.PDV (24K if used and not in system memory)	_____K
LASIID.PDV (23K if used and not in system memory)	_____K
LASIII.PDV (23K if used and not in system memory)	_____K
LASWRT.PDV (32K if used and not in system memory)	_____K
PSCART.PDV (32K if used and not in system memory)	_____K
***Minimal* amount of user memory to run AlphaWRITE 2.1C and later:**	_____K

AlphaWRITE'S MEMORY SEARCH PATH

AlphaWRITE searches memory following this path:

1. User memory.
2. System memory.
3. Specific disk locations as described in Appendix O of the *AlphaWRITE Reference Guide*.

CHAPTER SIX
COMPATIBILITY ISSUES AND UPGRADE TIPS

This chapter is especially for customers upgrading from AlphaWRITE 1.2A to the current AlphaWRITE. Important operational differences are discussed and compatibility information given. This chapter is a supplement to the current set of *AlphaWRITE Release Notes*. This chapter's topics include:

- Converting older AlphaWRITE documents.
- AlphaWRITE dictionary compatibility.
- Hardware handshaking.
- First time laser printing tips.
- Upgrades to AlphaWRITE 2.x from AlphaWRITE 1.2A.
- Operational changes from AlphaWRITE 1.2A.
- Upgrade tips especially for AlphaWRITE 1.2A users upgrading directly to AlphaWRITE 2.1A, or later.

DOCUMENT CONVERSION TIPS

Because documents created or edited under AlphaWRITE 2.1 or later are in a different format than earlier versions, it is important for you to convert all of the documents you use during AlphaWRITE's operation. Specifically, you should be sure to convert pre-AlphaWRITE 2.1 prototype documents, glossary documents, template index and table of contents documents, and so on, before using them under the current AlphaWRITE.

CONVERTING OLDER AlphaWRITE DOCUMENTS

Documents created with a version of AlphaWRITE earlier than 1.2A must first be converted to AlphaWRITE 1.2A prior to use with AlphaWRITE 2.x.

Failure to convert pre-1.2A documents to AlphaWRITE 1.2A can result in problems with your converted documents.

If you have AlphaWRITE pre-1.2A documents that you need to convert to AlphaWRITE 2.x, call your Alpha Microsystems dealer. Dealers can acquire the conversion instructions from Alpha Microsystems Technical Support.

AlphaWRITE DICTIONARY COMPATIBILITY

With AlphaWRITE 2.1 or later versions, AlphaWRITE's dictionaries have a new internal format. Older dictionaries belonging to AlphaWRITE 2.0 or earlier are not compatible. In addition, professional dictionaries created with versions of BLDPRF and DICSRT utilities other than the version arriving with AlphaWRITE 2.1 and later are not compatible and must be rebuilt using a current version of BLDPRF and DICSRT.

If an incompatible dictionary is encountered during SPELL, AlphaWRITE displays a message telling you so and the offending dictionary is not used.

HARDWARE HANDSHAKING

AlphaWRITE's screen display enhancements rely on proper hardware handshaking between your terminal and the computer. Flow control should be enabled on terminals by using appropriate wiring to prevent screen display corruption or display of spurious characters. If terminals exhibit these symptoms, check the terminal cable wiring.

FIRST TIME LASER PRINTING TIPS

If you used dot matrix or impact printers exclusively before and now intend to use laser printers, you need to keep the following points in mind.

You may encounter print anomalies if you do not use care in making appropriate format settings for laser printing. The settings to be wary of are listed below.

SETTING	REQUIREMENT
Left paper offset	Laser printers require a setting of at least 0.25".
Top margin	Laser printers require a setting of at least 0.25".
Page length	Settings less than the physical paper length in your laser printer will give unexpected print results. Typically, letter size paper in laser printers require 11" when using portrait mode, 8.5" in landscape mode.

UPGRADES TO AlphaWRITE 2.X FROM AlphaWRITE 1.2A

AlphaWRITE 2.x software versions are software maintenance releases for AlphaWRITE 2.0. AlphaWRITE 2.1 contained problem resolutions and some enhancements for AlphaWRITE 2.0. AlphaWRITE 2.1x versions are software maintenance releases. If you are upgrading directly to AlphaWRITE 2.x from AlphaWRITE 1.2A, you'll be interested in knowing what new features were introduced in AlphaWRITE 2.0 and consequently are a part of AlphaWRITE 2.x.

The summary is organized into these major groups:

- System level enhancements.
- Publishing features.
- Editing features.

System Level Enhancements introduced in AlphaWRITE 2.0

AlphaWRITE 2.0 introduced system level enhancements:

- Ersatz location for AlphaWRITE program files to free up space on DSK0:.
- Enhanced AWCONV utility allows for batch conversions, and conversion for WordPerfect documents and Sony Series 35 word processing files. More thorough conversions now take place for TXTFMT and SuperVUE format files.
- Improved international language support.
- Mode terminal support.
- On-screen color support.
- Keystroke journaling to ensure preservation of your work between **SAVE** commands.
- Built-in laser printing features for HP LaserJet II and III, Apple LaserWriter printers, and any PostScript compatible printers.
- Increase in maximum number of printers from 8 to 32.

Publishing Features

AlphaWRITE features which let you create near-typeset quality documents include:

- Index capabilities.
- Chapter features.
- Titles and footers allow multiple lines of text.
- **PAGINATE** now processes for the printer you select.
- Graphics to draw boxes and lines available when laser printing.
- Multiple typefaces and typesizes available when laser printing.
- Reverse, screened and gray text available when laser printing.
- Multiple units of measurement supported: lines, characters, metric, inches, points, didots, and ciceros.
- New special characters: keycap: KEYCAP, star: ★, bullet: ●, em dash: —, and en dash: – available on specific printers.

- New document header format settings such as leading, format text, kerning, and page orientation.
- **MERGE** options for including or excluding automatically generated page breaks in output documents.
- Other mail-merge improvements: The data field maximum length is increased to 8,192, variable name length was 64 characters, and the maximum number of variable names is now 128.

Editing Features

To make AlphaWRITE more flexible and easier to use for entering and editing text, these editing features will come in handy:

- Undelete previous character, word or line with [CANCEL].
- Record and playback of your keystrokes.
- Enhancements to glossary: on-line addition of glossary entries supported from all command screens, and new default entries for current file, user name, current disk and account are available.
- "Previous Match" for **SEARCH** command.
- The new Editing Menu **FORMAT** command.
- "Resume print at top of page" allowing you to print columns of text when laser printing.
- Margin ruler is now in inches.
- Import feature lets you include image files and AlphaCALC worksheets in your document.
- **PREVIEW** displays your formatted document.
- Printing only odd or even numbered pages.
- Direct PostScript programming in your document.

OPERATIONAL CHANGES FROM AlphaWRITE 1.2A

If you are familiar with using AlphaWRITE 1.2A, you will find many new features now available to you. In addition, you will notice some AlphaWRITE features operate differently now than they did before.

To help AlphaWRITE 1.2A users make the transition to the newer version of the software, and keep surprises to a minimum, the list below highlights AlphaWRITE 1.2A features under the current version of AlphaWRITE that operate somewhat differently now.

AREA OR FEATURE	WHAT'S CHANGED FROM 1.2A
All command screens	Screens having multiple fields—like the one PRINT gives you—now let you use the arrow keys to move between fields so you can make changes.
AWCONV to convert files	New command format and switches. Wildcarding supported. On-line help available by typing AWCONV [RETURN] from AMOS command level.
Command Line/Script Processing	Because of the many changes to AlphaWRITE commands, check any script files you use with AlphaWRITE to be sure they are still correct.
Default Prototype Document	AlphaWRITE requires you to specify a prototype document when you use CREATE. AlphaWRITE comes with its own prototype named DEFDOC, which is also the default name. You can still use any legal document name as a prototype.
Discretionary Hyphen	No more discretionary hyphen key; use the universal key sequence [ESC] [-] instead.
Document Header	Many new fields were added here and the default settings are different. Laser printer support is the biggest change and multiple units of measurement are supported so you can take advantage of many print features. The new setup might be tricky at first, but the defaults are standard and are a good place to begin and become familiar with the new arrangement. On-line help is available for every field; just press [HELP]. Be sure to read "First time Laser Printing tips" earlier in this chapter for guidelines on how header fields interact with laser printers.
Embedded Commands	No more slash commands, except // for comments. Embedded commands are now implemented through the [EMBED], [LAYOUT] and [PAGE] keys.
Embedded Text	Memory handling for embedded text—which includes page titles and footers as well as footnotes—has been improved, making it less likely you'll run out of memory while entering embedded text.

AREA OR FEATURE	WHAT'S CHANGED FROM 1.2A
Font Key	No more FONT key. It is now called STYLE and has many new options.
Footnote	No more footnote key; footnotes are located under EMBED.
Go To Page	No more "Go To Page," it is now called PAGE and includes the go to page feature, setting page breaks and "Resume print at top of page."
Help Files	You can scroll back and forth through Help screens, and use either MENU or CANCEL to exit.
Key to Process Commands	In many places where you've used RETURN to start executing an AlphaWRITE command, you'll now use EXECUTE. Be careful; many commands won't begin or won't put your changes into effect unless you exit with EXECUTE.
Mode Screen	Is now available from either the Main Menu or Editing Menu. Has many new options and you must use EXECUTE to put changes into effect. They remain in effect for your entire session with AlphaWRITE. You can see on-line help for any field by pressing HELP.
Page Breaks	No longer automatically inserted as you work along in your document. Hard and conditional page breaks are now made through the PAGE key.
Printing	Prompts for printing odd and even numbered pages. You must press EXECUTE to begin printing.
Printing Queue	**QUEUE**'s Wheel command has been changed to Font, and has more options. Also, the waiting list in this display is continually updated.
Superscript & Subscript	No more SUPER and SUB keys. These features are now available under the STYLE key.

UPGRADE TIPS ESPECIALLY FOR AlphaWRITE 1.2A USERS UPGRADING TO AlphaWRITE 2.X

If you are accustomed to using AlphaWRITE 1.2A you will find AlphaWRITE 2.x has some subtle but important differences which affect the way you work with it. Areas where you will find changes are:

- End of Paragraph Markers
- Using the Menu Key
- Text Display Ruler for Columns, Tabs and Margins
- Upgrading Documents and First Time Laser Printing
- Instructions in Existing Command Line Processing Script Files
- Converting older AlphaWRITE documents

End of Paragraph Markers

AlphaWRITE 2.x has more sophisticated formatting capabilities than previous versions of AlphaWRITE. These format capabilities rely even more extensively on the presence of "end of paragraph markers"in your document's text. "End of paragraph markers" signal blank lines, or signal the end of a line or paragraph and are made when you use [RETURN]. AlphaWRITE interprets these "end of paragraph markers" as begin and end reference points of text areas to be formatted in your document.

While AlphaWRITE 1.2A was forgiving when end of paragraph markers were omitted, AlphaWRITE 2.x is not. AlphaWRITE 2.x will not give you the printed results you expect if you omit [RETURN] at the end of a paragraph, at the end of a line, or on a line you want to be blank. In fact, when you troubleshoot unexpected print results, the first problem to check for is missing "end of paragraph markers"in your document.

Using the Menu Key

Although you still use [MENU] to get around in AlphaWRITE 2.x's menu system, its effect will probably not be the same as under 1.2A. Generally, in AlphaWRITE 2.x, you use [MENU] to switch between a command screen and the Main or Editing Menu, or to halt or cancel a command or feature. If you find a change you made did not happen as you expected, it may be that you used [MENU] instead of [EXECUTE].

There are instructions at the bottom of command screens describing the effect of [MENU], [CANCEL], and [EXECUTE] to let you know what result each key gives.

Upgrading Documents and First Time Laser Printing

If you used dot matrix or impact printers exclusively with AlphaWRITE 1.2A and are now upgrading to AlphaWRITE 2.x and intend to use laser printers, you need to keep these next points in mind.

AlphaWRITE 2.x brings forward format settings from your 1.2A document in characters and lines—it does not convert them to inches or any other unit of measurement. You may encounter print anomalies if you send this document to your laser printer without making some adjustments to its format settings. The settings to be wary of are listed at the beginning of this chapter: left paper offset, top margin, page length, and leading.

Text Display Ruler

The ruler shown at the bottom of your text display serves two purposes: it gives you a visual reference for column positions of displayed text and it corresponds to the location of text on the printed page.

AlphaWRITE 1.2A interpreted the units on the ruler as characters, and printed text based on the Characters Per Inch setting (CPI).

Now, AlphaWRITE 2.0 and later versions interpret each number on the ruler as *distance in inches* and interprets each dot as *distance in tenths of an inch* for margin and tab settings. This means you can have text print at precise page locations by setting margins and tabs at the corresponding measurement on your document's margin ruler. For example, if you set a tab at column 25, text tabbed on your screen to column 25 prints 2.5" from the left paper offset; text lined up at a left margin of 32 prints 3.2" from the left paper offset, and so on.

Instructions in Command Line Processing Script Files

AlphaWRITE's command line processing feature was introduced in version 1.2A and allows software programs and command files to access AlphaWRITE's word processing features. One aspect of this feature allows you to create a script file containing step-by-step instructions using the same conventions required by AlphaWRITE's glossary feature.

Script files created for use under 1.2A will probably require revision to execute correctly. Review your existing script files if you intend to use them with AlphaWRITE 2.x and update them as necessary. The section named "Operational Changes from Alpha-WRITE 1.2A" earlier in this chapter outlines areas where you will need to make changes. You may also want to test your script files so you can troubleshoot problems.

Lines Per Inch Setting

AlphaWRITE 1.2A's Lines Per Inch format setting was replaced by AlphaWRITE 2.x's Leading format setting. Both settings control the number of lines that print in a vertical space. The default value for AlphaWRITE 1.2A's Lines per Inch setting was 6 lines per inch which many people used. When you convert the 1.2A document to 2.x, whatever value has been used in 1.2A's Lines Per Inch field is supplied to 2.x's Leading format field. In AlphaWRITE 2.x, a leading value of 6 will not cause printing of six lines per inch. In AlphaWRITE 2.x to print 6 lines per inch, enter `12pt` as the value for the Leading setting.

APPENDIX A
AlphaWRITE'S FILES

The following list of files make up the AlphaWRITE 2.1C software. The list shows the proper destination accounts for files and their general purpose based on their file extensions. The list is organized by destination accounts.

FILENAME	DEST.	FUNCTION
AWREAD.SBR	BAS:	Reads text of document
DICSRT.CMD	CMD:	Command file to sort professional dictionary
AM*.M68	DSK0:[10,12]	Printer Driver sources
MISC.M68	DSK0:[10,12]	Miscellaneous printer driver source
LASWRT.M68	DSK0:[10,12]	Apple LaserWriter printer driver source
LASJET.M68	DSK0:[10,12]	HP LaserJet and LaserJet IID printer driver source
WRT???.M68	DSK0:[10,12]	Message file sources
*.PDV	DVR:	Printer Drivers
BLDPRF.HLP	HLP:	BLDPRF utility system level help file
DICSRT.HLP	HLP:	DICSRT utility system level help file
SYSDCT.HLP	HLP:	SYSDCT utility system level help file
WRITE.HLP	HLP:	WRITE command system level help file
WRTCLP.HLP	HLP:	WRITE command's command line processing features system level help file
WRTDIR.HLP	HLP:	WRTDIR command system level help file
WRTINI.HLP	HLP:	Initialization file information system level help file
WRTHED.OBJ	MAC:	Returns header information to a program

FILENAME	DEST.	FUNCTION
PDVSYM.M68	MAC:	AlphaWRITE printer driver symbol file source
MSGSYM.M68	MAC:	Message symbol file source
FWTSYM.M68	MAC:	Font width table symbol file
AWCONV.LIT	SYS:	Conversion utility
BLDPRF.LIT	SYS:	Builds professional dictionary
WRITE.LIT	SYS:	AlphaWRITE's main program
WRTDIR.LIT	SYS:	AMOS directory program for AlphaWRITE documents
SYSDCT.LIT	SYS:	Loads dictionary indices into system memory.
DICSRT.RUN	WRT:	Sort utility for professional dictionary
*.DCT[1]	WRT:	Dictionaries
72????.FWT	WRT:	AM-72 terminal Font Width Tables for use with PREVIEW command
DEFDOC.WRT	WRT:	Standard prototype document
HP????.FWT	WRT: or FWT:	HP LaserJet Font Width Tables
PS????.FWT	WRT: or FWT:	PostScript Font Width Tables
PST00.M68	DSK0:[10,12]	Times Roman Sample font Width Table for PostScript printers
HPT10.M68	DSK0:[10,12]	Times Roman 10 point Font Width Table for Hewlett-Packard printers
*.OVR	WRT:	Overlays
WRT*.USA	WRT:	Message Files
WHM*.USA	WRT:	Main Menu Help Files
WHE*.USA	WRT:	Editing Menu Help Files
WHT*.USA	WRT:	Text Display Help Files
WHH*.USA	WRT:	Header Screen - Field Help Files
WHS*.USA	WRT:	Mode Screen Field Help Files
*.WRX[2]	WRT:	Terminal Function Key Translation Tables
WRITE.NEW	WRT:	Sample initialization file
*.WRT	WRT:	Template or Sample AlphaWRITE files

NOTES:

1. DICTIONARIES
   SPELL.DCT, SMALL.DCT, and if present, the VERB.DCT and professional dictionary may be relocated to another destination. If so, the DICTIONARY initialization file command must direct AlphaWRITE to their new location.

2. FUNCTION KEY TRANSLATION TABLES
   The following files made with FIXTRN are included as function key translation tables:

ALPHA.WRX	AM60.WRX	AM62.WRX	AM62A.WRX
AM62C.WRX	AM62GF.WRX	AM62GM.WRX	AM62N.WRX
AM65.WRX	AM65A.WRX	AM65AX.WRX	AM65EX.WRX
AM72.WRX	AM72A.WRX	AM75.WRX	AM75A.WRX
AM75AX.WRX	AM75EX.WRX	WINDOW.WRX	

   If you intend to use AlphaWRITE 2.1C with AM-PC 1.2 and later, or AlphaMATE 3.0 and later, consult the documentation accompanying AM-PC or AlphaMATE for instructions on the translation tables required.

APPENDIX B
AlphaWRITE's SAMPLE INITIALIZATION FILE: WRITE.NEW

AlphaWRITE 2.1C's sample initialization file WRITE.NEW is reprinted below. For more information about creating initialization files or their commands, refer to the *AlphaWRITE Reference Guide*.

```
;*************************
;*  Printer Definitions  *
;*************************

;PRINTER LASER,LASWRT,"Apple LaserWriter+",,,0
;PRINTER LPT0,LASJET,"HP LaserJet",,,0
;PRINTER LPT0,LASII,"HP LaserJet II",,,0
;PRINTER LPT0,LASIID,"HP LaserJet IID/IIP",,,0
;PRINTER LPT0,LASIII,"HP LaserJet III/IIID",,,0
;PRINTER LPT1,MISC,"Draft Printer",,,0
;PRINTER LPT2,AM301,"AM301 Letter Quality Printer",,,0
;PRINTER LPT2,AM302,"AM302 Letter Quality Printer",,,0
;PRINTER LPT3,AM306D,"AM306 Draft Quality  ",,,0
;PRINTER LPT3,AM306C,"AM306 Corres. Quality",,,0
;PRINTER LPT3,AM306L,"AM306 Letter Quality ",,,0

;FONT=A-D,H,I,N,P,S,T,Z
;FONTCARTRIDGE LPT0=I,K

;******************
;*  Memory Usage  *
;******************

;DIRECTORYSIZE 400

;***************************
;*  Text Display Defaults  *
;***************************

;CHARINSERT=TRUE
;LINEINSERT=TRUE
;MENUBYPASS=TRUE
```

```
;**********************
;*  Display Defaults  *
;**********************

;DISPLAYATTRIBUTE=FALSE
;PROPORTIONAL=TRUE
;INTENSITY=FALSE
;COLOR=TRUE
;PALETTE=1,7,6,5,4
;MODEM=TRUE
;WIDTH=132

;*************************
;*  Keystroke Journaling  *
;*************************

JOURNAL=TRUE
JOURNALSIZE=20000

;**************
;*  Printing  *
;**************

REFORMAT=TRUE
SUBSTITUTE=TRUE

;*******************
;*  Miscellaneous  *
;*******************

;DICTIONARY DSK0:[7,12]
;DICTIONARYTWO DSK0:PROF.DCT[7,12]
SEARCHFOLD=TRUE
ACKWAIT=FALSE
```

APPENDIX C
AlphaWRITE's PRINTER DRIVERS

The AlphaWRITE software contains a set of printer drivers files. In the installation steps requiring you to modify PRINTER commands, you need to supply an AlphaWRITE .PDV file name for the printer you want to define.

The printer drivers accompanying the current AlphaWRITE software are shown below. The lefthand column lists the printer type and the righthand column indicates the AlphaWRITE printer driver filename to be used for that printer. For example, an HP LaserJet III printer uses LASIII.PDV printer driver. In your PRINTER command, you would use the filename LASIII to define the printer driver.

PRINTER	DRIVER NAME
Dot Matrix types	MISC.PDV
AM-301	AM301.PDV
AM-302	AM302.PDV
AM-306	AM306D.PDV[1]
AM-306	AM306L.PDV[2]
AM-306	AM306C.PDV[3]
HP LaserJet I	LASJET.PDV
HP LaserJet Plus	LASJET.PDV
HP LaserJet 500	LASJET.PDV
HP LaserJet II	LASII.PDV
HP LaserJet IID	LASIID.PDV
HP LaserJet IIP	LASIID.PDV
HP LaserJet III	LASIII.PDV
HP LaserJet IIID	LASIII.PDV
HP LaserJet IIIP	LASIII.PDV
HP LaserJet IID/III/IIID installed with PostScript Cartridge	PSCART.PDV
Apple LaserWriter	LASWRT.PDV
Apple LaserWriter Plus	LASWRT.PDV
Apple LaserWriter II	LASWRT.PDV

[1] Draft quality
[2] Letter quality
[3] Correspondence quality

The LASWRT.PDV printer driver supports any printer Adobe Corp. has officially identified as a "PostScript Compatible" printer. PostScript printers other than Apple LaserWriters may or may not have the same fonts available. For example, while the NEC LC 890 has an identical font set to the Apple LaserWriter Plus, the IBM ProPrinter II has a different collection of fonts. Other laser printer drivers may be available; for more information call Alpha Microsystems Technical Support.

The MISC.PDV supports most dot matrix printers and supplies capability for some special print features.

APPENDIX D
USING THE SYSDCT UTILITY

USING THE SYSDCT UTILITY

You can increase SPELL checking speed by using SYSDCT which loads the AlphaWRITE dictionary index file into system memory. SYSDCT also reduces the amount of user memory needed to invoke AlphaWRITE.

Characteristics

SYSDCT is re-entrant and re-usable. SYSDCT may be used with any of AlphaWRITE's dictionaries that are random files. This includes SPELL.DCT, VERB.DCT, and any professional dictionaries you create. The index information that SYSDCT loads is 45K in size.

SHORT.DCT, SMALL.DCT, and LOCAL.DCT are based on sequential files and may not be used with SYSDCT. However, you may load SMALL.DCT into system memory by using the SYSTEM command.

SYSDCT cannot be used from command level.

Format

```
SYSDCT filespec
```

Where `filespec` is the file specification for the dictionary whose index you want to load into system memory.

Defaults

Unless you specify otherwise, SYSDCT assumes a file extension of .DCT and that the .DCT file is located in WRT:. If the WRT: ersatz name has not been defined on your system, SYSDCT searches DSK0:[7,12].

If WRT: is on a disk other than DSK0:, that disk must be mounted prior to the first SYSDCT command. See your *AMOS System Operator's* manual for more information.

Operation

In your system initialization command file, place a SYSDCT line in the SYSTEM area for each dictionary whose index you want to load into system memory:

```
SYSTEM SYS:RUN.LIT
SYSTEM SYS:VUE.LIT
SYSDCT SPELL
SYSDCT DENTAL
SYSTEM DVR:TRM.DVR
SYSTEM
```

SYSDCT command lines must appear **after** the first SYSTEM statement and **before** the final SYSTEM statement.

Messages

?The SYSDCT command may only be used in the system initialization file

An attempt was made to invoke SYSDCT from command level after the system was booted.

SYSDCT loads an AlphaWRITE dictionary's 45K index into system memory
Usage: SYSDCT dictname
Where "dictname" is SPELL, VERB, or the name of a professional dictionary.

SYSDCT displays help information on its usage when no file specification was given on the command line.

?AlphaWRITE dictionary file [filespec] not found

The specified dictionary file was not found. Be sure the device where WRT: is located has been mounted prior to the SYSDCT command in your initialization file. Be sure the dictionary is present.

?No SYSTEM statements have been issued yet

The SYSDCT command has been placed before the first SYSTEM statement. Relocate SYSDCT to appear after the first before the last SYSTEM statement in your system initialization command file.

?SYSDCT only loads random file dictionaries
?Use the SYSTEM command to load xxxxxx.DCT into system memory

An attempt was made to load SHORT.DCT or SMALL.DCT via SYSDCT. These dictionaries are ineligible for use with SYSDCT because they are based on sequential files.

?LOCAL.DCT may not be loaded into system memory

An attempt was made to load LOCAL.DCT into system memory via SYSDCT. LOCAL.DCT is an ASCII file and ineligible for loading via SYSDCT.

?[filespec] is not an AlphaWRITE random dictionary file

The specified file is not a random-file dictionary compatible with AlphaWRITE 2.1x or later.

INDEX

*.WRX
  memory requirements 5-2

8-bit support
  dependencies 2-3

AlphaVUE 2-2
AlphaWRITE
  2.0 upgrade tips 6-6
  2.1 file list A-1 to A-3
  changes between 1.2A and 2.1A 6-4
  pre-1.2A upgrades 2-2
  program files 2-3
AlphaWRITE Documentation Library 1-3, 1-4
AlphaWRITE initialization file
  PRINTER command 3-5, 4-6
  WRITE.NEW 3-4, 3-5, 4-5
AlphaWRITE Installation Instructions 1-3
AlphaWRITE Keyboard Commands Reference 1-3
AlphaWRITE Main Menu 5-3
AlphaWRITE Programmer's Information 1-4
AlphaWRITE Reference Guide 1-3
AlphaWRITE Release Notes 1-3, 2-2
AlphaWRITE software
  destination accounts for files 3-4, 4-5
  downloading to disk 3-3
AM-72 graphics terminal
  AMIGOS compatibility 1-4
  preview command 2-4
AMIGOS Reference Guide 1-4
AMIGOS software
  documentation 1-4
  preview command 2-4
AMOS Laser Printer Support Software
  documentation 1-4
AMOS system initialization file
  SYSTEM commands 4-3
AMOS System Operator's Guide
  AMOS Initialization File 1-4
AMOS Systems Commands Reference Manual 1-4
AMOS Systems Operator's Guide 1-4
AMOS versions 2-3
AMTEC+
  AlphaWRITE software patches 2-4
AWCONV utility
  AlphaWRITE 2.0 feature 6-3, 6-5

BLDPRF utility 6-2

Chapter feature
  AlphaWRITE 2.0 feature 6-3
Command line processing
  AlphaWRITE 2.0 feature 6-5, 6-8
  memory requirements 5-2
Command screens
  AlphaWRITE 2.0 feature 6-5
Compatibility
  dictionaries 6-2

Control key 1-3
Conventions 1-2, 1-3
  used in this book 1-2
Conversion of documents 6-1
Create command
  memory requirements 5-3

DICSRT utility 6-2
Dictionaries
  compatibility 6-2
  SYSDCT utility D-1 to D-3
Discretionary hyphen
  AlphaWRITE 2.0 feature 6-5
Disk space requirements 2-2
Document Header fields
  AlphaWRITE 2.0 feature 6-5
Documents
  conversion to AlphaWRITE 2.1A 6-1

Edit command
  memory requirements 5-3
Editing
  AlphaWRITE 2.0 features 6-4
  memory reserved for 5-3
Embed key
  AlphaWRITE 2.0 feature 6-5
Embedded commands
  AlphaWRITE 2.0 feature 6-5
End of paragraph markers
  AlphaWRITE 2.0 feature 6-7
Ersatz
  reserved account for 3-2, 4-2
  reserved accounts 3-2, 4-2
Ersatz account 2-3
  AlphaWRITE 2.0 feature 6-3
  FWT: 3-2, 4-2
  single version installation 4-2
  WRT: 3-2
Escape key 1-3
Execute key
  AlphaWRITE 2.0 feature 6-6
Extended characters
  dependencies 2-3

Files
  list of AlphaWRITE A-1 to A-3
Font key
  AlphaWRITE 2.0 feature 6-6
Font option Queue command
  AlphaWRITE 2.0 feature 6-6
Font width tables
  ersatz location for 3-2, 4-2
Fonts
  AlphaWRITE 2.0 feature 6-3
Footers
  AlphaWRITE 2.0 feature 6-3
Footnote feature
  AlphaWRITE 2.0 feature 6-6
Format command
  AlphaWRITE 2.0 feature 6-4
Format settings
  AlphaWRITE 2.0 feature 6-4
Function key translation tables
  memory requirements 5-2
FWT:
  account number for 3-2, 4-2
  ersatz 3-2, 4-2

Glossary feature

AlphaWRITE 2.0 feature 6-4
Go to page feature
AlphaWRITE 2.0 feature 6-6
Graphics
AlphaWRITE 2.0 feature 6-3

Halt symbol 1-3
Help files
AlphaWRITE 2.0 feature 6-6
Hint symbol 1-3
HP laser printers
software required 2-3

Import feature
AlphaWRITE 2.0 feature 6-4
Index feature
AlphaWRITE 2.0 feature 6-3
Initialization
memory requirements 5-2
Initialization file
WRITE.NEW B-1, B-2
Installation
prerequisites 2-2, 2-3
scenarios 2-1
single AlphaWRITE version 3-1, 4-1, 4-3 to 4-6
International language support
AlphaWRITE 2.0 feature 6-3

Key to process commands
AlphaWRITE 2.0 feature 6-6
Keystroke journaling
AlphaWRITE 2.0 feature 6-3

Language support
initialization file 3-5, 4-6
Laser Printer Support Software 2-3
Laser printing
AlphaWRITE 2.0 features 6-3
upgrade tips 6-2, 6-7
LASWRT.PDV
printers supported C-2
Layout key
AlphaWRITE 2.0 feature 6-5
Left paper offset format setting
laser printers 6-2
Lines per inch 6-8

Margin ruler measurement used
AlphaWRITE 2.0 feature 6-4
Measurement
AlphaWRITE 2.0 feature 6-3
and text display ruler 6-8
Memory 5-1 to 5-4
handling 6-5
requirements 2-3, 5-1, 5-2, 5-5
requirements, estimating 5-4, 5-5
search path 5-5
Menu key
AlphaWRITE 2.0 feature 6-7
Merge command
AlphaWRITE 2.0 feature 6-4
Message files
memory requirements 5-3
MISC.PDV
printers supported C-2
Mode command
AlphaWRITE 2.0 feature 6-6

Operating System versions 2-3

Operational changes
  AlphaWRITE 2.0 feature 6-4
Overview of book 1-1, 1-2

Page breaks
  AlphaWRITE 2.0 feature 6-6
Page key
  AlphaWRITE 2.0 feature 6-5, 6-6
Page length format setting
  laser printers 6-2
Paginate command
  AlphaWRITE 2.0 feature 6-3
Patches,
  software 2-4
PIC
  WRITE/P command 3-5, 4-6
Playback feature
  AlphaWRITE 2.0 feature 6-4
PostScript
  printer driver C-2
  programming, AlphaWRITE 2.0 6-4
  software required 2-3
Prerequisites
  memory 5-1, 5-2, 5-5
Preview command
  AlphaWRITE 2.0 feature 6-4
  AMIGOS requirement 2-4
  AMIGOS software 1-4
Previous match
  AlphaWRITE 2.0 feature 6-4
Print command
  AlphaWRITE 2.0 feature 6-4, 6-6
  memory requirements 5-3
PRINTER command
  AlphaWRITE initialization file 3-5, 4-6
  memory requirements 5-2
  printer drivers C-1, C-2
PRINTER commands
  maximum number 6-3
Printer definition
  memory requirements 5-2
  PRINTER command 3-5, 4-6
  PRTDEF.INI file 3-5, 4-6
PrINTER driver
  PRINTER command 4-6
Printer drivers C-1, C-2
  memory requirements 5-2
  MISC.PDV C-2
  PRINTER command 3-5
Product Installation Code (PIC) 3-5, 4-6
Prototype document
  AlphaWRITE 2.0 feature 6-5
PRTDEF.INI
  printer definition file 3-5, 4-6
Publishing features
  AlphaWRITE 2.0 features 6-3

Queue command
  AlphaWRITE 2.0 feature 6-6

Record feature
  AlphaWRITE 2.0 feature 6-4
Reference Guide Addendum for AlphaWRITE 1-3
Remember symbol 1-3
Requirements
  AMIGOS 2-4
  AMOS version 2-3
  disk space 2-2
  ersatz 2-3

PostScript printing 2-3, 2-4
preview command 2-4
user memory partition 2-3
Resetting computer 3-2, 4-3
Restart print top of page
AlphaWRITE 2.0 feature 6-4
Return key
AlphaWRITE 2.0 feature 6-6, 6-7
Ruler
at Text Display 6-7

Script files
AlphaWRITE 2.0 feature 6-5, 6-8
Search path
memory 5-5
Software
patches 2-4
Special characters
AlphaWRITE 2.0 feature 6-3
Spell command
dictionaries 6-2
increasing speed D-1 to D-3
Style key
AlphaWRITE 2.0 feature 6-6
Sub key
AlphaWRITE 2.0 feature 6-6
Super key
AlphaWRITE 2.0 feature 6-6
SYSDCT
system memory utility D-1 to D-3
System initialization file 2-2
System memory
AlphaWRITE files 4-3

Terminal support
AlphaWRITE 2.0 feature 6-3
Text display ruler
AlphaWRITE 2.0 feature 6-7
measurement used 6-7
Titles
AlphaWRITE 2.0 feature 6-3
Top margin format setting
laser printers 6-2

Undelete
AlphaWRITE 2.0 feature 6-4
Upgrade tips 6-1 to 6-7
AlphaWRITE 1.2A to 2.1A 6-3 to 6-7
first time laser printing 6-7

VERIFY command
.DIR file column requirements 3-3, 4-4
WRITE.DIR file 3-3, 4-3, 4-4

Wheel option Queue command
AlphaWRITE 2.0 feature 6-6
WRITE command 3-5, 4-6
WRITE.DIR file
customizing for ersatz 3-3, 4-4
customizing for WRT: location 3-3, 4-4
WRITE.LIT
memory requirements 5-1
WRITE.NEW
AlphaWRITE 2.1C initialization file B-1, B-2
AlphaWRITE initialization default file 3-4, 3-5, 4-5
WRITE/P
command 3-5, 4-6
WRT000.OVR
memory requirements 5-1

WRT080.OVR
  memory requirements 5-2
WRT190.OVR
  memory requirements 5-3
WRT200.OVR
  memory requirements 5-3
WRT:
  account number for 3-2, 4-2
  ersatz 3-2, 4-2
  single version installation 4-2, 4-3