

Cisco CLI Cheat Sheet - Packet Tracer

Gestión básica

```
enable
configure terminal
end
exit
copy running-config startup-config
show running-config
show startup-config
```

Interfaces

```
interface gigabitEthernet0/0
ip address 192.168.X.1 255.255.255.0
no shutdown
exit
interface serial2/0
ip address 190.7.73.1 255.255.255.252
clock rate 2000000 # Solo en el DCE
no shutdown
exit
show ip interface brief # Verificación rápida
```

DHCP en el router

```
ip dhcp excluded-address 192.168.1.1 192.168.1.30
ip dhcp pool NOMBREPOOL
network 192.168.1.0 255.255.255.0
default-router 192.168.1.1
dns-server 192.168.200.5
end
show ip dhcp binding # Verificar leases
```

Relay DHCP

```
interface gigabitEthernet0/0
ip helper-address 192.168.100.10
```

Ruteo estático

```
ip route 1.1.1.0 255.255.255.0 190.7.73.2
ip route 1.1.2.0 255.255.255.0 190.7.73.2
```

Ruteo dinámico (RIP)

```
router rip
version 2
network 192.168.100.0
network 192.168.200.0
network 190.7.73.0
network 10.0.0.0
no auto-summary
show ip route
```

NAT

```
access-list 1 permit 192.168.66.0 0.0.0.255
interface gigabitEthernet0/0
ip nat inside
interface gigabitEthernet0/1
ip nat outside
ip nat inside source list 1 interface gigabitEthernet0/1 overload
show ip nat translations
show ip nat statistics
```

ACL

```
access-list 10 permit 192.168.100.0 0.0.0.255
access-list 10 deny any
interface gigabitEthernet0/0
ip access-group 10 in
```

Diagnóstico

```
ping 192.168.X.X
tracert 8.8.8.8
arp -a
ipconfig
```