EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · FRONT · SIDE 1 OF 2

Running the EOC (Emergency Operations Center) Message Center

Share this card

STARTING UP

1. **Double-click the EOC Server icon** on the Windows host laptop
   Window shows: `http://10.x.x.x:8080` — note this IP (Internet Protocol) address
2. **Overview tab: do each step of "Set up this EOC"** (its **Go** button). Share the URL (web address) with operators on the Wi-Fi.

RECEIVING MESSAGES

3. **Winlink Express: Open Session** for new mail
   Telnet with internet; Vara FM Winlink by radio. Activation: every 5 minutes.
4. Once: **choose the Winlink callsign** that feeds the EOC
   Click the blue bar: pick the Winlink Express folder (C:\RMS Express), then tick the callsign found.
5. **Watch the blue "WINLINK AUTO-INGEST ON" bar**
   Church forms appear on every screen within 10 seconds. Bar says OFF? Drag the .mime files onto the page.
6. **SITREP (situation report):** Disaster Reports tab → **Generate SITREP** (toolbar above the table) → **Copy** → send it up
   Satellite → Stake Center EOC. Stake → council line (Area Seventy) and welfare line: Welfare and Self-Reliance Manager (WSRM), then Area Welfare and Self-Reliance Manager (AWSRM).
7. **Stake EOC: forward the forms up the welfare line**
   Winlink Express: open the form message → Forward → the welfare line's Winlink address → Send. Every Disaster Report and Supply Order.

Every work item (Work Items tab): give it an owner now (HIGH items at once), move it (In work, Up, Done), and write the decision in.

Reports without Winlink. Phones: volunteers on the EOC Wi-Fi tap **Send to EOC** (the wall code). Other reports arrive as `.txt` files: save them into the **EOC Drop Folder** on the Desktop.

Paper by runner (Emergency): type it in at `http://<server-ip>:8080/forms/dr` (`so`, `wcl`) and tap **Send**.

Before the event: Python 3 from `python.org/downloads` (not the Microsoft Store placeholder) and Winlink Express · USB (Universal Serial Bus) thumb drives, one USB-C/Lightning for iPhones · **Export sheet JSON** (JavaScript Object Notation file) to every EOC · blank paper forms (form address + `?blank=1`, **Print**).

Turn over → Card 3, side 2: Tabs, Status, Shift Handoff, Roll-up & SITREP

EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · BACK · SIDE 2 OF 2

Tabs, Status, Shift Handoff, Roll-up & SITREP

TABS — WHAT GOES WHERE

Overview — the **Set up this EOC** checklist

Disaster Reports — damage by address; **Generate SITREP**

Supply Orders — requests + the welfare line's approval status

Work Crew Logs — crews, hours, homes completed

Roster — who has reported. Missionary bar: "no report has answered yet" until one does

Work Items — what the reports ask you to do or decide: owner, status, next action, decision

Messages — every record, **Via** = the EOC it came through · **Notes** — shift log

Status badges (click one to move it on): NEW just arrived, nobody has read it · ACK acknowledged: someone read it · ASSGN assigned: someone is acting on it · DONE handled.

Shift Handoff: Export Handoff JSON → USB drive → the incoming operator clicks Import Handoff JSON (it *replaces* the event's records: shift change only). **New emergency?** Setup tab → **Open a New Event** (the old event keeps its reports).

Roll-up to the EOC above you (Satellite → Stake → Council / Area EOC, if open): Setup tab: level, name and parent once → **Export Roll-up JSON** ("only new" ticked) with every SITREP, by the PACE (Primary, Alternate, Contingency, Emergency) level: **P/A** email to the parent's drop email · **C** Winlink attachment · **E** USB drive with the printed SITREP. The parent merges it by itself; nothing counts twice. **No Council / Area EOC open?** Items set Up go up only in the SITREP; phone or email the welfare line for anything urgent.

SITREP: first as soon as possible, then regular status reports on the interval leadership sets (Setup tab), to the Stake President, the council line (Area Seventy) and the welfare line (WSRM, AWSRM). Its header shows the **PACE level in force**. Send it by the roll-up's path.

Wall display (TV): open `http://<server-ip>:8080/wall`, press **F**. **Drill:** press **I am ready** on the drill bar; new to drills: card 9. Your level: cards 6–8.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/