# 21.13. ftplib — FTP protocol client

Source code: Lib/ftplib.py

This module defines the class FTP and a few related items. The FTP class implements the client side of the FTP protocol. You can use this to write Python programs that perform a variety of automated FTP jobs, such as mirroring other FTP servers. It is also used by the module urllib.request to handle URLs that use FTP. For more information on FTP (File Transfer Protocol), see Internet RFC 959.

Here's a sample session using the ftplib module:

```
>>>
>>> from ftplib import FTP
>>> ftp = FTP('ftp.debian.org')
                                   # connect to host, default port
>>> ftp.login()
                                   # user anonymous, passwd anonymous
'230 Login successful.'
>>> ftp.cwd('debian')
                                   # change into "debian" directory
>>> ftp.retrlines('LIST')
                                   # list directory contents
             1 1176
                        1176
                                      1063 Jun 15 10:18 README
-rw-rw-r--
drwxr-sr-x
             5 1176
                         1176
                                     4096 Dec 19
                                                   2000 pool
             4 1176
                                      4096 Nov 17
                                                   2008 project
drwxr-sr-x
                         1176
            3 1176
                                     4096 Oct 10 2012 tools
drwxr-xr-x
                         1176
'226 Directory send OK.'
>>> ftp.retrbinary('RETR README', open('README', 'wb').write)
'226 Transfer complete.'
>>> ftp.quit()
```

The module defines the following items:

```
class ftplib. FTP(host=", user=", passwd=", acct=", timeout=None, source address=None)
```

Return a new instance of the FTP class. When *host* is given, the method call connect(host) is made. When *user* is given, additionally the method call login(user, passwd, acct) is made (where *passwd* and *acct* default to the empty string when not given). The optional *timeout* parameter specifies a timeout in seconds for blocking operations like the connection attempt (if is not specified, the global default timeout setting will be used). *source\_address* is a 2-tuple (host, port) for the socket to bind to as its source address before connecting.

The FTP class supports the with statement, e.g.:

```
>>>
>>> from ftplib import FTP
>>> with FTP("ftp1.at.proftpd.org") as ftp:
       ftp.login()
       ftp.dir()
• • •
'230 Anonymous login ok, restrictions apply.'
dr-xr-xr-x 9 ftp
                       ftp
                                    154 May 6 10:43 .
dr-xr-xr-x 9 ftp
                       ftp
                                    154 May 6 10:43 ...
dr-xr-xr-x 5 ftp
                       ftp
                                  4096 May 6 10:43 CentOS
dr-xr-xr-x 3 ftp
                                      18 Jul 10
                                                2008 Fedora
                       ftp
>>>
```

Changed in version 3.2: Support for the with statement was added.

Changed in version 3.3: source\_address parameter was added.

class ftplib. **FTP\_TLS**(host=", user=", passwd=", acct=", keyfile=None, certfile=None, context=None, timeout=None, source\_address=None)

A FTP subclass which adds TLS support to FTP as described in RFC 4217. Connect as usual to port 21 implicitly securing the FTP control connection before authenticating. Securing the data connection requires the user to explicitly ask for it by calling the prot\_p() method. context is a ssl.SSLContext object which allows bundling SSL configuration options, certificates and private keys into a single (potentially long-lived) structure. Please read Security considerations for best practices.

*keyfile* and *certfile* are a legacy alternative to *context* – they can point to PEM-formatted private key and certificate chain files (respectively) for the SSL connection.

New in version 3.2.

Changed in version 3.3: source\_address parameter was added.

Changed in version 3.4: The class now supports hostname check with ssl.SSLContext.check\_hostname and Server Name Indication (see ssl.HAS SNI).

Deprecated since version 3.6: keyfile and certfile are deprecated in favor of context. Please use ssl.SSLContext.load\_cert\_chain() instead, or let ssl.create\_default\_context() select the system's trusted CA certificates for you.

Here's a sample session using the FTP\_TLS class:

```
>>> ftps = FTP_TLS('ftp.pureftpd.org')
>>> ftps.login()
```

```
'230 Anonymous user logged in'
>>> ftps.prot_p()
'200 Data protection level set to "private"'
>>> ftps.nlst()
['6jack', 'OpenBSD', 'antilink', 'blogbench', 'bsdcam', 'clockspee
```

#### exception ftplib.error reply

Exception raised when an unexpected reply is received from the server.

#### exception ftplib.error temp

Exception raised when an error code signifying a temporary error (response codes in the range 400–499) is received.

#### exception ftplib.error perm

Exception raised when an error code signifying a permanent error (response codes in the range 500–599) is received.

#### exception ftplib.error\_proto

Exception raised when a reply is received from the server that does not fit the response specifications of the File Transfer Protocol, i.e. begin with a digit in the range 1–5.

#### ftplib.all\_errors

The set of all exceptions (as a tuple) that methods of FTP instances may raise as a result of problems with the FTP connection (as opposed to programming errors made by the caller). This set includes the four exceptions listed above as well as OSError.

#### See also:

#### Module netro

Parser for the .netrc file format. The file .netrc is typically used by FTP clients to load user authentication information before prompting the user.

# 21.13.1. FTP Objects

Several methods are available in two flavors: one for handling text files and another for binary files. These are named for the command which is used followed by lines for the text version or binary for the binary version.

FTP instances have the following methods:

```
FTP. set debuglevel(level)
```

Set the instance's debugging level. This controls the amount of debugging output printed. The default, 0, produces no debugging output. A value of 1 produces a moderate amount of debugging output, generally a single line per request. A value of 2 or higher produces the maximum amount of debugging output, logging each line sent and received on the control connection.

#### FTP. **connect**(host=", port=0, timeout=None, source\_address=None)

Connect to the given host and port. The default port number is 21, as specified by the FTP protocol specification. It is rarely needed to specify a different port number. This function should be called only once for each instance; it should not be called at all if a host was given when the instance was created. All other methods can only be used after a connection has been made. The optional timeout parameter specifies a timeout in seconds for the connection attempt. If no timeout is passed, the global default timeout setting will be used. source\_address is a 2-tuple (host, port) for the socket to bind to as its source address before connecting.

Changed in version 3.3: source\_address parameter was added.

### FTP.getwelcome()

Return the welcome message sent by the server in reply to the initial connection. (This message sometimes contains disclaimers or help information that may be relevant to the user.)

## FTP. **login**(user='anonymous', passwd=", acct=")

Log in as the given *user*. The *passwd* and *acct* parameters are optional and default to the empty string. If no *user* is specified, it defaults to 'anonymous'. If *user* is 'anonymous', the default *passwd* is 'anonymous@'. This function should be called only once for each instance, after a connection has been established; it should not be called at all if a host and user were given when the instance was created. Most FTP commands are only allowed after the client has logged in. The *acct* parameter supplies "accounting information"; few systems implement this.

## FTP.abort()

Abort a file transfer that is in progress. Using this does not always work, but it's worth a try.

## FTP. **sendcmd**(*cmd*)

Send a simple command string to the server and return the response string.

### FTP. voidcmd(cmd)

Send a simple command string to the server and handle the response. Return nothing if a response code corresponding to success (codes in the range 200 –299) is received. Raise error reply otherwise.

### FTP. retrbinary(cmd, callback, blocksize=8192, rest=None)

Retrieve a file in binary transfer mode. *cmd* should be an appropriate RETR command: 'RETR filename'. The *callback* function is called for each block of data received, with a single bytes argument giving the data block. The optional *blocksize* argument specifies the maximum chunk size to read on the low-level socket object created to do the actual transfer (which will also be the largest size of the data blocks passed to *callback*). A reasonable default is chosen. *rest* means the same thing as in the transfercmd() method.

#### FTP. retrlines(cmd, callback=None)

Retrieve a file or directory listing in ASCII transfer mode. *cmd* should be an appropriate RETR command (see retrbinary()) or a command such as LIST or NLST (usually just the string 'LIST'). LIST retrieves a list of files and information about those files. NLST retrieves a list of file names. The *callback* function is called for each line with a string argument containing the line with the trailing CRLF stripped. The default *callback* prints the line to sys.stdout.

#### FTP. set\_pasv(val)

Enable "passive" mode if *val* is true, otherwise disable passive mode. Passive mode is on by default.

## FTP. **storbinary**(cmd, fp, blocksize=8192, callback=None, rest=None)

Store a file in binary transfer mode. *cmd* should be an appropriate STOR command: "STOR filename". *fp* is a file object (opened in binary mode) which is read until EOF using its read() method in blocks of size *blocksize* to provide the data to be stored. The *blocksize* argument defaults to 8192. *callback* is an optional single parameter callable that is called on each block of data after it is sent. *rest* means the same thing as in the transfercmd() method.

Changed in version 3.2: rest parameter added.

## FTP. storlines(cmd, fp, callback=None)

Store a file in ASCII transfer mode. *cmd* should be an appropriate STOR command (see storbinary()). Lines are read until EOF from the file object *fp* (opened in binary mode) using its readline() method to provide the data to be stored. *callback* is an optional single parameter callable that is called on each line after it is sent.

#### FTP. transfercmd(cmd, rest=None)

Initiate a transfer over the data connection. If the transfer is active, send an EPRT or PORT command and the transfer command specified by *cmd*, and accept the connection. If the server is passive, send an EPSV or PASV command, connect to it, and start the transfer command. Either way, return the socket for the connection.

If optional *rest* is given, a REST command is sent to the server, passing *rest* as an argument. *rest* is usually a byte offset into the requested file, telling the server to restart sending the file's bytes at the requested offset, skipping over the initial bytes. Note however that **RFC 959** requires only that *rest* be a string containing characters in the printable range from ASCII code 33 to ASCII code 126. The transfercmd() method, therefore, converts *rest* to a string, but no check is performed on the string's contents. If the server does not recognize the REST command, an error\_reply exception will be raised. If this happens, simply call transfercmd() without a *rest* argument.

#### FTP. **ntransfercmd**(*cmd*, *rest=None*)

Like transfercmd(), but returns a tuple of the data connection and the expected size of the data. If the expected size could not be computed, None will be returned as the expected size. *cmd* and *rest* means the same thing as in transfercmd().

## FTP. mlsd(path="", facts=[])

List a directory in a standardized format by using MLSD command (RFC 3659). If path is omitted the current directory is assumed. facts is a list of strings representing the type of information desired (e.g. ["type", "size", "perm"]). Return a generator object yielding a tuple of two elements for every file found in path. First element is the file name, the second one is a dictionary containing facts about the file name. Content of this dictionary might be limited by the facts argument but server is not guaranteed to return all requested facts.

New in version 3.3.

## FTP. nlst(argument[, ...])

Return a list of file names as returned by the NLST command. The optional *argument* is a directory to list (default is the current server directory). Multiple arguments can be used to pass non-standard options to the NLST command.

**Note:** If your server supports the command, mlsd() offers a better API.

## FTP.dir(argument[, ...])

Produce a directory listing as returned by the LIST command, printing it to standard output. The optional *argument* is a directory to list (default is the cur-

rent server directory). Multiple arguments can be used to pass non-standard options to the LIST command. If the last argument is a function, it is used as a *callback* function as for retrlines(); the default prints to sys.stdout. This method returns None.

**Note:** If your server supports the command, mlsd() offers a better API.

#### FTP. rename(fromname, toname)

Rename file *fromname* on the server to *toname*.

#### FTP. **delete**(filename)

Remove the file named *filename* from the server. If successful, returns the text of the response, otherwise raises error\_perm on permission errors or error reply on other errors.

#### FTP. **cwd**(pathname)

Set the current directory on the server.

#### FTP. **mkd**(pathname)

Create a new directory on the server.

#### FTP. pwd()

Return the pathname of the current directory on the server.

#### FTP. rmd(dirname)

Remove the directory named dirname on the server.

#### FTP. size(filename)

Request the size of the file named *filename* on the server. On success, the size of the file is returned as an integer, otherwise None is returned. Note that the SIZE command is not standardized, but is supported by many common server implementations.

#### FTP. quit()

Send a QUIT command to the server and close the connection. This is the "polite" way to close a connection, but it may raise an exception if the server responds with an error to the QUIT command. This implies a call to the close() method which renders the FTP instance useless for subsequent calls (see below).

## FTP. close()

Close the connection unilaterally. This should not be applied to an already closed connection such as after a successful call to quit(). After this call the

FTP instance should not be used any more (after a call to close() or quit() you cannot reopen the connection by issuing another login() method).

## 21.13.2. FTP\_TLS Objects

FTP TLS class inherits from FTP, defining these additional objects:

#### FTP\_TLS.ssl\_version

The SSL version to use (defaults to ssl.PROTOCOL\_SSLv23).

#### FTP\_TLS. auth()

Set up a secure control connection by using TLS or SSL, depending on what is specified in the ssl\_version attribute.

Changed in version 3.4: The method now supports hostname check with ssl.SSLContext.check\_hostname and Server Name Indication (see ssl.HAS SNI).

#### FTP\_TLS.ccc()

Revert control channel back to plaintext. This can be useful to take advantage of firewalls that know how to handle NAT with non-secure FTP without opening fixed ports.

New in version 3.3.

#### FTP TLS. prot p()

Set up secure data connection.

#### FTP\_TLS.prot\_c()

Set up clear text data connection.