Vendor panel (0.1.9)

The vendor panel is the seller's own control screen: one login that manages every client business, its outlets, licences, plans, payments and self-hosted servers. It runs inside the normal POS server on the seller's cloud only. Design and rulings V-1..V-20: `docs/superpowers/specs/2026-10-19-vendor-panel-design.md`.

Client kind	Where its data lives	How the panel reaches it
Cloud	Your server	Directly. Devices pull a new licence after their next sync
Self-host	The client's own server	Their server phones home once a day; offline = send the licence file
Standalone	The device only	You send the licence file; the shop imports it

Business contact shown to shops (app licence card, request buttons, website, guide): **+91 89229 62849** (WhatsApp/call) and **universalpos2026@gmail.com**; in the app it lives in `apps/pos/lib/seller_contact.dart`.

1. Turn it on (your cloud server only)

Add to the server `.env` (never on a client's self-hosted server):

```
POS_VENDOR_MODE=1
POS_LICENSE_KEY_FILE=/run/secrets/license.key   # the signing key, see server-setup.md section 3
```

Then migrate and create the one vendor login:

```
python -m app.cli migrate                       # applies 0008 (vendor tables, device roles)
python -m app.cli create-vendor-admin --email seller@example.com   # asks for a password, 12+ characters
```

Open `https://pos.example.com/vendor/` and log in. The panel needs HTTPS (its cookie is `Secure`). Without `POS_VENDOR_MODE=1` every `/vendor` address answers 404.

Login is e-mail and password only. Five wrong tries a minute from one address are refused for a minute. A session ends after 30 minutes without use (`POS_VENDOR_SESSION_MINUTES`). Every change is written to the audit log.

2. Plans

`python -m app.cli seed-plans` adds the website's plans once (trial, monthly, quarterly, half-yearly, annual, 2-year, 3-year, 5-year, lifetime; price per device, every feature, no role slots or limits, the website's "Includes" text for invoices). Running it again adds only the plans that are missing.

Plans → name a plan (for example `Retail`, `Restaurant`) → save its first version: price, period in months, device slots per role (till, waiter, kitchen, kiosk), limits (products, customers, categories) and features.

- A saved version never changes. Saving again makes the next version; outlets stay on their version until you move them (**Move outlets to another version** re-signs their licences).
- A blank slot or limit box means no limit for that role or kind.
- When a plan has no role slots, **Total devices** is the device limit.

3. Add a client

Businesses made before 0.1.6 with the CLI: `python -m app.cli import-existing` adds each as a cloud client with its shops and every stored licence as history (files unchanged, nothing re-signed). Running it again adds only new ones. Licences signed offline with `tools/license_tool` were never stored on the server; add those clients by their licence request.

New client (top bar, or `+` on the phone tab bar) opens a 5-step wizard. **Next** checks each step before moving on; **Back** keeps everything you typed.

1. **Details**: business, owner, WhatsApp phone, e-mail, GSTIN, city.
2. **How it runs**: pick the card: Standalone, Self-host or Our cloud.
3. **Outlets**:
4. Standalone / self-host: ask the shop to open **Settings** → **License** → **Request / renew licence** and send you the text. Paste one or more requests (or type the business id and shop id).
5. Cloud: type one outlet name per line and the shop admin's e-mail.
6. **Plan & licence**: pick a plan card (or Custom), change any value for this client only (empty box = no limit), set the last valid day.
7. **Review & sign**: the summary of what you typed. **Check outlets** shows the ids the panel read; **Create client and sign** does it.

Result:

- Standalone / self-host: a licence file per outlet (download, or copy the text). The shop imports it in **Settings** → **License**.
- Cloud: the shop admin's login (temporary password, shown once) and a pair code per outlet. Tills pair with those codes (pair codes are single use and short-lived; make new ones from the client page).

Another outlet of the same business: on the new device choose **New outlet of an existing business** in first setup and type or scan the business id (on the first outlet: **Settings** → **License** → **Business id**). Then add the outlet on the client page with its licence request. Outlets installed separately before this can still be added to the same client; they stay separate businesses for data.

4. Daily use

The panel has a left sidebar (Dashboard, Clients, Licences, Payments, Revenue, Plans, Self-host, Audit, Help), a search box in the top bar (press `/`; finds names, phones, tenant and shop ids) and a light/dark switch. On a phone the menu button opens the sidebar and a bottom bar holds Home, Clients, New, Revenue and Help.

- **Dashboard**: tiles for clients, active outlets, licences expiring within 14 days, overdue (grace or expired) and revenue this month against last month. **Needs action** has tabs: Expiring, In grace, Expired, Over limit, Devices quiet, Self-host quiet. Each row has **Renew** and **WhatsApp** (a ready reminder to the owner).
- **Renew** (dashboard row, outlet card or Licences list): pick 1, 3, 6 or 12 months; the amount is filled in from the plan price × devices × months and can be changed; method, reference, paid date → **Renew & record payment**. The licence is re-signed and the payment saved in one step. An expired licence restarts from today.
- **Client page**: header with status and WhatsApp / Call / E-mail buttons, **Edit details**, and tabs **Outlets** (licence summary per outlet, Renew, Change licence, licence file, pair code, history), **Payments**, **Devices** (cloud: role, last seen, revoke) and **Activity**.
- **Record payment** (client header): amount, method (UPI, bank, cash, other), reference, months; with **Extend** ticked each chosen outlet's licence moves by the months paid.
- **Change licence**: plan cards and every value editable for this outlet; the **Preview** panel shows the licence and what changes while you type; **Sign licence** issues it. Cloud tills pick it up after their next sync; standalone shops need the new file.
- **Licences**: every outlet's current licence, soonest end first, filter by status.
- **Payments**: all payments with month and method filters and the total. **Revenue**: the last 12 months as bars, money due this month (licences ending, at plan price) and the top 10 clients.
- **Move to our cloud** (standalone or self-host client): creates the business and shops on this server with the same ids and copies their licences. The shop then pairs its tills with no wipe.

Limits (products, customers, categories) only warn: the shop sees "Plan limit passed" and you see the outlet under **Over quota**; nothing is blocked or deleted. Device slots are enforced when a till pairs or changes role; a till that is over its slots after a smaller licence keeps working and shows a banner.

5. Self-hosted clients (not offered)

Not sold to clients (owner, 2026-10-20): server code never leaves your machines. The wizard has no Self-host choice and the website no self-host plan; the code below stays for your own servers

only.

Send the client `universal-pos-server_<version>_amd64.deb`, their licence file and (below) a phone-home token; their IT person follows self-host.md (`sudo apt install ./…deb`, then `sudo pos-server setup`).

Self-host → pick the client, name the server → **Make token**. The token is shown once. On the client's server add to its `.env` and restart:

```
POS_VENDOR_URL=https://pos.example.com
POS_VENDOR_TOKEN=<token>
```

It checks in 60 seconds after start and then every 24 hours: it sends device counts per role and the latest usage, and imports any newer licence you signed for its shops. Run it at once with `python -m app.cli vendor-checkin`. If it cannot reach you nothing changes; licences run to their end date, then the normal 30 days of grace.

Offline self-hosted server: download the licence file in the panel and run `python -m app.cli import-license --file outlet.poslicense` on that server.

6. Shop admins can no longer sign licences

`POST /v1/shops/{id}/license` is gone. A shop admin can only upload a licence you signed (`POST /v1/shops/{id}/license/import`). The CLI `issue-license` still works where the signing key is, and takes `--roles till=3,kiosk=1` and `--quotas products=5000`.

7. Help page

Help (sidebar) lists every link and command the seller needs, each command with a **Copy** button: issue licence, pair code, shop admin login, seed plans, import earlier clients, migrate, start the server, health check, backup, builds and tests. It also shows the support contact shops see, the server version and the database revision.

Your private addresses are read from the server env (never committed): `POS_VENDOR_PANEL_URL` (shop web panel), `POS_VENDOR_PUBLIC_URL` (this server's public address), `POS_VENDOR_WEBSITE_URL`, `POS_VENDOR_RELEASES_URL`. Unset ones show "not set". Guide PDFs appear after `bash tools/vendor_docs.sh` (copies the newest ones from `dist/`).

8. Invoices

Every payment you record gets an invoice at once, numbered `UP/2026-27/0001` (prefix, Indian financial year 1 April to 31 March, a counter that restarts each year; no gaps, no duplicates).

1. **Invoices** → **Invoice settings** (once): trade name, address and state are required; PAN, GSTIN, phone, e-mail, UPI ID, bank details, footer note and the number prefix are optional. Saved in the server database only.
2. Record a payment (client page or **Renew**). The payment row shows the invoice number. Payments recorded before the settings were filled show **Create invoice**; the invoice takes the payment's date and that year's next number.
3. Open the invoice → **Download PDF** → **WhatsApp** or **E-mail** opens a ready message to the client; attach the PDF and send.

Item	How it works
Type	No GSTIN in settings: **Bill of supply** ("Supplier not registered under GST; no tax charged"). With a GSTIN: **Tax invoice** for new invoices; the amount you record includes GST (18%: CGST 9% + SGST 9% when your state is the client's, else IGST 18%). Earlier invoices never change.
Lines	One per outlet the payment extended: plan, months, outlet, period, devices × plan price, SAC 998434, the plan's "Includes" text. Multi-device (3+ 10%, 5+ 15%) and multi-year (24/36/60 months 10/15/20%) discounts as on the website; if you received a different amount, a "Special discount / adjustment" row makes the total equal the payment.
Client details	Address, state and pincode on the client (wizard step 1 or **Edit details**). Without a state the invoice says "Place of supply: (not given)".
Changes	An issued invoice never changes, even when the client, plan or settings change later. Wrong one? **Cancel invoice** (reason required): the number stays used and the PDF shows CANCELLED. Then **Create invoice** on the payment for a new number.
Free payments	₹0 payments and the trial get no invoice.

9. Licence QR and backup keys (0.1.8)

- **QR:** client page → outlet card → **QR** shows the signed licence as a QR code. On the till: **Settings** → **License** → **Scan QR** (phones and tablets). Same file as **Download**, no internet needed.
- **Backup key:** from 0.1.8 every licence the panel signs carries the outlet's secret `backup_key` (made once per outlet, the same in every renewal, never shown in the change list). The till uses it to lock its `.posbackup` files, so a backup opens only with that outlet's licence. **Send every existing outlet a freshly signed licence once** (Change licence → Sign, or Renew): until then its backups are only protected against damage, and the till's Backup card says so. Licences made with the `issue-license` command have no backup key.