Overview

Kaui lets you configure basic settings for how the system behaves when an account is overdue. For overdue configuration, you define:

- · The various states that the account must go through
- The change in users' entitlements when the account is transitioned from one state to the other
- The period after which the state is re-evaluated

These three pieces of information make up the *overdue flow*.

Overdue configuration applies at the tenant level. However you can also configure overdue flows for the *global* Kill Bill system.

In Kaui, overdue configuration is a subset of the full overdue configuration settings. For more information on the full configuration settings and global settings, see the *Overdue System Guide*.

See the following sections to create overdue (dunning) flows for a tenant:

- View overdue configuration
- Create overdue flows
- Upload an XML overdue configuration file
- View overdue configuration as XML
- Delete overdue flows

Additional Overdue Resources

- "Overdue" section in the Subscription Guide.
- Overdue System Guide

View Overdue Configuration


If any overdue (dunning) flows are configured, you can see them on the Overdue Show tab at the bottom of the Tenant Configuration page. To get there:

1. Click on your username and tenant name in the upper right corner:



Kaui displays the Tenant Configuration page.


2. Scroll down and click on the Overdue Show tab:



Create Overdue Flows


The following steps explain how to set up overdue flows (i.e., actions) for the tenant.

1. Go to the Overdue Show tab on the Tenant Configuration page.



2. Click the plus sign () next to **Existing Overdue Config**.

Kaui opens the Overdue Configuration screen:




3. Click + New Overdue States. Kaui opens the fields for editing:




4. Fill in the fields for the current row. For field information, see the Overdue Configuration Field

Descriptions table.

5. To add another overdue configuration row, click + **new overdue states**.



6. When you are done adding configuration rows, click the **Save** button. Kaui displays a success message at the top of the screen and displays the new overdue flow(s) on the Overdue Show tab.





Note: To edit an existing overdue flow, on the Overdue Show tab, click the plus sign () next to **Existing Overdue Config.** This opens the overdue configuration fields in edit mode.

Overdue Configuration Field Descriptions

Field	Description
Name	The name assigned to the overdue state.
External Message	Message text that other plugins, when listening for overdue events, can retrieve and display to the user. (Optional)
Block Subscription Changes	If set to true, the customer <i>cannot</i> make plan changes to the subscription in this overdue flow. If set to false, the customer is allowed to make changes.

Field	Description
Subscription Cancellation	 Select the option that describes how Kill Bill behaves regarding a cancellation in this overdue flow: NONE: Kill Bill ignores this field, and the subscription is not cancelled. POLICY_NONE: Same as NONE above. POLICY_IMMEDIATE_POLICY: Cancels the subscription immediately and applies a partial credit to the account based on how much of the service has been consumed. POLICY_END_OF_TERM: Cancels the subscription at the end of the billing period with no refund to the customer (i.e., no proration).
Days Since Earliest Unpaid Invoice	Specifies how many days should pass after the last unpaid invoice before initiating this overdue flow.
Tag Inclusion	Specifies that the overdue flow will occur if the account has a system (control) tag matching the one selected here. To disregard tag inclusion for this overdue flow, leave as the default NONE setting. • AUTO_PAY_OFF • AUTO_INVOICING_OFF • OVERDUE_ENFORCEMENT_OFF • MANUAL_PAY • TEST • PARTNER For a description of system tags, see the "Tags" section of the Subscription Guide.
Tag Exclusion	Specifies that overdue flow will occur if the account has NO system (control) tags matching the one selected here. To disregard tag exclusion for this overdue flow, leave as the default NONE setting.
Number of Unpaid Invoices	Specifies that the overdue flow will occur if the number of unpaid invoices equals or exceeds the specified value.
Total Unpaid Invoice Balance	Specifies that the overdue action will occur if the total unpaid invoice balance equals or exceeds the specified value.

Upload an XML Overdue Configuration File


Kill Bill overdue configuration is stored in XML format. This section explains how to upload an XML file that contains the overdue configuration.

DRAFT



Note: You cannot edit a raw overdue configuration XML file in Kaui.

1. Go to the Overdue Show tab on the Tenant Configuration page.



Kaui opens the Overdue Configuration screen:



3. Click **Enable Advanced Configuration (Upload XML)**. Kaui displays an upload screen:




4. Click the **Choose File** button, locate the XML file, and select it.

Once you have selected the file, Kaui displays the filename next to the **Choose File** button.




5. Click the **Upload** button.

If the upload is successful, Kaui displays a success message at the top of the screen and displays the overdue flow(s) on the Overdue Show tab.



View Overdue Configuration as XML


1. Go to the Overdue Show tab on the Tenant Configuration page.



- 3. To return to Kaui, click the Back arrow button of your browser.

Delete Overdue Flows


1. Go to the Overdue Show tab on the Tenant Configuration page.



2. Click the plus sign (🛨) next to **Existing Overdue Config.**

Kaui opens the Overdue Configuration screen.

3. Click the red X(X) to the right of every configuration row you want to delete.



4. Click the **Save** button.

Kaui removes the overdue configuration row(s) from the Overdue Show tab and displays a delete confirmation message.