



MX Linux ユーザーマニュアル

v. 20230630

manual AT mxlinux DOT org

Ctrl-F = マニュアル内検索

Glossary = 第8章

Translations by [DeepL](#)

目 次

1はじめに.....	4
1.1 このマニュアルについて.....	4
1.2 MX Linux について.....	5
1.3 情報を得る！	7
1.4 サポートと EOL.....	7
翻訳者のための注意事項.....	8
2インストール.....	9
2.1 はじめに.....	9
2.2 ブータブルメディアの作成.....	11
2.3 プリインストール.....	15
2.4 第一印象.....	20
2.5 インストール手順.....	34
2.6 トラブルシューティング.....	43
3 設定（環境設定）	46
3.1 Peripheral Devices 周辺機器.....	46
3.2 基本的な MX ツール.....	55
3.3 ディスプレイ.....	75
3.4 ネットワーク.....	82
3.5 ファイル管理.....	94
3.6 Sound.....	101
3.7 Localization.....	103
3.8 Customization.....	107
4 Basic use.....	125
4.1 Internet.....	125
4.2 Multimedia.....	126
4.3 Office.....	132
4.4 Home.....	136
4.5 Security.....	137
4.6 Accessibility.....	140
4.7 System.....	140
4.8 Good practices.....	148
4.9 Games.....	151
4.10 Google tools.....	158
4.11 Bugs, issues and requests.....	159
5 Software Management.....	160
5.4 Troubleshooting Synaptic issues.....	169
5.5 Other methods.....	170
5.5.3 Self-contained packages.....	172
5.5.5 More install methods.....	173
5.5.6 Links.....	174
6 Advanced use.....	175
6.1 Windows programs under MX Linux.....	175
6.2 Virtual machines.....	176
6.3 Alternate Window Managers.....	180
6.4 Command Line.....	181
6.5 Scripts.....	185
6.6 Advanced MX Tools.....	189

6.7	SSH (Secure Shell).....	193
6.8	Synchronization.....	194
7	Under the hood.....	195
7.1	Introduction.....	195
7.2	The file system structure.....	195
7.3	Permissions.....	199
7.4	Configuration files.....	201
7.5	Runlevels.....	203
7.6	The kernel.....	204
7.7	Our positions.....	207
8	Glossary.....	211

1 はじめに

1.1 このマニュアルについて




図 1-1: マニュアルの必要性 ([xkcd.com](https://xkcd.com/1192/)).

MX ユーザーマニュアルは、 MX Linux コミュニティの多くのボランティアグループによる成果物です。そのため、必然的に誤字や脱字が含まれますが、それらを最小限にするよう努力しています。下記のいずれかの方法で、フィードバック、修正、提案をお送りください。必要に応じて更新を行います。

本マニュアルは、MX Linux を入手し、インストールし、自分のハードウェアで動作するように設定し、日常的に使用するまでのステップを、新しいユーザーに順を追って説明するためのものです。読みやすい一般的な入門書を目指し、利用可能な場合はグラフィカルなツールを優先しています。詳細なトピックや頻度の低いトピックについては、Wiki やその他のリソースを参照するか、[MX Linux フォーラム](#)に投稿してください。

MX Fluxbox は Xfce や KDE と大きく異なるため、このマニュアルを長く複雑にするため、ここには含まれていません。MX Fluxbox のインストールには、別のヘルプ文書が付属しています。

初めてお使いになる方は、本マニュアルで使われている用語の中には、馴染みのないものや分かりにくいものがあるかもしれません。私たちは難しい用語や概念の使用を制限するよう努めましたが、やむを得ないものもあります。巻末の用語集には、難解な文章を理解するのに役立つ定義やコメントが記載されています。

すべてのコンテンツは © 2021 by MX Linux Inc. であり、GPLv3 の下で公開しています。引用される場合は次のように表示してください:

MX Linux Community Documentation Project. 2023. Users Manual for MX Linux.

フィードバック:

- 電子メール: manual AT mxlinux DOT org

- ・ フォーラム: [MX Documentation and Videos](#)


1.2 MX Linux について

MX Linux を含め、どんなオペレーティングシステムに対しても、ユーザーの態度は実にさまざまです。ある人は、要求に応じて熱い飲み物を作ってくれるコーヒーポットのように、単純に動作する家電製品のような物が欲しいだけかもしれません。また別のある人は、実際にどのように動作するのか、つまり、なぜコーヒーが出るのに、どうぞろしたものが出ないのかに興味があるかも知れません。このセクションは、2番目のグループに方向性を与えることを意図しています。最初のグループに入る方は、セクション 1.3 「情報を得よう！」にお進みください。

MX Linux は、1990 年代初頭に始まった [GNU](#) の自由なソフトウェアのコレクションと Linux カーネルの融合のデスクトップ版です。[GNU/Linux](#) は、よりシンプルに、一般的に「Linux」と呼ばれ、カーネルからツール、ファイル構造(セクション 7)に至るまで、ユニークで非常に成功したアプローチを持つ、フリーでオープンソースのオペレーティングシステム(OS)です。Linux は、[ディストリビューション](#)や "ディストロ" を通じてユーザーに提供されますが、その中でも最も古く、最も人気のあるもののひとつが [Debian](#) であり、MX Linux はその Debian をベースに構築されています。

1.2.1 Linux

概要を簡単に説明するために、『*Anatomy of Linux kernel*』から Linux OS の簡略図と説明を引用します。



- ・ 最上部はユーザースペースで、アプリケーションスペースとも呼ばれます。ここでは、ディストリビューションが提供する、あるいはユーザーが追加したアプリケーションが実行され

ます。アプリケーションとカーネルを接続する GNU C ライブラリ (*glibc*) インターフェースもあります。（このため、図に示す「GNU/Linux」という別称があります）。

- ユーザー空間の下にはカーネル空間があり、Linux カーネルが存在します。カーネルはハードウェア・ドライバによって支配されています。

ファイルシステム

多くの Linux 初心者が最初に悩む問題の 1 つは、ファイルシステムの仕組みです。多くの新規ユーザーは、例えば **C:** ライブや **D:** ドライブを探すのに無駄に探したことがあると思いますが、Linux はハードディスクやその他の記憶媒体の扱いが Windows とは異なります。MX Linux は、各デバイスに個別のファイルシステム・ツリーを持つのではなく、単一のファイルシステム・ツリー（ファイルシステムの **root** と呼ばれる）を持ち、このツリーは "/" と表記され、接続されているすべてのデバイスを含みます。ストレージデバイスがシステムに追加されると、そのファイルシステムはファイルシステムのディレクトリまたはサブディレクトリにアタッチされます。これをドライブまたはデバイスのマウントと呼びます。また、各ユーザーは **/home** の下に専用のサブディレクトリを持ち、デフォルトではここで自分のファイルを探すことになります。詳しくはセクション 7 をお読みください。

MX Linux のほとんどのプログラムとシステム設定は、個別のプレーンテキストによる設定ファイルに保存されています。このファイルは、プログラムの起動時の動作を記述するパラメータと値の単純なリストです。

留意点

真新しいユーザーは、これまでの経験からの期待を持ってやって来ます。これは自然なことですが、最初は混乱やフラストレーションにつながります。心に留めておくべき 2 つの基本的な考え方があります：

1. MX Linux は Windows ではありません。上記の通り、レジストリも **C:** ドライブもなく、ほとんどのドライバはすでにカーネルに入っています。
2. MX Linux は Ubuntu ファミリーではなく、Debian そのものをベースにしています。このため、Ubuntu ファミリーのコマンド、プログラム、アプリケーション（特に「Personal Package Archives」または PPA に含まれるもの）が正しく機能しなかったり、欠落していることがあります。

1.2.2 MX Linux

2014 年に初めてリリースされた MX Linux は、[antiX](#) と旧 [MEPIS](#) コミュニティの共同事業であり、それぞれのディストロから最高のツールと才能を使用し、ウォーレン・ウッドフォード (Warren Woodford) が元々作成した作業とアイデアを含んでいます。この OS は、エレガントで効率的なデスクトップとシンプルな構成、高い安定性、確かなパフォーマンス、中程度のフットプリントを組み合わせるように設計されたミッドウェイト OS です。

Linux とオープンソースコミュニティによる優れたアップストリームワークに依存し、MX-23 では、デスクトップ環境として、KDE/Plasma とともに、フラッグシップの [Xfce4.18](#) を導入しています。5.27 と Fluxbox 1.3.7 を別々の独立したバージョンとしてリリースしました。これらはすべて、[Debian 安定版](#) (Debian 12, "Bookworm") をベースとしており、中核となる antiX システム

ムも利用しています。継続的なバックポートやレポジトリへの外部からの追加により、ユーザーの要求に応じてコンポーネントを最新の状態に保つことができます。

MX 開発チームは、様々な経歴、才能、興味を持つボランティアのグループで構成されています。詳しくは、[私たちについて](#)をご覧ください。このプロジェクトの継続的な強力なサポートに対して、MX Linux のパッケージャ、ビデオ制作者、偉大なボランティア、そしてすべての翻訳者に特別な感謝を捧げます！

1.3 情報を得る！

デスクトップのアイコンは、FAQ とユーザーマニュアルの 2 つの有用な文書にリンクしています。

- FAQ は、フォーラムで最もよく寄せられる質問に答えることで、新規ユーザーのための簡単なオリエンテーションを提供します。
- ユーザーマニュアルには、OS の詳細が書かれています。このマニュアルを隅から隅まで読む人はほとんどいないでしょうが、1) アウトラインを使って興味のあるトピックにジャンプしたり、2) $Alt + F1$ を押してマニュアルを開き、 $Ctrl + F$ を押して特定の項目を検索したりすることで、素早く参照することができます。
- その他の情報源としては、[フォーラム](#)、[Wiki](#)、オンラインビデオコレクション、各種ソーシャルメディアのアカウントなどがあります。これらの情報源には、[ホームページ](#)から簡単にアクセスできます。

1.4 サポートと EOL

MX Linux にはどのようなサポートがありますか？ この質問に対する答えは、あなたが意味するサポートの種類によって異なります：

- ユーザーベースの問題.** MX Linux には、公式文書やビデオ、フォーラム、検索エンジンなど、さまざまなサポートの仕組みがあります。詳しくは[コミュニティサポートのページ](#)をご覧ください。
- ハードウェア.** ハードウェアは、継続的な開発が行われているカーネルでサポートされています。非常に新しいハードウェアはまだサポートされていないかもしれませんし、非常に古いハードウェアはまだサポートされているとはいえ、デスクトップやアプリケーションの要求にはもはや十分ではないかもしれません。しかし、ほとんどのユーザーは、自分のハードウェアのサポートが利用可能であることに気づくでしょう。
- デスクトップ.** Xfce4 は開発中の成熟したデスクトップです。MX Linux に同梱されているバージョン (4.18) は安定版とみなされています。重要なアップデートが利用可能になり次第、適用されます。KDE/Plasma 環境は継続的にメンテナンスされています。

- **アプリケーション.** アプリケーションは、MX Linux のどのバージョンがリリースされた後でも開発され続けているため、出荷されたバージョンは時間の経過とともに古くなっています。この問題は、いくつかのソースを組み合わせることで対処しています: Debian (Debian バックポートを含む)、個々の開発者 (MX Devs を含む)、コミュニティのパッケージングチームが、可能な限りユーザのアップグレード要求を受け入れています。新しいパッケージがダウンロード可能になると、MX Updater が知らせてくれます。
- **セキュリティ.** Debian からのセキュリティアップデートは MX Linux ユーザを最大 5 年間カバーします。利用可能かどうかの通知については MX Updater を見てください。

翻訳者のための注意事項

ユーザー マニュアルを翻訳する人のためのオリエンテーション:

- 最新リリースの英語版テキストは [GitHub のレポ](#)にあります。翻訳は "tr" ディレクトリに保存されています。
 - You can work within the GitHub system: [clone](#) that main repo, make changes and then make a [pull request](#) to have it reviewed for merging with the source. GitHub のシステム内で作業することができます: メインレポをクローンし、変更を加え、[プルリクエスト](#)を行い、ソースにマージするためのレビューを受けてください。
 - あるいは、興味のあるものをダウンロードし、ローカルで作業してから、*manual AT mxlinux DOT org* に電子メールを送るか、フォーラムに投稿して、準備ができたことを通知することもできます。
- 重要性の観点から、新規ユーザーに最も関連性の高い情報を提供するセクション 1 ~ 3 から始めることをお勧めします。それが終われば、後のセクションを翻訳している間に、部分的な翻訳としてユーザーに配布することができます。
- 利用可能な翻訳は、[MX/antiX Wiki](#) で追跡できます。

2 インストール

2.1 はじめに

MX Linux のライブ・メディア（USB メモリまたは DVD）は、ハードディスクにアクセスせずにコンピュータを起動します。仮想ファイルシステムを RAM にコピーし、コンピュータの一時的なオペレーティング・システムの中心として動作します。ライブセッションを終了すると、コンピュータのすべてが元の状態に戻り、変更されません（セクション 6.6.1 を参照してください）。これには多くのメリットがあります：

- MX Linux をインストールすることなく、コンピュータ上で MX Linux を実行することができます。
- これによって、MX Linux がお使いのハードウェアと互換性があるかどうかを判断することができます。
- これは、MX Linux がどのように動作するかを感じ、その機能のいくつかを探求するのに役立ちます。
- 現在のシステムに永久的な影響を与えることなく、MX Linux があなたの望むものかどうかを判断することができます。

Live メディアからの実行には、いくつかの欠点もあります：

- システム全体が RAM と Live メディアの組み合わせで動作しているため、MX Linux はハードドライブにインストールした場合よりも多くのメモリを必要とし、動作が遅くなる可能性があります。
- 特殊なドライバやカスタム設定を必要とする珍しいハードウェアの中には、（DVD のような）読み取り専用のライブセッションで動作せず、永続的なファイルをインストールできないものがあります。私たちのパーシステンス機能付き USB メモリには、この問題はありません。

2.1.1 PAE か non-PAE か？

MX Linux は、[32 ビット](#)と [64 ビット](#)の 2 つのアーキテクチャで利用可能で、どちらも[物理アドレス拡張](#) (PAE) が有効になっています。PAE は、32 ビット OS が約 4 GB を超える RAM にアクセスできるようにする方法です。non-PAE バージョンを PAE システムで使用することは可能ですが、その逆はできません。あなたのマシンが PAE を扱えない場合（つまり、非常に古い場合）、代わりに姉妹ディストロの [antiX Linux](#) をインストールすることをお勧めします。

PAE 版と non-PAE 版のどちらが必要かわからない場合は、現在使用している OS に適した以下の方法を使用してください。

- Linux. 端末を開き、次のコマンドを入力します（必要であれば、最初に inxi をインストールします）：inxi -f. CPU Flags の項目に PAE が含まれていない場合、MX Linux をインストールすることはできません。
- Mac. インテル版 OSX は PAE をサポートしています。
- Windows®
 - Windows2000 以前: non-PAE

- Windows XP および Vista. [マイコンピュータ] を右クリックし、[プロパティ] の [全般] タブを開きます。一番下に Physical Address Extension (=PAE) と表示されていれば、PAE がインストールすべき正しいバージョンです。
- Windows 7. スタートボタン > すべてのプログラム > アクセサリ > コマンドプロンプトの順にクリックして、コマンドプロンプトウィンドウを開きます。端末ウィンドウが表示されます。カーソルが置かれているコマンドプロンプトに次のコードを入力します:

```
wmic os get PAEEnabled
```

PAE が有効になつていれば、次のようなリターンが返ってきます: PAEEnabled. この返り値の後に TRUE が続くこともあります、続かないこともあります。
- Windows 8 以降。デフォルトで PAE が有効。

2.1.2 32 ビット版か 64 ビット版か？

お使いの CPU のアーキテクチャは？

お使いのマシンが 32 ビットか 64 ビットかを調べるには、以下の手順に従ってください。*

- Linux. ターミナルを開き、`lscpu` コマンドを入力し、最初の数行でアーキテクチャ、コア数などを調べます。
- Windows. [マイクロソフトのこの文書](#)を参照してください。
- Apple. [Apple のこの文書](#)を参照してください。

* OS のアーキテクチャを知りたい場合は、`uname -m` というコマンドがすべての Linux ディストロと macOS で使えます。

一般的に、64 ビットの CPU と、お使いのマシンとプロセッサーに必要な容量のメモリがあれば、64 ビット版を使うべきです。64 ビットの方が一般的に高速だからですが、日常的な使用ではその違いに気づかないかもしれません。さらに長期的に見れば、64 ビット・バージョンに制限される大規模なアプリケーションが増えしていくでしょう。なお、32 ビットのアプリケーションや OS は 64 ビット CPU 上で動作させることができますが、その逆はできません。

詳しくは[こちら](#)をご覧ください。

メモリ (RAM) の容量は？

- Linux の場合。端末を開いて、`free -h` コマンドを入力し、合計欄の数字を見ます。
- Windows の場合。お使いのバージョンで推奨されている方法で「システム」ウィンドウを開き、"Installed memory (RAM)" という項目を探します。
- Apple の場合。Mac OSX のアップルメニューにある「この Mac について」という項目をクリックし、RAM 情報を探してください。

2.1.3 システム要件

ハードドライブにインストールされた MX Linux システムには、通常、以下のコンポーネントが必要です。

最低限

- CD/DVD ドライブ（およびそのドライブから起動可能な BIOS）または 4 GB の USB メモリ（および USB から起動可能な BIOS）
- 最新の i686 インテルまたは AMD プロセッサ
- 1 GB のメモリ (RAM)
- 6 GB のハードディスク空き容量

おすすめ

- CD/DVD ドライブ（およびそのドライブからブート可能な BIOS）、または 8 GB の USB メモリ（パーシステンスを使用する場合）（および USB からブート可能な BIOS）
- 最新の i686 インテルまたは AMD プロセッサ
- 2 GB 以上のメモリ (RAM)
- 20 GB 以上のハードディスク空き容量
- 3D デスクトップ対応の 3D 対応ビデオカード
- SoundBlaster、AC97、または HDA 互換のサウンドカード

注: MX Linux 64 ビット・ユーザーの中には、一般的な使用には 2 GB の RAM で十分だという人もいますが、メモリを大量に消費するプロセス（リマスタリングなど）やアプリケーション（オーディオエディタやビデオエディタなど）を実行する場合は、少なくとも 4 GB の RAM を推奨します。

2.2 ブータブルメディアの作成

2.2.1 ISO イメージの入手

MX Linux は、[ISO 9660](#) ファイルシステム形式のディスクイメージファイルである ISO イメージとして配布されています。[ダウンロードページ](#)で 2 つのフォーマットで入手できます。

- あるバージョンのオリジナルのリリース。
 - これは、一度リリースされると変更されない静的バージョンです。
 - リリースから時間が経てば経つほど、最新のものではなくなっています。
- あるバージョンの月例アップデート。この月例 ISO イメージは、MX スナップショット（セクション 6.6.4 を参照）を使用してオリジナルのリリースから作成されます。

- オリジナルのリリースからのすべてのアップグレードが含まれているため、インストール後に大量のファイルをダウンロードする必要がありません。
- また、最新バージョンのプログラムでライブセッションを実行することもできます。
- ダイレクト・ダウンロードでのみ入手可能です！



Windows から antiX/MX ライブ USB を作る

購入

ISO イメージがプリインストールされた USB ドライブやコンピュータなどは、[ハードウェアのページ](#)に掲載されています。




図 2-1 :MX Linux ミラーの分布（2021 年 9 月）。

ダウンロード

MX Linux は、[ダウンロードページ](#)から 2 つの方法でダウンロードできます。

- **ダイレクトの場合。** ダイレクト・ダウンロードは、ダイレクト・レポまたはミラーからご利用いただけます。ISO イメージをハードディスクに保存してください。あるソースが遅いと感じたら、別のソースを試してみてください。オリジナルリリースと月例アップデートの両方が利用可能です。
- **Torrent の場合。** [BitTorrent](#) ファイル共有は、効率的な大量データ転送のためのインターネットプロトコルを提供します。良好な帯域幅の接続を利用し、低帯域幅の接続への負担を最小限に抑えるように、転送を分散化します。さらに、すべての BitTorrent クライアントがダウンロードプロセス中にエラーチェックを行うため、ダウンロード完了後に別途 md5sum チェックを行う必要がないという利点もあります。すでにチェックは完了しています!

MX Linux Torrent Team は、公式リリースから 24 時間以内に archive.org に登録された最新の MX Linux ISO イメージ（オリジナルリリースのみ）の BitTorrent 群を管理しています。トレントへのリンクは[ダウンロードページ](#)にあります。

- ダウンロードページに行き、あなたのアーキテクチャに合った Trrent リンクをクリックしてください。ブラウザが Trrent であることを認識し、それをどのように処理するか尋ねてくるはずです。そうでない場合は、ご希望のアーキテクチャの Trrent を左クリックしてページを表示し、右クリックして保存します。ダウンロードした Trrent をクリックすると、Trrent クライアント（デフォルトでは Transmission）が起動し、リストに Trrent が表示されます。トレントをハイライトして [開始] をクリックすると、ダウンロードプロセスが開始します。ISO イメージをすでにダウンロードしている場合は、ダウンロードした Trrent と同じフォルダにあることを確認してください。

2.2.2 ダウンロードした ISO イメージの検証

ISO イメージをダウンロードしたら、次のステップはそれを検証することです。いくつかの方法があります。

md5sum

各 ISO イメージには、一致する md5sum ファイルが添付されています。ダウンロードしたファイルの md5sum を公式のものと照合してください。ダウンロードした ISO イメージが本物であれば、その md5sum は公式の md5sum と同じになります。以下の手順で、どの OS プラットフォームでもダウンロードした ISO イメージの完全性を確認できます。

- Windows
ユーザーは、[Rufus](#) ブータブル USB メーカーで最も簡単にチェックできます。また、[WinMD5FREE](#) というツールも無料でダウンロードして使用できます。
- Linux
MX Linux の場合、ISO と md5sum ファイルをダウンロードしたフォルダに移動します。 md5sum ファイルを右クリックし、[Check data integrity] を選択します。ダイアログボックスが表示されます：数字が同じなら "OK" と表示されます。ISO を右クリック > md5sum を計算し、別のソースと比較することもできます。

このオプションが使えない場合は、ISO をダウンロードした場所で端末を開き（Linux のファイルマネージャーには通常、「ここで端末を開く（Open Terminal Here）」オプションがあります）、次のように入力します：

```
md5sum filename.iso
```

filename は必ず実際のファイル名に置き換えてください（最初の数文字を入力し、Tab キーを押すと自動的に補完入力されます）。この計算で得られた数値を、公式サイトからダウンロードした md5sum ファイルと比較してください。両者が同一であれば、あなたのコピーは公式リリースと同一です。

- MacOS

Mac ユーザーは、端末を開き、ISO ファイルと md5sum ファイルのあるディレクトリに移動する必要があります。そして、以下のコマンドを実行します：

```
md5 -c filename.md5sum
```

filename は必ず実際のファイル名に置き換えてください。

sha256sum

[sha256](#) と [sha512](#) により セキュリティが強化されています。ファイルをダウンロードして ISO の完全性を確認してください。

- Windows: 方法はバージョンによって異なります。Windows <バージョン> check sha256 sum "でウェブ検索してください。
- Linux: 上記の md5sum の指示に従って、以下のように置き換えます。
sha256sum または **sha512sum** を md5sum に置き替えます。
- MacOS: 端末を開いて、ISO ファイルと sha256 ファイルのあるディレクトリに移動し、以下のコマンドを実行します：

```
shasum -a 256 /path/to/file
```

GPG 署名

MX Linux の ISO ファイルは、MX Linux の開発者によって署名されています。このセキュリティ方法により、ユーザーは ISO が開発者の公式 ISO イメージであることを確信することができます。このセキュリティチェックを実行する方法の詳細については、[MX /antiX Technical Wiki](#) をご覧ください。

2.2.3 Live メディアの作成

DVD

いくつかの重要なガイドラインに従う限り、ISO を DVD に書き込むのは簡単です。

- イメージをデータファイルのように空の CD/DVD に焼かないでください！ ISO イメージはフォーマットされた OS の起動可能なイメージです。CD/DVD 作成プログラムのメニューから、ディスクイメージの書き込みまたは ISO の書き込みを選択する必要があります。ファイルリストヘドラング&ドロップして、普通のファイルとして焼くだけでは、起動可能な Live メディアは作れません。
- 容量 4.7GB の書き込みが可能な、品質の良い DVD-R または DVD+R をご使用ください。

USB

ほとんどのシステムで動作するブート可能な USB サムドライブ (USB メモリ) を簡単に作成できます。MX Linux には、このタスクのためのツール **MX Live USB Maker** (セクション 3.2 を参照) が含まれています。

- Windows で USB サムドライブを作成したい場合は、ブートローダーをサポートする Rufus か、最近のバージョンの Unetbootin を使用することをお勧めします。
- Linux をお使いの場合は、[64 ビット版 Appimage](#) として live-usb-maker-qt を提供しています。
- USB メモリが起動しても *gfxboot.c32: not a COM32R image* というエラーメッセージが表示される場合でも、次の行のプロンプトで「live」と入力すれば起動できるはずです。USB メモリを再フォーマットし、ISO イメージをリフレッシュすればエラーは解消されるはずです。
- もしグラフィカルな USB 作成ツールが失敗した場合は、MX Live USB Maker のオプションに追加されたコマンド "dd" を使用することができます。
 - 警告: dd コマンドは保存先ドライブのデータを完全に上書きしてしまうので、保存先 USB メモリの保存先が正しいかどうか注意してください。
 - USB サムドライブの正しいデバイス名／文字を確認するには、端末を開き、*lsblk* と入力して Enter キーを押します。
システムに接続されているすべてのデバイスのリストが表示されます。リストにあるストレージサイズによって、USB サムドライブを特定できるはずです。
- 詳しくは [the MX/antiX Wiki](#) をご覧ください。

```
$ lsblk
NAME   MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sda      8:0     0 111.8G  0 disk 
└─sda1   8:1     0  20.5G  0 part /
└─sda2   8:2     0  91.3G  0 part /home
sdb      8:16    0 931.5G  0 disk 
└─sdb1   8:17    0   10.8G  0 part [SWAP]
└─sdb2   8:18    0  920.8G 0 part /media/data
```

図 2-3: *lsblk* コマンドの典型的な出力（それぞれ 2 つのパーティションを持つ 2 つのハードディスクを表示）

2.3 プリインストール

2.3.1 Windows からやって来たとき

Microsoft Windows® の代替として MX Linux をインストールする場合、現在 Windows に保存されているファイルやその他のデータを統合し、バックアップしておくことをお勧めします。デュアルブートを計画している場合でも、インストール中に予期せぬ問題が発生した場合に備えて、これらのデータのバックアップを作成しておく必要があります。

ファイルのバックアップ

オフィス文書、写真、ビデオ、音楽など、すべてのファイルを検索します:

- 通常、これらのほとんどは「マイドキュメント」フォルダにあります。

- Windows のアプリケーションメニューからさまざまな種類のファイルを検索し、すべて見つけて保存したことを確認してください。
- Windows で作成した文書を開くことができるアプリケーション (LibreOffice など) を使うために、MX Linux で再利用なフォントをバックアップするユーザーもいます。
- そのようなファイルをすべて見つけたら、CD や DVD に焼くか、USB メモリなどの外部デバイスにコピーしてください。

電子メール、カレンダー、連絡先データのバックアップ

使用しているメールやカレンダープログラムによっては、メールやカレンダーのデータが分かりやすい場所や分かりやすいファイル名で保存されていない場合があります。ほとんどのメールやスケジュールアプリケーション (Microsoft Outlook ® など) は、このデータを 1 つまたは複数のファイル形式でエクスポートできます。データをエクスポートする方法については、アプリケーションのヘルプ文書を参照してください。

- 電子メールのデータ:ほとんどのメールソフトがこの機能をサポートしているため、最も安全なメール形式はプレーンテキストです。すべてのファイル属性が維持されるように、必ず **ファイルを zip 圧縮してください。** Outlook Express を使用している場合、メールは.dbx または.mbx ファイルに保存されており、MX Linux の Thunderbird (インストールされている場合) にインポートすることができます。Windows の検索機能を使ってこのファイルを探し、バックアップにコピーしてください。Outlook のメールは、MX Linux で使用するためにエクスポートする前に、まず Outlook Express にインポートする必要があります。
- カレンダーのデータ: MX Linux で使用する場合は、カレンダーのデータを iCalendar または vCalendar 形式にエクスポートします。
- 連絡先データ: 最も一般的なフォーマットは CSV (カンマ区切り値) または vCard です。

アカウントとパスワード

通常、バックアップ可能な可読ファイルに保存されることはありませんが、コンピュータに保存されている可能性のあるさまざまなアカウント情報をメモしておくことは重要です。ウェブサイトや ISP などのサービスの自動ログインデータは、何度も入力する必要があるため、これらのサービスに再度アクセスするために必要な情報をディスク以外に保存しておくようにしましょう。例えば、以下のものがあります:

- ISP のログイン情報: インターネットサービスプロバイダのユーザー名とパスワード、ダイヤルアップまたは ISDN を利用している場合は接続用の電話番号が少なくとも必要です。他の詳細には、ダイヤル発信番号、ダイヤルタイプ (パルスまたはトーン)、認証タイプ (ダイヤルアップの場合)、IP アドレスとサブネットマスク、DNS サーバー、ゲートウェイ IP アドレス、DHCP サーバー、VPI/VCI、MTU、カプセル化タイプ、DHCP 設定 (各種ブロードバンドの場合) などが含まれる場合があります。何が必要かわからない場合は、ISP に相談してください。
- ワイヤレスネットワーク: パスキーまたはパスフレーズとネットワーク名が必要です。
- ウェブパスワード: さまざまなウェブフォーラム、オンラインショップ、その他の安全なサイトのパスワードが必要です。
- 電子メールアカウントの詳細: ユーザー名とパスワード、メールサーバーのアドレスまたは URL が必要です。また、認証タイプも必要です。これらの情報は、メールクライアントのアカウント設定ダイアログから取得できるはずです。

- ・ インスタントメッセージ: IM アカウントのユーザー名とパスワード、バディリスト、必要に応じてサーバー接続情報。
- ・ その他: VPN 接続（職場への接続など）、プロキシサーバ、その他設定済みのネットワークサービスがある場合、再設定が必要な場合に必要な情報を確認しておくこと。

ブラウザのお気に入り

ウェブブラウザのお気に入り（ブックマーク）はバックアップ中に見落とされがちで、通常はわかりやすい場所に保存されていません。ほとんどのブラウザには、ブックマークをファイルにエクスポートするユーティリティが含まれています。使用するブラウザのブックマークマネージャで最新の方法を確認してください。

ソフトウェアライセンス

Windows 用のプロプライエタリなプログラムの多くは、ライセンスキーや CD キーがないとインストールできない。Windows を永久に使わないというのでなければ、ライセンスキーは必ず持っておきましょう。Windows を再インストールすることになった場合（あるいはデュアルブートのセットアップがうまくいかなかった場合）、キーがなければこれらのプログラムを再インストールすることはできません。

もし製品に付属している紙のライセンスが見つからない場合は、Windows レジストリで探すか、[ProduKey](#) のようなキーファインダを使用してください。その他の方法がうまくいかない場合は、コンピュータの製造元に問い合わせてみてください。

Windows プログラムの実行

Windows のプログラムは Linux OS の中では動かないで、MX Linux ユーザーはネイティブの同等品を探すことをお勧めします（セクション 4 参照）。ユーザーにとって重要なアプリケーションは、Wine（セクション 6.1 参照）で実行できるかもしれません。

2.3.2 Apple Intel コンピュータ

Intel チップ搭載の Apple コンピュータへの MX Linux のインストールには問題があります。難易度は、関係するハードウェアによって異なります。このようなインストールに興味のあるユーザは、Debian の資料やフォーラムで最近の動向を検索し、参考にすることをお勧めします。多くの Apple ユーザが MX Linux のインストールに成功していますので、MX Linux フォーラムを検索したり、質問を投稿したりすると良い結果が得られるでしょう。

リンク

[Apple コンピュータへの Debian のインストール](#)
[Debian フォーラム](#)

2.3.3 ハードドライブに関する FAQ

MX Linux はどこにインストールすればいいですか？

インストールを始める前に、MX Linux をインストールする場所を決める必要があります。

- ・ ハードドライブ全体
- ・ ハードドライブ上の既存のパーティション

- ハードディスクに新しいパーティションを作る

インストール中に最初の 2 つのオプションのいずれかを選択するだけです。3 番目のオプションは、新しいパーティションを作成する必要があります。インストール中に行うこともできますが、インストールを開始する前に行うことをお勧めします。MX Linux では通常、**GParted** (Xfce) または **Partition Manager** (KDE) を使用して、グラフィカルにパーティションを作成・管理します。

伝統的な Linux のインストール構成では、複数のパーティションがある場合、下図のように root、home、swap にそれぞれ 1 つずつパーティションがあります。Linux を初めて使う場合は、この構成から始めるとよいでしょう。UEFI 対応マシンでは、FAT32 フォーマットの [EFI システムパーティション \(ESP\)](#) も必要でしょう。その他のパーティション配置も可能で、例えば、経験豊富なユーザーの中には、root パーティションと home パーティションを組み合わせ、データ用に別のパーティションを用意する人もいます。




図 2-2: *GParted* で 3 つのパーティション (sda1)、(sda2)、スワップ (sda3) を表示。ドライブのサイズはユーザーの好みです(最小要件についてはセクション 1.3 を参照)。

もっと見る: [GParted マニュアル](#)

[Gparted で新しいパーティションを作成](#)

[マルチブートシステムのパーティション](#)

パーティションの編集方法は?

ディスクマネージャと呼ばれる非常に便利なツールは、マシン上のすべてのパーティション（スワップを除く）をグラフィカルに表示し、ディスクパーティションのマウント、アンマウント、いくつかのプロパティの編集を迅速かつ簡単に行うためのシンプルなインターフェイスを提供します。変更は自動的かつ即座に /etc/fstab に書き込まれ、次回の起動のために保存されます。

ヘルプ: [ディスクマネージャ](#)

私の Windows インストールにある他のパーティションは何ですか？

最近の Windows 搭載の家庭用コンピュータは、OS のインストールされたパーティション以外に、診断用パーティションと復元用パーティションも一緒に販売されています。もし GParted で見覚えのない複数のパーティションが表示されたら、それはおそらくそれらのパーティションであり、放っておくべきです。

ホームパーティションは別に作るべきですか？

インストーラが / (root) 内に /home ディレクトリを作成するので、ホームパーティションを別に作成する必要はありません。しかし、独立したパーティションがあると、アップグレードが簡単になり、ユーザーが大量の写真や音楽、ビデオでドライブをいっぱいにすることで発生する問題から保護されます。

/ (root) はどれくらいの大きさにするべきですか？

- （Linux の場合、フォワードスラッシュ「/」は root パーティションを示します。）インストールされる基本サイズは 5 GB 弱なので、基本的な機能を使えるように 6 GB 以上を推奨します。
- この最小サイズでは、多くのプログラムをインストールできず、アップグレードや VirtualBox の実行などが困難になる可能性があります。そのため、通常の使用で推奨されるサイズは 20 GB です。
- ホームパーティション（/home）がルートディレクトリ（/）内にあり、大きなファイルをたくさん保存している場合、より大きなルートパーティションが必要になります。
- 大容量ゲーム（Wesnoth など）をプレイするゲーマーは、データ、画像、サウンドファイル用に通常より大きな root パーティションが必要になることに注意する必要があります。

swap パーティションを作成する必要がありますか？

swap は、仮想メモリに使用されるディスク領域です。Windows が仮想メモリに使用する「ページ」ファイルに似ています。インストーラが swap パーティションを作成します（セクション 2.5.1 参照）。もしシステムをハイバネート（サスペンドだけでなく）するつもりなら、swap フィールドのサイズに関する推奨事項を以下に示します：

- メモリ（RAM）の容量が 1 GB 未満の場合、swap フィールドは少なくともメモリの容量と等しく、システムで使用可能なハードディスクの容量に応じて最大でメモリの 2 倍が必要です。
- 大容量のメモリを搭載したシステムの場合、swap フィールドは少なくともメモリサイズと同じにする必要があります。
- 技術的には、Linux システムは swap なしでも動作しますが、大容量のメモリを搭載したシステムでも、性能上の問題が発生する場合があります。

sda のような名前は何を意味するのですか？

インストールを始める前に、Linux OS がハードドライブとそのパーティションをどのように扱うかを理解しておくことが重要です。

- ドライブ名。** ハードドライブの各パーティションにドライブ文字を割り当てる Windows とは異なり、Linux ではシステム上の各ハードドライブやその他のストレージデバイスに短いデバイス名を割り当てます。デバイス名は、SATA ドライブの場合は sd + 1 文字（例："sda"、"sdb" など）で始まり、NVMe ドライブの場合は nvme0n + 1 数字（例：

"nvme0n1"、"nvme0n2"など)で始まります。また、より高度なドライブの命名方法もあります。たとえば、最も一般的なものは UUID (Universally Unique Identifier) で、機器の追加や取り外しによって変更されることのない永続的な名前を割り当てるために使用されます。

- **パーティション名.** 各ドライブ内では、各パーティションはデバイス名に付加された番号で呼ばれます。したがって、SATA の場合、**sda1** は最初のハードドライブの最初のパーティションとなり、**sdb3** は 2 番目のドライブの 3 番目のパーティションとなります。NVMe の場合、**nvme0n1p1** は最初のハードドライブ上の第 1 パーティション、**nvme0n2p3** は第 2 ドライブ上の第 3 パーティションとなります。
- **拡張パーティション.** PC のハードディスクはもともと 4 つのパーティションしか許されていません。プライマリパーティションの 1 つを拡張パーティションにし、それを 5 以降の番号の論理パーティション（上限 15）に分割することで数を増やすことができます。Linux はプライマリパーティションにも論理パーティションにもインストールできます。

2.4 第一印象

Live メディアへのログイン

ログアウトや再ログイン、新しいパッケージのインストールなどに備えて、ここにユーザー名とパスワードを記載しておきます:

- 一般ユーザー（通常のユーザー）
 - 名前: demo
 - パスワード: demo
- スーパーユーザー（管理者）
 - 名前: root
 - パスワード: root

2.4.1 Live メディアを起動する

Live CD/DVD

CD/DVD をトレイに入れて再起動するだけです。

Live USB メモリ

USB メモリを使用してコンピュータを正しく起動させるには、いくつかの手順を踏む必要があります。

- USB メモリで起動するために、多くのコンピュータでは起動中に特定のキーを押してデバイスを選択することができます。デバイスの起動メニューの代表的なキーは、Esc や機能

キーのうちの 1 つ、あるいは Return や Shift などです。再起動時に表示される最初の画面をよく見て、正しいキーを見つけてください。

- あるいは、BIOS に入ってブートデバイスの順番を変更する必要があるかもしれません:
 - コンピュータを起動し、最初に必要なキー (F2、F10、Esc など) を押して BIOS に入ります。
 - Boot タブキーをクリック (または矢印キーで移動) します。
 - USB デバイス (通常は USB HDD) を識別してハイライトし、リストの一番上に移動させます (システムがそのように設定されている場合は、Enter キーを押します)。保存して終了します。
 - BIOS の変更について不明な点や不安な点がある場合は、[MX フォーラム](#)でサポートを求めてください。
- BIOS で USB をサポートしていない古いコンピュータでは、USB ドライバをロードしてメニューを表示する [Plop Linux LiveCD](#) を使うことができます。詳しくはウェブサイトをご覧ください。
- システムが起動プロセス中に USB メモリを認識するように設定したら、USB メモリを接続してマシンを再起動するだけです。

UEFI



UEFI ブートの問題と確認すべきいくつかの設定！

マシンにすでに Windows 8 以降がインストールされている場合は、[\(U\)EFI](#) とセキュアブートの存在に対処するための特別な手順を踏む必要があります。ほとんどのユーザーは、マシンの起動時に BIOS に入ってセキュアブートをオフにするよう促されます。残念ながら、その後の正確な手順はメーカーによって異なります:

UEFI 仕様が MBR パーティションテーブルを完全にサポートすることを要求しているにもかかわらず UEFI ファームウェアの実装の中にはブートディスクのパーティションテーブルの種類によって BIOS ベースの CSM ブートに即座に切り替えてしまうものがあり MBR パーティションのディスク上の EFI システムパーティションから UEFI ブートを実行することを事实上妨げています。 (*Wikipedia, "Unified Extensible Firmware Interface", 10/12/19 取得*)

UEFI のブートとインストールは 32 ビットと 64 ビットのマシン、そして 32 ビット UEFI の 64 ビットマシンでサポートされています。とはいえ、32-bit UEFI の実装には問題があります。トラブルシューティングについては、[MX /antiX Wiki](#) を参照するか、[MX フォーラム](#)で質問してください。

ブラック・スクリーン

時折、何も表示されていない黒い画面が表示され、その隅にカーソルが点滅していることがあります。これは、Linux で使用されるウインドウシステムである X の起動に失敗していることを表し、使用されているグラフィックドライバの問題が原因であることがほとんどです。**解決策:** 再起動し、メニューから Safe Video または Failsafe ブートオプションを選択してください。セクション 3.3.2 を参照してください。

2.4.2 標準的な開始画面



図 2-3: x64 ISO イメージの Live メディアのブート画面。

Live メディアが起動すると、上図のような画面が表示されます。インストールされたシステムの画面はかなり違って見えます。カスタムの項目はメインメニューにも表示されることがあります。

メインメニューの項目

表 1: Live ブートのメニュー項目

項目	コメント
MX-XX.XX (<リリースされた日>)	このエントリーはデフォルトで選択されており、ほとんどのユーザーが Live システムを起動する標準的な方法です。 Return キーを押すだけでシステムが起動します。
ハードディスクからの起動	システムのハードディスクに現在インストールされているものをすべて起動します。
メモリテスト	メモリ (RAM) をチェックするテストを実行します。このテストがパスした場合、ハードウェアに問題があるか、メモリに問題がある可能性があります。

最下段には縦にいくつかの項目が表示され、その下には横一列に以下のオプションが並んでいます。
その画面で F1 を押すと詳細が表示されます。

オプション

- F2 Language.** 言語。ブートローダーと MX システムの言語を設定します。これはインストール時に自動的にハードドライブに転送されます。
- F3 Time Zone.** タイムゾーン。システムのタイムゾーンを設定します。これはインストール時に自動的にハードドライブに転送されます。
- F4 Options.** オプション。ライブシステムのチェックと起動のためのオプション。これらのオプションのほとんどは、インストール時にハードドライブに転送されません。

- **F5 Persist.** パーシスト。マシンのシャットダウン時に LiveUSB への変更を保持するためのオプション。
- **F6 Safe/Failsafe Video Options.** セーフ / フェイルセーフビデオオプション。デフォルトで X で起動しないマシン用のオプション。
- **F7 Console.** コンソール。仮想端末の解像度を設定します。カーネルモード設定と競合する可能性があります。コマンドラインインストールでブートする場合や、初期ブートプロセスをデバッグする場合に便利です。このオプションはインストール時に引き継がれます。

もっと見る: [Linux スタートアッププロセス](#), [MX/antiX Wiki](#)

2.4.3 UEFI の開始画面




図 2-4: UEFI が検出されたときの x64 (MX-21 以上) の Live メディアのブート画面。

ユーザーが UEFI ブート用に設定されたコンピュータを使っている場合 ([MX/antiX Wiki](#) を参照) 、UEFI の Live ブート開始画面が異なる選択肢で代わりに表示されます。

- メニューは、機能キーメニューの代わりにブートオプションの設定に使用されます。
- 一番上のオプションは、選択したオプションを有効にして OS を起動します。
- 詳細オプションは、パーシステンスや、レガシーブートの機能キーメニューにあるその他の項目を設定します。
- 「言語」 - 「キーボード」 - 「タイムゾーン」は、これらのオプションを設定します。




図 2-5: Live メディア（左）とインストールオプションの画面例。

ブートオプションを持続させたい場合は、必ずセーブオプションを選択してください。

2.4.4 口グイン画面




図 2-6: 左 : Xfce ログイン画面、セッションボタンは中央上部。右 KDE: ログイン画面。

自動ログインを選択しない限り、インストールされたブートプロセスはログイン画面で終了します。ライブセッションでは背景画像のみが表示されますが、デスクトップからログアウトすると完全な画面が表示されます（画面のレイアウトは MX のバージョンによって異なります）。小さな画面では、画像がズームされて表示されることがあります。これは MX Linux で使用されているディスプレイメーニュの特性です。

トップバーの右端に 3 つの小さなアイコンが見えます。右から左の順に以下のとおりです:

- 端にある**電源ボタン**には、サスペンド、再起動、シャットダウンのオプションがあります。
- **言語ボタン**は、ユーザーがログイン画面に適切なキーボードを選択できるようにします。
- **視覚支援ボタン**は、一部のユーザーの特別なニーズに対応します。

真ん中にはセッションボタンがあり、使用するデスクトップマネージャを選択できます: デフォルトの Xsession、Xfce Session、その他インストールされているものを選択できます (セクション 6.3)。Fluxbox はもはやデフォルトでは含まれていませんが、MX パッケージインストーラでインストールできます。

起動時に毎回ログインすることを避けたい場合 (セキュリティ上の問題がある場合はお勧めしません)、MX ユーザーマネージャの「オプション」タブで「自動ログイン」に変更することができます。

MX KDE/Plasma バージョンには、セッションチューナー、オンスクリーン・キーボード、電源/シャットダウン/再起動の機能を含む、異なるログイン画面が同梱されています。

2.4.5 異なるデスクトップ

MX-Xfce




図 2-7: デフォルトの Xfce デスクトップ。

MX-KDE




図 2-8: デフォルトの KDE/Plasma デスクトップ。

デスクトップは [Xfce](#) または KDE/Plasma で作成・管理され、それぞれの外観と配置は MX Linux 用に大きく変更されています。最初に見たときの 2 つの特徴に注意してください: パネルとウェルカム画面です。

パネル

MX Linux のデフォルトのデスクトップには、画面に縦長のパネルが 1 つあります。パネルの向きは **MX ツール > MX Tweak** で簡単に変更できます。一般的なパネルの機能は以下のとおりです:

- 電源ボタン: ログアウト、再起動、シャットダウン、サスペンドのダイアログボックスが開きます (Xfce)
- LCD フォーマットの時計: クリックするとカレンダーを表示します (xfce)
- タスクスイッチャ/ウィンドウボタン: 開いているアプリケーションが表示されるエリア
- Firefox: Firefox ブラウザ
- ファイルマネージャ (Thunar)
- 通知エリア
 - アップデートマネージャ
 - クリップボードマネージャ
 - ネットワークマネージャ
 - 音量調節
 - 電源管理
 - USB の取り出し
- ページヤ: 利用可能なワークスペースを表示 (デフォルトは 2 つ、右クリックで変更可)
- アプリケーションメニュー (Xfce では "Whisker")
- 他のアプリケーションが、実行中にパネルや通知領域にアイコンを挿入することができます。

パネルのプロパティを変更するには、セクション 3.8 を参照してください。

ウェルカム画面




図 2-9: MX linux (インストール済み) のウェルカム画面とバージョン情報画面。

When the user boots up for the first time, a Welcome screen appears in the center of the screen with two tabs: “Welcome” offers quick orientation and help links (Figure 2-7) while “About”

displays a digest of information about the OS, the running system, etc. When running a live session, the passwords for demo and root users will be shown at the bottom. Once closed, running live or installed, it can be displayed again using the menu or MX Tools. ユーザーが初めて起動すると、画面中央に2つのタブを持つ「ようこそ」画面が表示される: 「Welcome」はクイックオリエンテーションとヘルプリンクを提供し(図2-7)、「About」はOSや実行中のシステムなどに関する情報のダイジェストを表示する。ライブセッションを実行している場合、デモユーザーとルートユーザーのパスワードが下部に表示されます。一度閉じたり、ライブを実行したり、インストールしたりすると、メニューや MX Tools を使って再度表示することができます。

It is very important for new users to work carefully through the buttons, as it will save much confusion and effort in the future use of MX Linux. If time is limited, it is recommended that you scan through the FAQ document linked on the Desktop, where the most common questions are answered. 新規ユーザーにとって、ボタンを注意深く操作することは非常に重要である。時間が限られている場合は、次のことをお勧めします。デスクトップにリンクされているFAQ文書に目を通し、最も一般的な質問に答えてください。

ヒントとコツ




Figure 2-10: Settings is your one-stop location to make changes. Contents vary. 図 2-10: 「Settings (設定)」はワンストップで変更できる場所。内容は様々です。

Some handy things to know at the beginning: 最初に知っておくと便利なことがいくつかある:

- If you are having problems with sound, network, etc., see Configuration (Section 3). サウンドやネットワークなどに問題がある場合は、コンフィギュレーション(セクション3)
- を参照してください。
- Adjust sound general loudness by scrolling with the cursor over the speaker icon, or by right-clicking speaker icon > Open Mixer. スピーカーのアイコンの上にカーソルを置いてスクロールするか、スピーカーのアイコンを右クリックして > ミキサーを開く。
- Set the system to your particular keyboard layout by clicking Application Menu > Settings > Keyboard, Layout tab, and selecting the model with the pull-down menu. This is also where you can add other language keyboards. アプリケーションメニュー > 設

定 > キーボード > レイアウトタブをクリックし、プルダウンメニューでモデルを選択して、システムを特定のキーボードレイアウトに設定します。ここで他の言語のキーボードを追加することもできます。

- Adjust preferences for mouse or touchpad by clicking **Application Menu > Settings > Mouse and Touchpad**. アプリケーションメニュー] > [設定] > [マウスとタッチパッド] をクリックして、マウスまたはタッチパッドの環境設定を調整します。
- Trash can be easily managed in the file manager, where you will see its icon in the left pane. Right-click to empty. It can also be added to the Desktop or panel. It is important to realize that using delete, whether by highlighting and hitting the delete button or via a context menu entry, removes the item forever and it will not be recoverable. ゴミ箱はファイルマネージャーで簡単に管理でき、左ペインにアイコンが表示されます。右クリックで空にできます。デスクトップやパネルに追加することもできます。削除を使うと、ハイライトして削除ボタンを押すか、コンテキストメニューから削除するかにかかわらず、そのアイテムは永久に削除され、復元することはできません。
- Keep your system current by watching for the indicator (outlined box) of available updates on the MX Updater to turn green. See Section 3.2 for details. MX アップデータの利用可能なアップデートのインジケータ(輪郭のあるボックス)が緑色になるのを確認し、システムを最新の状態に保ってください。詳細については、セクション 3.2 を参照してください。
- Handy key combinations (managed in All Settings > Keyboard > Application Shortcuts). 便利なキーの組み合わせ(すべての設定 > キーボード > アプリケーションのショートカットで管理)。

Table 2: Handy key combinations 表 2 :便利なキーの組み合わせ

キーストローク	Action アクション
F4	Drops a terminal down from top of screen 画面上部から端末を降ろす
Windows キー	Brings up the Application menu アプリケーションメニューを表示する
Ctrl-Alt-Esc	Changes the cursor into a white x to kill any program カーソルを白い×印に変え、プログラムを終了させる。
Ctrl-Alt-Bksp	Closes the session (without saving!) and returns you to the login screen セッションを閉じ(保存はしない!)、ログイン画面に戻る。
Ctrl-Alt-Del	Locks the desktop on Xfce; logout on KDE/Plasma Xfce ではデスクトップをロックし、KDE/Plasma ではログアウトします。
Ctrl-Alt-F1	Drops you out of your X session to a command line; use Ctrl-Alt-F7 to return X セッションからコマンドラインにドロップします。
Alt-F1	Opens this MX Linux Users Manual (Xfce only, menu on KDE/Plasma) の MX Linux ユーザーズマニュアルを開きます (Xfce のみ、KDE/Plasma ではメニュー)
Alt-F2	Brings up a dialog box to run an application アプリケーションを実行するためのダイアログボックスを表示します。
Alt-F3	Opens the Application Finder, which also allows some editing of menu entries (Xfce only) アプリケーションファインダーを開き、メニュー エントリーの編集を行うことができます (Xfce のみ)
Alt-F4	Closes an application in focus; over the desktop, brings up the exit dialog デスクトップ上で、終了ダイアログを表示する。

PrtScr	Opens the screenshot utility for screen captures スクリーンキャプチャ用のスクリーンショットユーティリティを開く
--------	--

アプリケーション

アプリケーションはさまざまな方法で開始できます。




Figure 2-11:

LEFT: Xfce Whisker menu (contents vary). RIGHT: KDE/Plasma menu. 図 2-11: 左: Xfce Whisker メニュー(内容は異なる)。右: KDE/Plasma メニュー。

- Click the Application menu icon, in lower-left corner. 左下のアプリケーションメニュー アイコンをクリックします。
 - It opens to Favorites category, and you can hover mouse over other categories on right side to see contents in the left pane. お気に入り」カテゴリーが開き、右側の他のカテゴリーにマウスカーソルを合わせると、左側のペインに内容が表示される。
 - At the top is a powerful incremental search box: just type in a few letters to find any application without needing to know its category. 上部には強力なインクリメンタル検索ボックスがあり、数文字を入力するだけで、カテゴリーを知らなくてもどんなアプリケーションでも見つけることができる。
- Right-click the desktop > Applications. デスクトップを右クリック > アプリケーション。
- If you know the name of the application, you can use Application Finder, started easily in one of two ways. アプリケーションの名前がわかっていれば、アプリケーション・ファインダーを使うことができる。
 - Right-click the desktop > Run command ... デスクトップを右クリック > コマンドを実行 ...
 - Alt-F2
 - Alt-F3 (Xfce) brings up an advanced version that lets you check commands, locations etc. Alt-F3 (Xfce)で、コマンドや場所などを確認できる詳細バージョンが表示されます。
- On KDE/Plasma desktop, just start typing KDE/Plasma デスクトップ上で、次のように入力します。
- Use a keystroke you have defined to open a favorite application. お気に入りのアプリケーションを開くには、定義したキーストロークを使用します。

- Xfce - Click **Application Menu** > **Settings**, then Keyboard, Application shortcuts tab. Xfce - [Application Menu] > [Settings] をクリックし、[Keyboard] の [Application shortcuts] タブをクリックします。
- KDE/Plasma – Global Shortcuts in menu KDE/Plasma - メニューのグローバルショートカット




Figure 2-12: Application Finder identifying application. 図 2-12 : アプリケーションを特定するアプリケーション・ファインダー。

Other その他

System information システム情報

- Click **Application Menu** > **Quick System Info** that will put the results of the command `inxi -Fxz` into your clipboard ready to paste in Forum posts, text files, etc. アプリケーションメニュー>クイックシステム情報をクリックすると、コマンドの結果が表示されます。`inxi -Fxz` を クリップボードにコピーして、フォーラムの投稿やテキストファイルなどに貼り付けることができます。
- KDE/Plasma - Click **Application Menu** > **System** > **Infocenter** for a nice graphic display KDE/Plasma - アプリケーションメニュー > システム > インフォセンターをクリックすると、素敵なグラフィックが表示されます。

Video and audio ビデオとオーディオ

- For basic monitor settings, click **Application Menu** > **Settings** > **Display** 基本的なモニター設定は、アプリケーションメニュー > 設定 > ディスプレイの順にクリックします。
- Sound adjustment is done through **Application Menu** > **Multimedia** > **PulseAudio Volume Control** (or right-click Volume manager icon) サウンドの調整は、アプリケーションメニュー > マルチメディア > PulseAudio ボリュームコントロール(またはボリュームマネージャーアイコンを右クリック)で行います。

NOTE: for troubleshooting areas such as display, sound or internet, consult Section 3: Configuration. 注:ディスプレイ、サウンド、インターネットなどのトラブルシューティングについては、セクション3「設定」を参照してください。

Links リンク

- [Xfce 関連文書](#)
- [Xfce FAQs](#)
- [KDE](#)

2.4.7 Exiting 終了する

When you open Application menu, you will see by default four command buttons in the upper-right corner (change what shows with a right click on the menu icon > Properties, Commands tab). From left to right: アプリケーションメニューを開くと、デフォルトでは右上に4つのコマンドボタンが表示されます(メニューアイコンを右クリック > プロパティ > コマンドタブで表示内容を変更できます)。左から :

- All Settings (All Settings) すべての設定(すべての設定)
- Lock Screen 画面のロック
- Switch Users ユーザーの切り替え
- Log Out ログアウト





Figure 2-13: command buttons 図 2-13: コマンドボタン

上: **Xfce**

右: **KDE/Plasma**

It is important to exit MX Linux correctly when you have finished your session so that the system can be brought down in a secure way. All running programs are first notified that the system is going down, giving them the time to save any file being edited, exit from mail and news programs, etc.

If you just turn the power off, you risk the possibilities of damaging the operating system. システムを安全な方法で停止できるように、セッションが終了したら MX Linux を正しく終了することが重要です。実行中のすべてのプログラムは、最初にシステムがダウンすることを通知されます。編集中のファイルを保存する時間、メールやニュース・プログラムから終了する時間など。ただ電源を切るだけでは、オペレーティング・システムにダメージを与える可能性がある。



Similar options to the command buttons are available in the KDE/Plasma LEAVE menu. コマンドボタンと似たようなオプションが KDE/Plasma の LEAVE メニューにもあります。

Permanent 永続的に

To leave a session for good, select one of the following on the Log Out dialog box: セッションを完全に終了するには、ログアウトダイアログボックスで以下のいずれかを選択します:

- **Log out.** Choosing this will terminate everything you are doing, ask you about saving open files if you have not closed the files yourself, and bring you back to the login screen with the system still running. ログアウト。これを選ぶと、今やっていることがすべて終了

し、ファイルを閉じていない場合は開いているファイルの保存について尋ねられ、システムがまだ動いている状態でログイン画面に戻ります。

- The command at the bottom of the screen, “Save session for future logins,” is checked by default. Its task is to save the state of your desktop (opened applications and their location) and restore it during the next startup. If you have had problems with your desktop function, you can uncheck this to get a fresh start; if that does not solve the problem, click All Settings > Session and Startup, Session tab, and press the Clear saved sessions button. 画面下部の「Save session for future logins(将来のログインのためにセッションを保存する)」というコマンドは、デフォルトでチェックされています。このコマンドはデスクトップの状態(開いているアプリケーションとその場所)を保存し、次回の起動時に復元します。デスクトップ機能に問題がある場合は、このチェックを外して再スタートできます。それでも問題が解決しない場合は、[すべての設定]>[セッションとスタートアップ]の[セッション]タブをクリックし、[保存されたセッションを消去]ボタンを押します。
- **Restart or Shut Down.** Self-explanatory options that alter the system state itself. Also available using the icon in the upper right corner of the top bar on the login screen. 再起動またはシャットダウン。システムの状態そのものを変更する説明不要のオプション。ログイン画面のトップバーの右上にあるアイコンからも利用できる。

TIP: In the event of a problem, **Ctrl-Alt-Bksp** will kill your session and return you to the login screen, but any open programs and processes will not be saved. ヒント:問題が発生した場合、Ctrl-Alt-Bksp を押すとセッションが終了し、ログイン画面に戻りますが、開いているプログラムやプロセスは保存されません。

Temporary 一時的に

You can temporarily leave your session in one of the following ways: 以下のいずれかの方法で、一時的にセッションを離れるすることができます:

- **Lock screen.** This option is easily available from an icon in the top right corner of the Application Menu. It protects your Desktop from unauthorized access while you are away by requiring your user password to return to the session. ロック画面。このオプションは、アプリケーションメニューの右上隅にあるアイコンから簡単に利用できます。セッションに戻る際にユーザー・パスワードを要求することで、外出中の不正アクセスからデスクトップを保護します。
- **Start a parallel session as a different user.** This is available from the Switch User command button in the top right corner of the Application Menu. You choose this to leave your current session where it is and allows a session for a different user to be started. 別のユーザーとしてパラレルセッションを開始します。これはアプリケーションメニューの右上にある Switch User コマンドボタンから利用できます。これを選択すると、現在のセッションはそのままで、別のユーザーのセッションを開始することができます。
- **Suspend using Power Button.** This option is available from the Log Out dialog box, and places your system into a low-power state. Information on system configuration, open applications, and active files is stored in main memory (RAM), while most of the system's other components are turned off. It is very handy and generally works very well in MX Linux. Invoked by the Power Button, suspend works well for many users, though

its success varies according to the complex interaction among a system's components: kernel, display manager, video chip, etc. If you have problems, consider trying the following changes:電源ボタンを使用したサスペンド。このオプションは[ログアウト]ダイアログボックスから使用でき、システムを低電力状態にします。システム構成、開いているアプリケーション、アクティブなファイルに関する情報はメインメモリ(RAM)に保存され、システムの他のコンポーネントのほとんどはオフになります。これは非常に便利で、MX Linux では一般的に非常によく機能します。カーネル、ディスプレイ・マネージャー、ビデオ・チップなど、システムのコンポーネント間の複雑な相互作用によってその成功は異なりますが、電源ボタンによって起動されるサスペンドは、多くのユーザーにとってうまく機能します。問題がある場合は、以下の変更を試してみてください:

- Switch graphical driver, e.g., from radeon to AMDGPU (for newer GPU's), or from nouveau to the proprietary Nvidia driver. グラフィカルドライバを切り替える。例えば、radeon から AMDGPU(新しいGPU用)へ、またはヌーボーから Nvidia 専用ドライバへ。
- Adjust the settings in Application Menu > Settings > Power Manager. For instance: on the System tab, try unchecking "Lock screen when system is going for sleep." アプリケーションメニュー>設定>パワーマネージャで設定を調整します。例えば:システムタブで、"システムがスリープに入るときに画面をロックする"のチェックを外してみてください。
- Click Application Menu > Settings > Screensaver, and adjust the Display Power Management values on the Advanced tab. Application Menu(アプリケーションメニュー) > Settings(設定) > Screensaver(スクリーンセーバー)をクリックし、Advanced(詳細)タブで Display Power Management(ディスプレイ電力管理)の値を調整します。
- AGP cards: add **Option "NvAgp" "1"** to the Device section of xorg.conf. AGP カード:xorg.conf の Device セクションに Option "NvAgp" "1" を 追加。
- **Suspend** using laptop lid close. Some hardware configurations may experience trouble with this. Action on lid closing can be adjusted on the General tab of Power Manager, where "Switch off display" has proved reliable in MX users' experience. ノートパソコンの蓋を閉じてサスペンドします。ハードウェアの構成によっては、これで問題が発生する場合があります。蓋を閉じたときの動作は、パワーマネージャの[全般]タブで調整することができます。
- **Hibernation.** The hibernation option was removed from the logout box in earlier MX Linux versions because users experienced multiple problems. It can be enabled in MX Tweak, Other tab. Consult also [the MX/antiX Wiki](#).ハイバネーション。ハイバネーションオプションは、ユーザーが複数の問題を経験したため、以前の MX Linux バージョンではログアウトボックスから削除されました。MX Tweak の Other タブで有効にできます。MX/antiX Wiki も参照してください。

2.5 インストール手順

2.5.1 詳細なインストール手順



[MX Linux の基本インストール \(パーティショニングを含む\)](#)



[MX Linux の暗号化インストール \(パーティショニング付き\)](#)



[マイホームフォルダの設定](#)

まず、LiveMedium を起動し、左上のインストーラアイコンをクリックします。アイコンがない場合は、F4 をクリックし、*minstall-pkexec* (Live メディアの root パスワード: root) と入力してください。




Figure 2-14: Home screen of Installer. 図 2-14 :インストーラーのホーム画面

Comments コメント

- The right side of the Installer screen presents user choices as the installation proceeds; the left side provides clarification of the content of the right side. インストーラ画面の右側は、インストールが進むにつれてユーザーの選択肢を表示し、左側は右側の内容を明確にします。
- Keyboard Settings permits changing the keyboard for the installation process. キーボードの設定では、インストールプロセスのキーボードを変更することができます。




Figure 2-15: Installer set to Customized Install. 図 2-15 : インストーラをカスタマイズインストールに設定。

Comments コメント

- **Use disk.** If unsure which is the partition you want, use the names you see in GParted. The disk you select will be examined cursorily for reliability by SMART. If problems are detected, you will see a warning screen. You will need to decide whether to accept that risk and continue, select another disk or terminate the installation. For more information, click Application Menu > System > GSmartControl and “Perform tests” on the drive.
ディスクを使います。それが目的のパーティションかわからない場合は、GParted に表示されている名前を使用してください。選択したディスクは SMART によって信頼性がずっと調べられます。問題が検出された場合、警告画面が表示されます。そのリスクを受け入れて続行するか、別のディスクを選択するか、インストールを終了するかを決める必要があります。詳細については、アプリケーションメニュー > システム > GSmartControl をクリックし、ドライブの"Perform tests" を参照してください。




Figure 2-16: SMART warning of risk of failure 図 2-16 : SMART による故障リスクの警告

- **Regular install using entire disk.** Select this option if you plan to use the entire hard drive for MX Linux. The disk will be repartitioned and any existing data will be lost.
ディスク全体を使用する通常のインストール。ハードドライブ全体を MX Linux に使用する場合は、このオプションを選択してください。ディスクは再パーティション化され、既存のデータは失われます。
 - By default a root and swap partition will be created. A /boot partition will also be created if you choose to use encryption. デフォルトではルート/パーティションとス

マップパーティションが作成されます。暗号化を使用する場合は、/boot パーティションも作成されます。

- If you wish to have a separate home partition, you can use the slider to divide the available space between root and home partitions. ホームパーティションを分けたい場合は、スライダーでルートパーティションとホームパーティションの空き容量を分けることができます。
 - A pop-up message will ask you to confirm using the entire disk. ディスク全体の使用を確認するポップアップメッセージが表示されます。
-
- **Customize the Disk Layout:** If existing partitions are detected on disk, this option will be the default. You will be able to use the partition selection screen to use existing partitions. ディスクレイアウトをカスタマイズする:ディスク上に既存のパーティションが検出された場合、このオプションがデフォルトになります。パーティション選択画面で既存のパーティションを使用することができます。




Figure 2-17: Partition selection. 図 2-17: パーティションの選択




Figure 2-18: Right click on a disk to show template options.図 2-18 :ディスクを右クリックしてテンプレートオプションを表示する。

Comments コメント

- **Choose Partitions.** Specify the root and swap partitions you want to use. Use the **USE FOR** column to chose what you want to use a partition for. If you set up a separate partition for your home directory, specify it here, otherwise leave /home set to root./パーティションを選択します。ルートパーティションとスワップパーティションを指定します。USE FOR」欄で、パーティションを何に使うかを選びます。ホームディレクトリ用に別のパーティションを設定する場合は、ここで指定します。そうでない場合は、/home を root に設定したままにします。
 - Many users prefer to locate their home directory in a different partition than that of / (root), so that any problem with — or even total replacement of — the installation partition will leave all the user's individual settings and files untouched.多くのユーザーは、ホームディレクトリを / (ルート) とは別のパーティションに置くことを好みます。そうすることで、インストールパーティションに問題が発生しても、あるいは完全に置き換えられても、ユーザーの個々の設定やファイルはそのまま残ります。
 - Unless you are using encrpytion or know what you are doing, leave boot set to root. 暗号化を使用しているか、自分が何をしているかわかっているのでなければ、ブートは root のままにしておいてください。
 - There is simple partition management available on this screen. Right click a disk to show partition templates. The templates are only suitable for whole disk changes, so if you want to resize or otherwise fine tune partition layouts, use an external partition manager (i.e., GParted) availabe by clicking the Partition Manager button in the lower right of the Partition Chooser.この画面では簡単なパーティション管理ができる。ディスクを右クリックすると、パーティションテンプレートが表示されます。テンプレートはディスク全体の変更にしか適していないので、パーティションレイアウトのサイズ変更や微調整をしたい場合は外部パー

ティションマネージャ (GParted など) は、Partition Chooser の右下にある Partition Manager ボタンをクリックすることで利用できます。

- **Preferences.** 各種設定

- Check Preserve data in /home if you are doing an upgrade and already have data in an existing partition or folder. This option is not generally recommended because of the risk that old configurations will not match the new installation, but can be useful in specific situations, e.g., repairing an installation. アップグレードを行う場合で、既存のパーティションやフォルダに既にデータがある場合は、「/home にデータを保存」をチェックします。このオプションは、古い設定が新しいインストールと一致しなくなる危険性があるため、一般的には推奨されませんが、インストールの修復など、特定の状況では有用です。
- Select Check for bad blocks if you want to do a scan for physical defects on the hard drive during formatting. This is recommended for users with older drives. フォーマット中にハードディスク・ドライブの物理的な欠陥をスキャンする場合は、不良ブロックのチェックを選択します。これは古いドライブを使用しているユーザにお勧めします。
- You can change the label of the partition where you want to install (e.g., to “MX-23 Testing Installation”) in the **Label** column. Label "欄で、インストールするパーティションのラベルを変更できます("MX-23 Testing Installation"など)。
- Finally, you can optionally select the type of file system you want to use on the hard drive. The default ext4 is recommended in MX Linux if you have no particular choice. 最後に、ハードドライブで使用するファイルシステムのタイプをオプションで選択できます。特に選択肢がない場合は、MX Linux ではデフォルトのext4が推奨されます。
- You can fine-tune your encryption cipher settings with the “Advanced Encryption Settings” button or just keep the defaults. 高度な暗号化設定」ボタンで暗号化設定を微調整することも、デフォルトのままにしておくこともできます。




Figure 2-19: Installer asking about boot method. 図 2-19 : ブート方法について尋ねるインストラー。

Comments コメント

- While the main linux OS is being copied to the hard drive, you can click the “Next” button to fill in some additional configuration information. Figure 2-18 shows the GRUB bootloader installation options. メインのlinux OS がハードドライブにコピーされている間に、"Next "ボタンをクリックして追加設定情報を入力することができます。図 2-18 に GRUB ブートローダーのインストールオプションを示します。
- Most average users will accept the defaults here, which will install the bootloader into the very beginning of the disk. This is the usual location and will cause no harm. ほとんどの一般的なユーザーは、ブートローダをディスクの一番最初にインストールする、ここのデフォルトを受け入れるでしょう。これは通常の場所であり、害はありません。
- UEFI users should choose whatever ESP partition they wish to use. Default is the first one found. UEFI ユーザーは使いたい ESP パーティションを選んでください。デフォルトは最初に見つかったものです。
- When you click Next, a pop-up message will check to see that you accept the location of the bootloader GRUB. Installing GRUB can take a few minutes in some situations. Next をクリックすると、ポップアップメッセージが表示され、ブートローダ GRUB の場所を確認します。GRUB のインストールには、状況によっては数分かかることがあります。
- Note that the partition shown (sda) is just an example; your particular selection of partition may well differ. 表示されているパーティション(sda)は単なる例であることに注意してください。




Figure 2-20: Computer Network Names Setup. 図 2-20 :コンピュータネットワーク名のセットアップ。

Comments コメント

- Many users choose a unique name for their computer: laptop1, MyBox, StudyDesktop, UTRA, etc. You may also just leave the default name as it is. ラップトップ 1、MyBox、StudyDesktop、UTRA など。デフォルト名のままでも構いません。
- You can just click Next here if you have no computer network. コンピュータ・ネットワークがない場合は、ここで「次へ」をクリックしてください。

- If you are not going to host shared network folders on your PC, then you can disable Samba. This will not affect your PC's ability to access shares hosted elsewhere on your network.もし、あなたのPC上で共有ネットワークフォルダをホストしないのであれば、Sambaを無効にすることができます。これは、ネットワーク上の他の場所でホストされている共有にアクセスするあなたのPCの能力に影響を与えない。




Figure 2-21: Locale, Timezone, and Service Settings.図 2-21 :ロケール、タイムゾーン、およびサービスの設定。

Comments コメント

- The default settings will usually be correct here, as long as you were careful to enter any exceptions at the LiveMedium boot screen. LiveMedium のブートスクリーンで例外を入力するように注意していれば、デフォルト設定は通常ここで正しいでしょう。
- The settings can be changed again once you have booted into Xfce. Xfce を起動すれば、再度設定を変更することができる。




Figure 2-22: Enable/Disable Services.

Comments コメント

- This screen only shows if “View” was clicked on the Locale, Timezone & Services Setting screen. この画面は、「ロケール、タイムゾーン、サービス設定」画面で「表示」をクリックした場合のみ表示されます。
- Services are applications and functions associated with the kernel that provide capabilities for upper-level processes. If you are not familiar with a service, you should leave it alone. サービスとは、カーネルに関連するアプリケーションや関数のことで、上位プロセスに機能を提供するものである。サービスに馴染みがなければ、放っておくべきである。
- These applications and functions take time to start and require memory, so if you are concerned about the capacity of your computer, you can look at this list for items that you are sure you do not need. これらのアプリケーションや機能は起動に時間がかかり、メモリを必要とするため、コンピュータの容量が心配な場合は、このリストを見て、確実に不要なアイテムを探すことができる。
- If you later want to change or adjust the startup services, you can use a command-line tool called **sysv-rc-conf**. Sysv-rc-conf is installed by default and must be run as root. 後でスタートアップ・サービスを変更または調整したい場合は、sysv-rc-conf というコマンドライン・ツールを使うことができる。sysv-rc-conf はデフォルトでインストールされ、root として実行する必要がある。




Figure 2-23: User Configuration. 図 2-23 : ユーザー設定

Comments コメント

- The level of security on the passwords you choose here will depend greatly on the setting of the actual computer. A home desktop is generally less likely to be broken into. ここで選択するパスワードのセキュリティレベルは、実際のコンピュータの設定に大きく依存する。一般的に、自宅のデスクトップは侵入される可能性が低い。
- If you check Autologin, you will be able to bypass the login screen and speed up the boot process. The downside of that choice is that anyone with some kind of access to your computer would be able to log directly into your account. You can later change your

autologin preferences on the “Options” tab of the MX User Manager. 自動ログインにチェックを入れると、ログイン画面をバイパスして起動プロセスをスピードアップできる。この選択の欠点は、あなたのコンピュータにアクセスできる人なら誰でも、あなたのアカウントに直接ログインできてしまうことです。自動ログインの設定は、MX ユーザーマネージャの "オプション" タブで変更できます。

- You can transfer any changes you make to your live desktop to the hard drive installation by checking the last box. A small amount of critical information (e.g., the name of your wireless Access Point) will be transferred automatically. 最後のボックスにチェックを入れると、ライブデスクトップに加えた変更をハードドライブのインストールに転送できます。少量の重要な情報(ワイヤレスアクセスポイントの名前など)は自動的に転送されます。
- If you do not set a root password, GUI authentications will be set to the user password if they haven't been already. root パスワードを設定しない場合、GUI 認証はユーザーパスワードに設定されます。




Figure 2-24: Installation Complete.図 2-24 :インストールの完了。

Comments コメント

- After the system copy is finished and the configuration steps are complete, an “Installation Complete” screen will be presented and you are ready to go! システムのコピーが終了し、設定手順が完了すると、"Installation Complete" 画面が表示され、準備完了です!
- If you don't want to reboot after finishing installation, uncheck the automatic reboot option before clicking Finish. インストール終了後に再起動したくない場合は、Finish をクリックする前に自動再起動オプションのチェックを外してください。

2.6 トラブルシューティング

2.6.1 オペレーティングシステムが見つかりません

When rebooting after an installation, it sometimes happens that your computer reports that no operating system or bootable disc was found. It also may not show another installed OS such as Windows. Usually, these problems mean that GRUB did not install properly, but that is easy to correct. インストール後に再起動すると、オペレーティングシステムやブータブルディスクが見つからないとコンピュータが報告することがあります。また、Windows のような他のインストールされた OS が表示されないこともあります。通常、これらの問題は GRUB が正しくインストールされなかったことを意味しますが、修正するのは簡単です。

- If booting with UEFI, make sure Secure Boot is turned off in your system BIOS/UEFI settings. UEFI で起動する場合は、システム BIOS/UEFI 設定でセキュアブートがオフになっていることを確認してください。
- If you can boot into at least one partition, open there a root terminal and run this command: 少なくとも 1 つのパーティションで起動できるのであれば、そこで root テーミナルを開き、次のコマンドを実行する:
update-grub
- Otherwise, proceed with MX Boot Repair. そうでなければ、MX ブート修復を続行する。
 - Boot to the LiveMedium. Live メディアを起動する。
 - Launch **MX Tools > Boot Repair**. MX Tools > Boot Repair を起動します。
 - Make sure that “Reinstall GRUB Bootloader” is selected, then click OK. GRUB ブートローダーの再インストールが選択されていることを確認し、「OK」をクリックします。
 - If this still does not fix it, you may have a faulty hard drive. Usually, you will have seen a SMART warning screen about it when you began your installation. それでも直らない場合は、ハードドライブが故障している可能性があります。通常、インストール開始時に SMART の警告画面が表示されます。

2.6.2 データまたはその他のパーティションにアクセスできない

Partitions and drives other than the one designated as boot may not be booted or require root access after installation. There are a couple of ways to change this. ブートとして指定されたパーティション以外のパーティションやドライブは、インストール後にブートされなかったり、root アクセスが必要になったりします。これを変更するには、いくつかの方法があります。

- For internal drives, use Start > Settings > MX Tweak, Other tab: check "Enable mounting of internal drives by non-root users." 内蔵ドライブについては、[スタート] > [設定] > [MX Tweak] の [その他] タブで、"非 root ユーザーによる内蔵ドライブのマウントを有効にする" をチェックします。
- **GUI.** Use Disk Manager to check anything you want mounted at boot and save; when you reboot it should be mounted and you will have access in the file manager (Thunar). ディスクマネージャーを使って、起動時にマウントしたいものをチェックし、保存します。再起動するとマウントされ、ファイルマネージャー(Thunar)でアクセスできるようになります。

- **CLI.** Open a file manager and navigate to the file /etc/fstab; use the right-click option to open it as root in a text editor. Look for the line containing the partition or drive to which you want access (you may need to type `blkid` in a terminal to identify the UUID). Change it following this example for a data partition. ファイルマネージャーを開き、/etc/fstab ファイルに移動する。右クリックオプションを使って、テキストエディタで root として開く。アクセスしたいパーティションやドライブを含む行を探します(UUID を特定するためにターミナルで `blkid` と 入力する必要があるかもしれません)。データパーティションの場合は、以下の例に従って変更してください。

```
UUID=9501<snip>912 /data ext4 users 0 2
```

This entry will cause the partition to be automatically mounted at boot time, and also allow you to mount it and umount it as a normal user. This entry will also cause the file system to be checked periodically at boot time. If you don't want it mounted automatically at boot time then change the options field from "user" to "user,noauto". このエントリーにより、パーティションはブート時に自動的にマウントされ、通常のユーザーとしてマウントやアンマウントができるようになります。このエントリは、起動時にファイルシステムを定期的にチェックするようにします。ブート時に自動的にマウントしたくない場合は、オプションフィールドを "user" から "user,noauto" に変更してください。

- If you don't want it checked regularly then change the final "2" to a "0". Since you have an ext4 filesystem, it is suggested that you enable the automated checking. 定期的にチェックしたくない場合は、最後の "2" を "0" に変更してください。ext4 ファイルシステムを使用しているので、自動チェックを有効にすることをお勧めします。
- If the item is mounted but not showing in the file manager, add an additional "comment=x-gvfs-show" to the line in your fstab file, which will force the mount to be visible. In the example above, the change would look like this: マウントされているにもかかわらずファイル・マネージャに表示されない場合は、fstab ファイルの行に "comment=x-gvfs-show" を追加する。上記の例では、次のように変更します:

```
UUID=9501<snip>912 /data ext4 users,comment=x-gvfs-show 0 2
```

NOTE: neither of these procedures will change Linux permissions, which are enforced on the folder and file level. See Section 7.3. 注意: これらの手順はどちらも Linux のパーティションを変更するものではない。セクション 7.3 を参照のこと。

2.6.3 Keyring problems キーリングの問題

A default key ring should be created automatically and the user will not need to do anything. If using autologin, when an app accesses the keyring the user would be asked to enter a new password to create a new default keyring. For details, see the [MX/Antix Technical Wiki](#). デフォルトのキー・ホルダーは自動的に作成され、ユーザーは何もする必要はありません。オートログインを使用する場合、アプリがキーリングにアクセスすると、ユーザーは新しいデフォルトのキーリングを作成するために新しいパスワードの入力を求められます。詳細については、MX/Antix Technical Wiki を参照してください。

Note that if malevolent agents get physical access to your machine, using a blank password will make it easier to break into. But it seems pretty clear that if a malevolent agent has physical access to your machine, it's all over anyway. 悪意のあるエージェントがあなたのマシンに物理的にアクセスした場合、空白のパスワードを使用すると侵入が容易になることに注意してください。

しかし、悪意のあるエージェントがあなたのマシンに物理的にアクセスした場合、いずれにせよすべてが終わることは明らかにようだ。

2.6.4 Locking up ロックアップ

If MX Linux is locking up during installation, it is usually due to a problem with faulty computer hardware or a bad DVD. If you have determined that the DVD is not the problem, it may be due to faulty RAM, a faulty hard drive, or some other piece of faulty or incompatible hardware. インストール中に MX Linux がロックしてしまう場合、通常はコンピュータのハードウェアに問題があるか、DVD の不良が原因です。DVD に問題がないと判断された場合、RAM の不良、ハードドライブの不良、その他のハードウェアの不良や互換性の欠如が原因である可能性があります。

- Add one of the Boot Options using F4 at boot or consulting the [MX/antiX Wiki](#). The most common problem arises from the graphics driver . ブート時に F4 キーを押してブートオプションを追加するか、MX/antiX Wiki を参照してください。最も一般的な問題は、グラフィックドライバに起因します。
- Your DVD drive may be having problems. If your system supports it, create an MX Linux bootable USB thumb drive and install from that. DVD ドライブに問題がある可能性があります。システムがサポートしている場合は、MX Linux ブート可能な USB メモリを作成し、そこからインストールしてください。
- Systems often lock up due to overheating. Open the computer's case and ensure that all the system's fans are running when it is turned on. If your BIOS supports it, check the CPU and motherboard temperatures (enter **sensors** in a root terminal if possible) and compare them to the temperature specifications for your system. 過熱が原因でシステムがロックすることはよくあります。コンピュータのケースを開け、電源を入れたときにシステムのファンがすべて回転していることを確認してください。BIOS がサポートしている場合は、CPU とマザーボードの温度をチェックし(可能であればルートターミナルでセンサーを入力する)、システムの温度仕様と比較する。

Shut down your computer and remove any non-essential hardware, then attempt the installation again. Non-essential hardware may include USB, serial, and parallel-port devices; removable PCI, AGP, PCIE, modem slot, or ISA expansion cards (excluding video, if you do not have onboard video); SCSI devices (unless you are installing to or from one); IDE or SATA devices that you are not installing to or from; joysticks, MIDI cables, audio cables, and any other external multimedia devices. コンピュータをシャットダウンし、必要でないハードウェアを取り外し、再度インストールを試みます。必要でないハードウェアには、USB、シリアル、パラレルポートデバイス、取り外し可能な PCI、AGP、PCIE、モデムスロット、ISA 拡張カード(オンボードビデオを搭載していない場合はビデオを除く)、SCSI デバイス(インストール先またはインストール元が SCSI デバイスでない場合)、インストール先またはインストール元が IDE または SATA デバイス、ジョイスティック、MIDI ケーブル、オーディオケーブル、その他の外部マルチメディアデバイスが含まれます。

3 設定（環境設定）



VIDEO: [MX Linux インストール後にすべきこと](#)

This section covers configuration instructions in order to get your system running correctly from a fresh installation of MX Linux, and a short guide to personal customization. このセクションでは、MX Linux の新規インストールからシステムを正しく動作させるための設定手順と、個人的なカスタマイズに関する簡単なガイドを説明します。

3.1 周辺機器

3.1.1 スマートフォン (Samsung, Google, LG など)



VIDEO: [スマートフォン & MX-16 \(samsung galaxy s5 および iphone 6\)](#)

Android

Android デバイスとのファイル共有。

1. Android phones can be accessed via a web browser by installing an app from Google's Play Store such as [AirDroid](#). Android 携帯は、グーグルの Play ストアから AirDroid のようなアプリをインストールすることで、ウェブブラウザ経由でアクセスすることができる。

2. They can also be mounted directly. 直接取り付けることもできる。

- Most phones running Android 4.xx and later include MTP capability, and you can use the following procedure. Android 4.xx 以降を搭載しているほとんどの携帯電話には MTP 機能が搭載されており、以下の手順を使用することができます。
 - Connect phone, and tap on the link that appears to make sure storage option id is set to “file exchange” or something similar. 電話を接続し、表示されるリンクをタップして、ストレージオプションの ID が「ファイル交換」などに設定されていることを確認する。
 - Open MX File Manager. When the Devices shows your phone's name (or: Storage), click on it. If you don't see it, reboot the phone. Your phone may then show a dialog box asking if you allow access. MX ファイルマネージャーを開きます。デバイスに携帯電話の名前(または:ストレージ)が表示されたら、それをクリックします。表示されない場合は、電話を再起動します。すると、アクセスを許可するかどうかを尋ねるダイアログボックスが表示される場合があります。

- Navigate to the location you are looking for. お探しの場所に移動します。
- Some files can be viewed and managed with MX Linux applications: click on Device in the left pane, then double-click CD Drive if necessary. 一部のファイルは、MX Linux アプリケーションで表示・管理できます。左ペインで「デバイス」をクリックし、必要に応じて「CD ドライブ」をダブルクリックします。
- **KDE Connect** is also an option for sharing files with an Android phone. KDE Connect is available in the Application Menu in MX KDE. If not already installed on your Android phone, it is available from the Google Play Store. KDE Connect は、Android 携帯とファイルを共有するためのオプションもあります。KDE Connect は MX KDE のアプリケーションメニューから利用できます。Android 携帯にインストールされていない場合は、Google Play Store から入手できます。
- By default the firewall will block the connection from your Android device. It will have to be disabled or a Firewall Rule set to allow the connection. デフォルトでは、ファイアウォールは Android デバイスからの接続をブロックします。ファイアウォールを無効にするか、ファイアウォールルールを設定して接続を許可する必要があります。
- Music: use **the default music player (Strawberry)** 音楽: デフォルトの音楽プレーヤーを使用(ストロベリー)
- Pictures: use the default **image viewer application (nomacs)** or install a different application using **MX Package Installer**. 写真: デフォルトの画像ビューアアプリケーション(nomacs)を使用するか、MX パッケージインストーラを使用して別のアプリケーションをインストールしてください。




Figure 3-1a: Thunar connected to a Samsung Android phone. 図 3-1a : Samsung の Android 携帯に接続された Thunar 。




Figure 3-1b: Dolphin connected to a Samsung Android phone. 図 3-1b : サムスンのAndroid携帯に接続されたドルフィン

Apple iPhone

MX iDevice Mounter provides access through Thunar to older devices. Newer phones can no longer be accessed with that process. MX iDevice Mounter は Thunar を通して古いデバイスへのアクセスを提供します。新しい携帯電話は、このプロセスではアクセスできなくなりました。

3.1.2 Printer プリンタ




Figure 3-2: Print Setting's New Printer screen. 図 3-2 : Print Setting の New Printer 画面。

Attached printer 付属のプリンタ

MX Linux offers two utilities for configuring and managing printers. Print Settings usually works well, but if problems arise it is recommended that you switch to CUPS in a browser by entering “localhost:631: in a web browser address bar. MX Linux には、プリンターを設定・管理するためのユーティリティーが2つあります。通常、Print Settings はうまく機能しますが、問題が発生した場合は、Web ブラウザのアドレスバーに「localhost:631:」と入力して、ブラウザから CUPS に切り替えることをお勧めします。

- Print Settings application 印刷設定アプリケーション
 - Click **Start menu > System > Print Settings** スタート]メニュー > [システム] > [印刷設定]をクリックします。
 - Click on the “+Add” button 「追加」ボタンをクリック
 - Wait on the New Printer screen while the application searches for attached and wireless printers. アプリケーションが接続されたプリンターとワイヤレスプリンターを検索している間、「新しいプリンター」画面で待ちます。
 - It will show recommended software for any printer found. 見つかったプリンターに対応する推奨ソフトが表示されます。
 - Follow the prompts to conclude the printer installation. 画面の指示に従って、プリンターのインストールを終了してください。
 - If problems arise you can sometimes solve them by switching to CUPS.
 - Enter <http://localhost:631/admin> in a web browser
 - On that page you can add printers, examine jobs, etc.
- ヘルプ: [Debian Wiki](#).

Network Printer ネットワークプリンタ

[Samba](#) on MX Linux allows printing via the network to shared printers on other computers (Windows, Mac, Linux) and NAS (Network Attached Storage) devices offering Samba services (Section 3.5). Samba on MX Linux では、Samba サービスを提供する他のコンピューター (Windows、Mac、Linux) や NAS (Network Attached Storage) デバイス上の共有プリンターにネットワーク経由で印刷できます (3.5 節参照)。

Using Print Settings 印刷設定を使う

- Click **Start menu** > **System** > **Print Settings** スタートメニュー > システム > 印刷設定 をクリックする
- Select **Server** > **New** > **Printer** サーバー」 → 「新規作成」 → 「プリンター」を選択
- Select Network Printer > Windows Printer via SAMBA. Network Printer > Windows Printer via SAMBA を選択します。
- In the dialog window for smb:// enter either servername/printernname or server-ipaddress/printernname. For example: smb://bigserver/usbprinter1 or smb://192.168.0.100/printer2 smb://のダイアログウィンドウで、servername/printernname または server-ipaddress/printernname のいずれかを入力します。例: bigserver/usbprinter1 または 192.168.0.100/printer2
- If you have trouble identifying the server and printer names, click **Start menu** > **System** > **Samba** for details. サーバー名、プリンター名の特定が難しい場合は、スタートメニュー>システム>Samba をクリックし、詳細をご確認ください。
- Leave the button selected for Prompt user if authentication is required, then click Forward. Prompt user if authentication is required "のボタンを選択したまま、"Forward "をクリックします。
- Leave the button selected for Select printer from database and then click Forward. データベースからプリンターを選択する]ボタンを選択したまま、[進む]をクリックします。
- Select the driver and then Forward. ドライバを選択し、進むをクリックします
- Describe Printer if necessary and then Apply. 必要であればプリンターについて説明し、適用します
- When the printer appears in the window, right-click Properties > Print Test Page to make sure the connection and driver are operating correctly. ウィンドウにプリンターが表示されたら、「プロパティ」→「テストページの印刷」を右クリックし、接続とドライバーが正しく動作していることを確認します。

Troubleshooting トラブルシューティング

- There is a troubleshooting utility integrated into the Print Settings application. Click Help > Troubleshoot. 印刷設定アプリケーションには、トラブル解決のためのユーティリティが組み込まれています。ヘルプ] > [トラブルシューティング]をクリックします。

- For HP printers, the extra package HP Printing () will install a useful applet into the Notification Area which provides troubleshooting tools. HP 製プリンタの場合、追加パッケージの hplip-gui を使用すると、トラブルシューティングツールを提供する便利なアプレットを通知領域にインストールすることができます。
- If your printer suddenly stops printing, check that it is still enabled by clicking **Start menu > System > Print settings**, then right-click your printer and enable it again. 突然印刷ができなくなった場合は、「スタートメニュー」→「システム」→「印刷設定」でプリンタが有効になっていることを確認し、プリンタを右クリックして再度有効にしてください。
- If your printer is not recognized or does not function correctly, consult the [MX/antiX Wiki](#) for detailed help on getting the correct driver. プリンターが認識されない、または正しく機能しない場合は、MX/antiX Wiki で正しいドライバー入手するための詳細なヘルプを参照してください。

3.1.3 スキャナ

Scanners are supported in Linux by SANE (Scanner Access Now Easy), which is an application programming interface (API) that provides standardized access to any raster image scanner hardware (flatbed scanner, hand-held scanner, video- and still-cameras, frame-grabbers, etc.). スキャナは、SANE (Scanner Access Now Easy)というアプリケーション・プログラミング・インターフェースによって Linux でサポートされており、ラスターイメージスキャナのハードウェア(フラットベッドスキャナ、ハンドヘルドスキャナ、ビデオカメラ、スチールカメラ、フレームグランバーなど)に標準的にアクセスできるようになっている。

Basic steps 基本ステップ

You can manage your scanner in MX Linux with the default **Simple Scan**. It is very easy to use and can export to PDF with a single click. MX Linux では、デフォルトの Simple Scan でスキャナーを管理することができます。これは非常に使いやすく、ワンクリックで PDF にエクスポートすることができます。

Troubleshooting トラブルシューティング

- Some scanners require a different frontend (system interface to the scanner): you can install gscan2pdf, click Edit > Preferences, and use the pull-down menu to select another (e.g., scanimage). スキャナによっては、別のフロントエンド(スキャナとのシステムインターフェース)を必要とします。gscan2pdf をインストールし、Edit > Preferences をクリックし、プルダウンメニューで別のもの(例:scanimage)を選択することが可能です。
- Make sure your scanner is listed as supported by SANE on [this list](#). お使いのスキャナーが、このリストで SANE に対応していることを確認してください。

- If you continue to have problems, check [the MX/antiX Wiki](#) for solutions. 問題が解決しない場合は、MX/antiX Wiki で解決策を確認してください。

3.1.4 ウェブカメラ

Most likely your webcam video will work in MX Linux; you can test it by launching **Start menu** > **Multimedia** > **webcamoid** and using the settings at the bottom of the window to adjust for your system. If it does not appear to work, there is a recent detailed discussion of drivers and setup in [the Arch Wiki](#). Webcam audio is sometimes trickier, see Section 4.1 about Skype. ほとんどの場合、ウェブカメラのビデオは MX Linux で動作します。スタートメニュー > マルチメディア > webcamoid を起動し、ウィンドウの下部にある設定を使ってお使いのシステムに合わせることで、ウェブカメラビデオをテストすることができます。もし動かないようであれば、Arch Wiki にドライバやセットアップに関する最近の詳細な議論があります。Webcam オーディオは時々ト リッキーになることがあります、Skype についての 4.1 章を参照してください。

3.1.5 ストレージ

Disk Drives (such as SCSI, SATA and SSD), cameras, USB drives, phones, etc. – these are all different forms of storage. ディスクドライブ(SCSI、SATA、SSD など)、カメラ、USB メモリ、スマホなど。 - これらはすべて異なるストレージの形態です。

Storage Mounting ストレージをマウントする

By default, storage devices that are plugged into the system mount automatically in the `/media/<username>/` directory, and then a file browser window opens for each (that behavior can be changed in Thunar: Edit > Preferences or KDE: System Settings > Removable Storage). デフォルトでは、システムに接続されたストレージデバイスは、自動的に`/media/<ユーザー名>/` のディレクトリにマウントされ、それぞれファイルブラウザのウィンドウが開きます(この動作は、Thunar: Edit > Preferences または KDE: System Settings > Removable Storage で変更可能です)。

Not all storage devices, especially extra internal drives and partitions, are mounted automatically when they are plugged into a system and may require root access. Options can be adjusted with MX Tweak > Other, and Settings > Removable Drives and Media. すべてのストレージデバイス、特に余分な内蔵ドライブやパーティションが、システムに接続されたときに自動的にマウントされるとは限らず、ルートアクセスが必要になる場合があります。オプションは、MX Tweak > その他、および設定 > Removable Drives and Media で調整することができます。

Storage Permissions ストレージのパーミッション (アクセス権)

The extent of the user's access to storage will depend on the file system that it contains. Most commercial external storage devices, especially hard drives, will come preformatted as fat32 or

ntfs. ユーザーがストレージにアクセスできる範囲は、そのストレージに含まれるファイルシステムに依存します。ほとんどの市販の外付けストレージデバイス、特にハードディスクは、fat32 または ntfs として事前にフォーマットされています。

ストレージのファイルシステム	パーミッション (アクセス権)
FAT32	なし。
NTFS	デフォルトでは、デバイスをマウントするユーザーにパーミッション／所有権が付与されます。
ext2, ext4, および多数の Linux ファイルシステム	デフォルトでは、所有権を Root に設定してマウントされます。パーミッションの調整: セクション 7.3 を参照。

You can change the need to be Root for accessing internal storage devices with Linux file systems by using MX Tweak, Other tab (Section 3.2). Linux ファイルシステムで内蔵ストレージデバイスにアクセスする際の Root 化の必要性は、MX Tweak の Other タブ(3.2 項)で変更することができます。

SSD (ソリッドステートドライブ)

Newer machines may have an internal [SSD](#): a Solid State Drive that has no moving components. These drives tend to accumulate blocks of data that are no longer considered in use, slowing down this very fast drive. To prevent this from happening, MX Linux runs a [TRIM](#) operation on a weekly schedule that you can view by opening the file `/var/log/trim.log`. 新しい機種では、可動部品のない SSD(ソリッドステートドライブ)が内蔵されている場合があります。これらのドライブは、もはや使用されていないと考えられるデータのブロックを蓄積する傾向があり、この非常に高速なドライブの速度を低下させる。これを防ぐために、MX Linux は TRIM オペレーションを週次スケジュールで実行します。

3.1.6 Bluetooth 対応機器

External Bluetooth devices such as a keyboard, speaker, mouse, etc. will normally work automatically. If not, follow these steps: キーボード、スピーカー、マウスなどの外部 Bluetooth デバイスは、通常自動的に動作します。そうでない場合は、以下の手順に従ってください。

- Xfce: click Start menu > Settings > Bluetooth Manager (or: right-click the Bluetooth icon in the Notification Area > Devices). スタートメニュー > 設定 > Bluetooth Manager(または:通知領域で Bluetooth アイコンを右クリック > デバイス)をクリックします。
- KDE: Start menu > Settings > System Settings > Hardware > Bluetooth の順にクリックします。
- Check that your adapter is enabled and it is visible by clicking Start menu > Settings > Bluetooth Adapters. スタートメニュー > 設定 > Bluetooth アダプタの順にクリックし

て、アダプタが有効になっていること、およびアダプタが表示されていることを確認します。

- Make sure the device you want is visible; in Bluetooth Manager click Adapter > Preferences and select your visibility setting. Bluetooth マネージャで「アダプタ」> 「環境設定」をクリックし、可視性の設定を選択します。
- If the device you want is in the Devices window, select it and then click Setup. 目的のデバイスが「デバイス」ウィンドウにある場合は、それを選択し、「設定」をクリックします。
- If not, click the Search button, and press Connect on the line for the device to initiate pairing. そうでない場合は、「検索」ボタンをクリックし、デバイスの回線で「接続」を押して、ペアリングを開始します。
- For a phone, you will likely have to confirm the pairing number on both the phone and desktop. 電話の場合、デバイスとデスクトップの両方でペアリング番号を確認する必要がある可能性が高いです。
- After pairing with the Bluetooth device, the Setup dialog asks you to confirm the type of Bluetooth configuration to associate with it. Bluetooth 機器とのペアリング後、Setup ダイアログで関連付ける Bluetooth の設定の種類を確認します。
- When the Setup process is finished, the device should be working. セットアップが完了すると、デバイスが動作するはずです。

Object Transfer オブジェクトの転送

To be able to pass objects (documents, photos, etc.) back and forth between an MX Linux desktop and a device such as a phone using Bluetooth, take the following steps: MX Linux のデスクトップと携帯電話などのデバイス間で、bluetooth を使用してオブジェクト(ドキュメント、写真など)をやり取りできるようにするには、次の手順を実行します。

- Install **obex-data-server** from the repos. レポから obex-data-server をインストールします。
 - It will bring in libopenobex2 with it. libopenobex2 も一緒に持ってきてくれます。
 - In rare cases, the obex-data-server package may block Bluetooth mouse or keyboard usage. まれに、obex-data-server パッケージが Bluetooth マウスやキーボードの使用をブロックすることがあります。
- Confirm that the phone and desktop both have Bluetooth enabled and are visible. 携帯電話とデスクトップの両方がブルートゥースを有効にして、表示されていることを確認します。

- Send file. ファイルの送信
 - From the MX Linux desktop: right-click the Bluetooth icon in the Notification Area > Send file (or use Bluetooth Manager) MX Linux のデスクトップから: 通知領域の Bluetooth アイコンを右クリック > ファイルを送信(または Bluetooth Manager を使用)。
 - From the phone: follow the appropriate instructions for your device. 電話から: お使いのデバイスの適切な手順に従ってください。
- Keep your eye on the receiving device to confirm acceptance of the object being transferred. 受信デバイスから目を離さずに、転送されるオブジェクトの受け入れを確認する。

It is also possible to [make use of hcitool](#) on the command line. また、コマンドラインから hcitool を利用することも可能です。

Links リンク

- [Blueman Troubleshooting](#)
- [Arch Wiki](#)
- [Debian Wiki on Pairing](#)

3.1.7 ペンタブレット

[Wacom](#) pen tablets are auto-detected and natively supported on Debian. Details in [the MX/antiX Wiki](#). ワコムのペンタブレットは自動検出され、Debian でネイティブにサポートされます。詳細は MX/antiX Wiki をご覧ください。

Links

- [The Linux Wacom Project](#)

3.2 基本的な MX ツール

A number of applications have been developed specifically for MX Linux, adapted or brought over from antiX, or adapted from outside sources to save the user effort with important tasks often involving unintuitive steps. (Snapshot and other Advanced tools are treated in Section 6.6) 多くのアプリケーションが MX Linux 専用に開発され、アンチ X から適応または持ち込まれ、あるいは外部ソースから適応されて、しばしば直感的でない手順を含む重要なタスクでユーザー

の労力を節約しています。(スナップショットやその他のアドバンスドツールについては、セクション 6.6 で扱います)




Figure 3-3: MX Tools dashboard (Xfce installed). Live and KDE dashboards somewhat different. 図 3-3: MX Tools のダッシュボード (Xfce をインストール)。Live と KDE のダッシュボードはやや異なる。

3.2.1 MX アップデータ (旧 Apt-Notifier)

This versatile applet (Xfce only, KDE uses [Discover](#)) sits in the Notification Area where it notifies you when packages are available. Be sure to check the important options available through the context (right-click) menu. If it doesn't appear, launch MX Updater to refresh. Xfce only, KDE uses Discover.この多機能アプレット (Xfce のみ、KDE は Discover を使用)は、パッケージが利用可能になると通知領域に配置されます。コンテキスト(右クリック)メニューから利用可能な重要なオプションを必ず確認してください。もし表示されない場合は、MX Updater を起動して更新してください。Xfce のみ利用できます。KDE で Discover を使用してください。



Figure 3-4: View and upgrade screen from MX Updater. 図 3-4:MX アップデータからの表示とアップグレード画面

Notice the choice between upgrade and dist-upgrade. upgrade と dist-upgrade の選択に注目してください。

- **full-upgrade (dist-upgrade):** the default action. Will upgrade all packages that have updates, even those where an update will result in the automatic removal of other existing packages or cause new packages to be added to your installation in order that all dependencies are resolved. full-upgrade (dist-upgrade): デフォルトの動作です。アップデートの結果、他の既存のパッケージが自動的に削除されたり、すべての依存関係が解決するために新しいパッケージがインストールに追加されたりする場合でも、アップデートがあるすべてのパッケージをアップグレードします。
- **upgrade:** recommended only for more experienced users. Will only upgrade updateable packages that don't result in other packages being removed or installed. Using this option means some updateable packages may remain "held back" on your system. 経験豊富なユーザーにのみお勧めします。他のパッケージが削除されたりインストールされたりすることのない、アップデート可能なパッケージのみをアップグレードします。このオプションを使うと、アップデート可能なパッケージがシステム上に「保留」されたままになる可能性があります。
- An option for Unattended Upgrade is available in Preferences. It happens in the background, and neither add new or remove existing packages, using the "upgrade" method rather than dist-upgrade. 環境設定で無人アップグレードのオプションが用意されています。これはバックグラウンドで行われ、新しいパッケージの追加も既存のパッケージの削除も行わず、dist-upgrade ではなく「upgrade」方式で行われます。
- Other options are available in the config file その他のオプションは次の設定ファイルで利用可能です: `~/.config/MX-Linux/apt-notifier.conf`

ヘルプ: [こちら。](#)

3.2.2 Bash の設定

Bash (the default shell language in MX Linux) can now be set up with this small application. It allows the advanced user to make changes to the aliases and terminal prompt theming in the user's hidden `bashrc` file. Bash (MX Linux のデフォルトのシェル言語)は、この小さなアプリケーションで設定できるようになりました。上級ユーザは、ユーザの隠しファイルである `bashrc` で、エイリアスやターミナルプロンプトのテーマ設定を変更することができます。




Figure 3-5: the tab to add or change an alias. 図 3-5 : エイリアスを追加・変更するためのタブ

ヘルプ: [こちら。](#)

3.2.3 ブートオプション





Figure 3-6: Main screen showing various options. 図 3-6 : 各種オプションを表示したメイン画面

Boot Options include kernel parameters, GRUB themes, Splash images and other items. This app makes it quick and easy for users to manage these. The “Manage UEFI Boot Options” only appears when the PC is booted up in UEFI mode. Example below ブートオプションには、カーネルパラメータ、GRUB テーマ、スプラッシュイメージなどの項目があります。このアプリは、ユーザーがこれらを迅速かつ容易に管理することを可能にします。



ヘルプ: [こちら](#)。

3.2.4 Boot Repair ブートリペア

The bootloader is the first software program to run and is responsible for loading and transferring control to the kernel. It sometimes happens that the bootloader on a conventional installation (GRUB2) becomes dysfunctional, and this tool allows you to restore the bootloader to a functional state from a LIVE boot. ブートローダは、最初に実行されるソフトウェアプログラムで、カーネルの読み込みと制御の移行を担当します。従来のインストール(GRUB2)ではブートローダが機能しなくなることがあります。このツールを使用すると LIVE ブートからブートローダを機能する状態に回復させることができます。




Figure 3-7: Boot Repair main screen, with the most common option selected. 図 3-7: ブートリペアのメイン画面(最も一般的なオプションが選択されている状態)

HELP: [here](#).

3.2.5 明るさ調節トレイアイコン

This tool places an icon in the Systray that displays a small app with which the user can adjust screen brightness. このツールは、システムトレイにアイコンを配置し、ユーザーが画面の明るさを調整するための小さなアプリを表示します。





Figure 3-8: ready to adjust brightness. 図 3-8 : 明るさを調整するための準備

3.2.6 Chroot Rescue Scan

This tool allows you to get into a system even if its initrd.img is broken. このツールを使うと、initrd.img が壊れてもシステムに入ることができます。

ヘルプ: [こちら。](#)



```
Starting chroot-rescue-scan
=====
Scanning partitions ...
Scanning directories ...
Only one Linux system was found


Please select a Linux system to visit
  Distro      Date      Dir     Device   Arch   Label
> MX 21 Wildflower 2021-09-05 rootMX21 nvme0n1p4 64-bit rootMX21
> Rescan all partitions for Linux systems
> Quit

Press <Enter> to select the highlighted entry
Use 'r' to redraw, 'q' to quit
```

Figure 3-9: results of scan for Linux systems. 図 3-9 : Linux システムのスキャン結果

3.2.7 GPG キーの修復 (昔の Check apt GPG)

If you try to install non-authenticated packages, you will run into an apt error: *The following signatures couldn't be verified because the public key is not available.* This helpful utility saves carrying out the many steps necessary to obtain that key. 認証されていないパッケージをインストールしようとすると、apt のエラーに遭遇することになります。次の署名は、公開鍵が利用できないため、検証できませんでした。この便利なユーティリティを使えば、鍵入手するために必要な多くの手順を省くことができます。



```
Checking mx.debian.nz_mx_repo_dists_mx16_InRelease
  Good GPG signature found.

Checking ftp.nz.debian.org_debian_dists_jessie-updates_InRelease
  Good GPG signature found.

Checking mx.debian.nz_antix_dists_jessie_Release
  Good GPG signature found.

Checking ftp.nz.debian.org_debian_dists_jessie_Release
  Good GPG signature found.

Checking mx.debian.nz_mx_repo_dists_mx15_InRelease
  Good GPG signature found.

Checking security.debian.org_dists_jessie_updates_InRelease
  Good GPG signature found.

Press 'H' for online help, press any other key to close this window.
```

Figure 3-10: Results of checking repo public keys with Fix GPG keys. 図 3-10: Fix GPG キーでレポの公開鍵をチェックした結果

ヘルプ: [こちら。](#)

3.2.8 MX クリーンアップ




Figure 3-11: Cleanup ready to go to work. 図 3-11 :クリーンアップの準備完了

This handy little app offers an easy and safe way to remove unneeded files and restore space. Kernel Removal tool is used to remove older kernels no longer in use. この便利な小さなアプリは、不要なファイルを削除し、スペースを復元する簡単で安全な方法を提供します。

ヘルプ: [こちら。](#)

3.2.9 コーデックインストーラ

A codec is a piece of software that enables encoding/decoding a digital data stream or signal. Most codecs will be installed in MX Linux, but some are restricted. Libdvdcss2 (for reading commercial DVDs) and libtxc-dxtn0 (for certain 3D game textures) will be installed as well. This tool allows easy installation of certain restricted codecs while transferring the responsibility to the user. コーデックとは、デジタルデータのストリームや信号をエンコード/デコードするためのソフトウェアの一部です。MX Linux にはほとんどのコーデックがインストールされますが、いくつかは制限されています。Libdvdcss2 (市販 dvd の読み込み用)と libtxc-dxtn0 (特定の 3D ゲームのテクスチャ用)もインストールされる予定です。このツールを使えば、制限のあるコーデックを簡単にインストールすることができ、かつ、その責任をユーザーに転嫁することができます。



Figure 3-12: Codecs Installer main screen. 図 3-12 : Codecs インストーラのメイン画面

ヘルプ: [こちら。](#)

3.2.10 MX Conky

The app called **MX Conky** works in conjunction with [Conky Manager](#) to manipulate details of a Conky, especially color, in the MX Conky collection very easily. A “Conky Toggle” application to turn off and on any configured Conky is also in the menu. MX コンキー Conky というアプリは、Conky Manager と連動して、MX conky コレクションの中のコンキーの詳細(特に色)を非常に簡単に操作することができます。また、設定したコンキーの電源を切ったり入れたりする「コンキートグル」アプリもメニューにあります。




Figure 3-13: Conky ready to edit details of a default Conky. 図 3-13: デフォルトのコンキーの詳細を編集するためのコンキーの準備

ヘルプ: [こちら。](#)

3.2.11 ジョブスケジューラ

This handy app presents a graphic frontend to the command-line app [crontab](#), easing the setup of jobs. この便利なアプリは、コマンドラインアプリ crontab のグラフィックフロントエンドを提供し、ジョブのセットアップを容易にするものです。




Figure 3-15: Job Scheduler. 図 3-15: ジョブスケジューラ

HELP: local jobs file: </usr/share/job-scheduler/locale/>

3.2.12 Live-USB メーカー

This straightforward tool allows you to create quickly a Live-USB starting from an ISO file, a live -CD/DVD or an existing Live-USB or even a running live system. このシンプルなツールは、iso ファイル、ライブ CD/DVD、既存のライブ USB、あるいは実行中のライブシステムからライブ USB を素早く作成することができます。




Figure 3-16: Live USB Maker. 図 3-16: ライブ USB メーカー

ヘルプ: [こちら](#)

3.2.13 ネットワーク・アシスタント

This application renders the process of troubleshooting network problems much easier by detecting hardware, changing the state of a hardware switch, permitting Linux drivers to be managed, and providing general network tools. このアプリケーションは、ハードウェアの検出、ハードウェアスイッチの状態の変更、Linux と Windows のドライバの管理、一般的なネットワークツールの提供により、ネットワーク問題のトラブルシューティングをより容易にします。




Figure 3-18: Network Assistant detecting wireless hardware. 図 3-18: ネットワークアシスタントによる無線・有線ハードウェアの検出

ヘルプ: [こちら。](#)

3.2.14 Nvidia ドライバインストーラ

The Nvidia graphics driver installer vastly simplifies an important procedure: to install a proprietary graphic driver using the underlying ddm-mx script. Clicking on the Nvidia driver installer icon brings up a terminal, and all the user need do in most cases is accept the default. Nvidia グラフィックドライバインストーラは、基本的な ddm-mx スクリプトを使用して独自のグラフィックドライバをインストールするという、重要な手順を大幅に簡素化します。Nvidia ドライバインストーラのアイコンをクリックするとターミナルが表示され、ほとんどの場合、ユーザはデフォルトを受け入れるだけでよいのです。

ヘルプ: [こちら。](#)

3.2.15 パッケージインストーラ



VIDEO: [MX パッケージインストーラでアプリをインストールする](#)

The custom simple package manager for MX Linux allows you to can search for, install, or remove both popular packages and any package in the MX/Debian Stable, the MX Test, Debian Backports, and Flatpak repositories quickly, safely, and easily. MX Linux 用のカスタム簡単パッケージマネージャにより、人気のあるパッケージや MX/Debian Stable、MX Test、Debian Backports、Flatpak リポジトリのあらゆるパッケージを迅速、安全、簡単に検索、インストール、削除することができます。




Figure 3-20: Package Installer, showing popular packages for Development. / パッケージインストーラー(開発用の一般的なパッケージが表示されている

HELP: [here.](#)

3.2.16 クイックシステム情報





図 3-21: メインスクリーン

This useful tool allows the user to easily consult log files. The default log is Quick System Info that is required for Forum posts: note the button “Copy for forum” that permits a simple click to insert the log contents already formatted.この便利なツールは、ユーザーが簡単にログファイルを参照することができます。デフォルトのログは、フォーラムへの投稿に必要なクイックシステム情報です。“フォーラムにコピー”ボタンをクリックするだけで、すでにフォーマットされたログコンテンツを挿入できます。

3.2.17 リポマネージャ

There are many reasons why the user might want to change the default mirror being used, ranging from a server being offline to a change in the physical location of the computer. This great tool provides one-click switching of repos, saving a lot of time and effort. サーバーのオフラインからコンピュータの物理的な場所の変更まで、ユーザがデフォルトで使用されているミラーを変更したい理由はたくさんあります。この素晴らしいツールは、ワンクリックでレポを切り替えることができ、多くの時間と労力を節約できます。




It also provides a button that will test all repos (MX or Debian) and select the fastest. また、すべてのレポ (MX または Debian) をテストし、最速のものを提供するボタンもあります。

Figure 3-21: Choosing a Repository to use in Repo Manager. リポマネージャで使用するリポジトリを選択。

ヘルプ: [こちら。](#)

3.2.18 Samba 設定

MX Samba Config is a tool to help users manager their samba/cifs network shares. Users can create and edit shares that they own, as well as manage user access permissions for those shares. MX Samba 設定は、ユーザーの samba/cifs ネットワーク共有を管理するためのツールである。ユーザーは、自分が所有する共有の作成と編集ができ、共有のユーザーアクセスパーミッションを管理できる。



ヘルプ: [こちら。](#)

3.2.19 サウンドカード

Computers frequently have more than one sound card available, and the user who hears nothing may conclude that sound is not working. This clever little application allows the user to select which sound card should be used by the system. コンピュータには複数のサウンドカードが搭載されていることが多い、何も聞こえないユーザーはサウンドが機能していないと判断してしまうかもしれません。この小さなアプリケーションは、ユーザーがシステムで使用されるべきサウンドカードを選択することができます。



Figure 3-22: Making the selection in Sound Card. 図 3-22: サウンドカードで選択する

ヘルプ: [こちら。](#)

3.2.20 システムキーボード




Figure 3-23: Main screen ready for the user to select a different keyboard.図 3-23: 別のキーボードを選択するためのメイン画面

In case the user neglected to select system keyboard from the Login menu, missed setting it up on the Live session, or just needs to make a change, this little app provides an easy way to carry out that operation from the Start menu.ログインメニューでシステムキーボードを選択しなかったり、ライブセッションで設定し損ねたり、あるいは単に変更したい場合、この小さなアプリはスタートメニューからその操作を簡単に実行する方法を提供します。

ヘルプ: [こちら。](#)

3.2.21 システムロケール




Figure 3-24: Presentation of locales to be generated for the user.図 3-24: 表示されるロケールを生成します。

In case the user neglected to select system locale from the Login menu, missed setting it up on the Live session, or just needs to make a change, this little app provides an easy way to carry out that operation from the Start Menu.ログインメニューでシステムロケールを選択しなかったり、ライブセッションで設定し損ねたり、あるいは変更する必要がある場合、この小さなアプリはスタートメニューから簡単にその操作を実行する方法を提供するものです。

ヘルプ: [こちら.](#)

3.2.22 システム音 (Xfce のみ)

This little tool gathers into a single location the various actions and choices involved in setting up system sounds such as login/logout, actions, etc. この小さなツールは、ログイン/ログアウト、アクションなど、システムサウンドの設定に関する様々なアクションや選択肢を一箇所に集めることができます。




Figure 3-25: Setting up login and logout sounds in System Sounds. 図 3-25: システムサウンドでログインとログアウトのサウンドを設定する

ヘルプ: [こちら.](#)

3.2.23 日付と時間の設定

MX Date & Time allows adjustments of all kinds to be made from a single app. Xfce only. 日付と時刻の設定は、ルートアクセスを必要とし、1つのアプリからあらゆる種類の調整を行うことができます。




Figure 3-26: The main tab of Date & Time 図 3-26: 日付と時刻の設定メインタブ。左: Xfce、右: Xfce 。 KDE

ヘルプ: [こちら](#).

3.2.24 MX Tweak

MX Tweak brings together a number of small but often used customizations such as panel management, theme selection, compositor enabling and setup, etc. on a per-desktop basis. MX Tweak は、パネル管理、テーマの選択、コンポジターの有効化と設定など、小さいけれどよく使うカスタマイズをデスクトップ単位でまとめています。




Figure 3-27: The faces of MX-Tweak. Right: Plasma, Left: XFCE. 図 3-27: MX-Tweak の顔。右側。プラズマ、左: XFCE

ヘルプ: [こちら](#).

3.2.25 USB フォーマット




Figure 3-28: **USB Formatter ready to reformat with FAT32.** 図 3-28:USB フォーマッターは fat32 で再フォーマットする準備ができます。

This convenient little tool will clean out and reformat a USB drive in order to make it available for new purposes. この便利なツールは、USB ドライブをクリーンアップして再フォーマットし、新しい用途に使用できるようにします。

ヘルプ: [こちら](#).

3.2.26 USB アンマウンタ (Xfce のみ)

This tool for quickly unmounting USB and optical media sits in the Notification Area when enabled (default). A single click displays available media for unmounting with a double-click. USB や光学メディアを素早くアンマウントするためのツールで、有効化すると通知領域に表示されます(デフォルト)。ダブルクリックでアンマウント可能なメディアをシングルクリックで表示します。




Figure 3-29: **USB Unmounter with a device highlighted for unmounting.** 図 3-29: アンマウントするデバイスがハイライトされた USB Unmounter

ヘルプ: [こちら](#).

3.2.27 ユーザーマネージャ

This tool makes it much easier to add, edit and remove users and groups in your system. このアプリケーションは、システム内のユーザーとグループの追加、編集、削除を支援します。





Figure 3-30: User Manager, Administration tab. 図 3-30: ユーザーマネージャー、「管理」タブヘルプ: [こちら](#).

3.2.28 ユーザーインストールパッケージ

This application is intended to facilitate the re-installation of packages that the user has added to the default installation. このアプリケーションは、ユーザーがデフォルトのインストールに追加したパッケージの再インストールを容易にすることを目的としています。

It can display a list of packages manually installed by the user that can be saved in a simple text file. Furthermore, the application allows loading a saved list of packages for review and selection to be reinstalled. Such a procedure is especially easy and useful when installing a new system. ユーザーが手動でインストールしたパッケージのリストを表示し、シンプルなテキストファイルに保存することができます。さらに、このアプリケーションは、保存したパッケージのリストをロードして、再インストールするための確認や選択を行うことができます。このような手順は、新しいシステムをインストールする際に特に簡単で便利です。



ヘルプ: <file:///usr/share/user-installed-packages/help.html>

3.2.29 Deb インストーラ

This simple tool installs downloaded deb (Section 5.5.2) packages. このシンプルなツールは、ダウンロードした deb (セクション 5.5.2) パッケージをインストールする。

- Right-click on the deb package you want to install > "Open with Deb Installer". インストールしたい deb パッケージを右クリック > "Deb Installer で開く"。
- Click Install. Enter your root password when prompted. 「インストール」をクリックします。プロンプトが表示されたら、root パスワードを入力します。



Deb Installer will attempt to install the package, and report the results. Deb Installer はパッケージのインストールを試み、結果を報告します。

3.2.3 非推奨のツール

Some users will look for tools that either no longer exist or have been incorporated into new tools. ユーザーによっては、もう存在しないツールや、新しいツールに組み込まれたツールを探すこともあるでしょう。

- ATI/AMD ドライバインストーラ: 適切なドライバ候補がないため、削除しました。
- Broadcom マネージャ: ネットワークアシスタントとしてより一般的なニーズに対応できるように書き換えられました。
- Compton マネージャ: MX Tweak に組み込まれました。
- Debian バックポートインストーラ: パッケージインストーラに統合されました。
- Default Look: MX Tweak に組み込まれました。
- ネットワーク共有の検索: ライセンスの関係で削除されました。
- Flash Manager: Adobe® Flash® Player は現在非推奨で、完全に削除されました。
- Idevice Mounter: removed for lack of software support.
- Menu Editor: MenuLibre に置き換えられました。

- Panel Orientation: MX Tweak に統合されました。
- Test Repo Installer: パッケージインストーラに統合されました。
- Gdebi: Deb インストーラ MX ツールに置き換えられました。

3.3 ディスプレイ

3.3.1 ディスプレイの解像度




Figure 3-31: Display utility. Left: Xfce, Right: KDE/Plasma. 図 3-31: ディスプレイユーティリティ。左 :Xfce, 右 :KDE/plasma.

Resolution refers to the physical number of columns and rows of pixels creating the display (e.g., 1920x1200). In most cases, the resolution is correctly set by the kernel during installation or when a new monitor is connected. If not, you can change it in the following ways: 解像度とは、ディスプレイを構成するピクセルの列と行の物理的な数のことです(例: 1920x1200)。ほとんどの場合、インストール時や新しいモニターを接続したときに、カーネルによって解像度が正しく設定されます。そうでない場合は、以下の方法で変更することができます。

- Xfce: click Start Menu > Settings > Display. Use the pull-down menus to set the correct values for the monitor you want to adjust. For more options and finer control, install [xrandr](#) from the repos. スタートメニュー]→[設定]→[ディスプレイ]をクリックします。プルダウンメニューを使用して、調整したいモニターに適切な値を設定します。より多くのオプションとより細かい制御を行うには、レポから xrandr をインストールします。
- KDE: Start Menu > System Settings > Display and Monitor > Display Configuration.
- Xfce's Display makes fractional scaling for HiDPI monitors possible. Click on the pull-down menu for "Scale" and select Custom. 4.16 Xfce のディスプレイで、HiDPI モニタのための分数スケーリングが可能になりました。Scale" のプルダウンメニューをクリックし、"Custom" を選択します。

- In difficult situations, it is possible to manually alter the configuration file /etc/X11/xorg.conf. It may not exist, so you might need to [create it](#) first. Always back up the file before you change it, and check the Forum for help about the use of that file. 困難な状況下では、設定ファイルを手動で変更することが可能です。/etc/X11/xorg.conf。存在しないかもしれないのに、最初に作成する必要があるかもしれません。ファイルを変更する前に必ずバックアップを取り、そのファイルの使い方についてはフォーラムを参照してください。

3.3.2 グラフィックドライバ

If you are not satisfied with your display's performance, you may need/want to upgrade your graphic driver (make sure to first back up the file /etc/X11/xorg.conf, if used). Note that after a kernel upgrade you may have to repeat this, see Section 7.6.3. ディスプレイの性能に満足できない場合は、グラフィックドライバをアップグレードする必要があるかもしれません(/etc/X11/xorg.conf ファイルを使用している場合は、最初に必ずバックアップをとってください)。カーネルをアップグレードした後は、これを繰り返さなければならぬかもしれませんことに注意してください。

There are various methods available to do this. そのために、さまざまな方法が用意されています。

- For most **Nvidia** cards, by far the easiest method is to use the installers accessible from the MX Tools dashboard (see Section 3.2). ほとんどの Nvidia カードでは、MX Tools ダッシュボードからアクセスできるインストーラを使用するのが圧倒的に簡単な方法です (3.2 節を参照).
 - Some older or less common video cards require drivers (such as openchrome, mach64 & fbdev) that are only easily installable with **sgfxi** (Section 6.5.3). 古いビデオカードやあまり一般的でないビデオカードの中には、sgfxi (セクション 6.5.3) でしか簡単にインストールできないドライバ(openchrome, mach64 や fbdev など)を必要とするものがあります。
 - Some Nvidia cards are no longer supported in Debian Stable (“Jessie”), see [the MX/antiX Wiki](#). They are, however, supported by the **nouveau** and **vesa** drivers. いくつかの Nvidia カードは Debian 安定版（「Jessie」）ではサポートされなくなりましたので、 MX/antiX Wiki を参照してください。しかし、nouveau や vesa ドライバではサポートされています。
 - You can install the package **nvidia-settings** for a graphic tool that you can use to alter settings as root with the command: *nvidia-settings* nvidia-settings パッケージをインストールすれば、次のコマンドで、root 権限で設定を変更できるグラフィックツールが利用できます: *nvidia-settings*
 - Consult [the Debian Wiki](#) about open-source ati, radeon, and amdgpu drivers. Note that open drivers for AMD are no longer available. オープンソースの ati、raiden、amdgpu

ドライバについては、Debian Wiki を参照してください。AMD 用のオープンドライバはもう手に入らないことに注意してください。

- It is also possible, but more complicated, to download directly from the manufacturer. This method will require you to select and download the correct driver for your system; for system info, open a terminal and enter: `inxi -Gxx`. また、メーカーから直接ダウンロードすることも可能ですが、より複雑です。この方法では、お使いのシステムに適したドライバを選択してダウンロードする必要があります。システム情報については、ターミナルを開き、「`inx i -Gxx`」と入力してください。

Here are driver websites for the most popular brands (do a web search on “<brandname> linux driver” for others): 以下は、最も一般的なブランドのドライバのウェブサイトです(その他は「<br andname> linux driver」でウェブ検索してください)。

- [Nvidia](#)
- [Intel](#)

Intel drivers *must* be [compiled](#), but downloaded Nvidia drivers are easily installed: Intel のドライバーはコンパイルが必要ですが、Nvidia のドライバーはダウンロードしたもので簡単にインストールすることができます。

- Navigate in Thunar to the folder where the driver was downloaded. Thunar でドライバがダウンロードされたフォルダに移動します。
- Right-click the file, select the Permissions tab, check Is **executable**. ファイルを右クリックし、「アクセス権」タブを選択し、「実行可能」にチェックを入れます。
- Press CTRL-ALT-F1 to exit X (the graphical environment) and get to a terminal prompt. CTRL-ALT-F1 を押して X(グラフィカル環境)を終了し、ターミナルのプロンプトを表示します。
- root でログインします。
- 次のとおり入力します: `service lightdm stop`.
- 次のとおり入力します: `sh <ファイル名>.run` (必ず実際のファイル名で入力してください)
- Allow the NVIDIA driver to turn off the nouveau kernel. NVIDIA ドライバによる nouveau カーネルをオフにすることを許可する
- When it finishes, type: `service lightdm start` to start lightdm and xorg again. 終了後、`service lightdm start` と入力し、lightdm と xorg を再度起動します。

- Another important driver option is [MESA](#), an open-source implementation of the [OpenGL](#) specification - a system for rendering interactive 3D graphics. Users on high-performance machines report that upgrading this brings a significant stabilization to their system. もう一つの重要なドライバーオプションは、インタラクティブな 3D グラフィックをレンダリングするためのシステムである OpenGL 仕様のオープンソース実装である mesa です。高性能マシンのユーザーからは、これをアップグレードすることでシステムが大幅に安定したとの報告があります。
 - A more recent version may be available in the Test Repo; use the MX Package Installer (Section 3.2) to get it. Uncheck the box that hides the lib and dev packages, search for "MESA", and check off the packages that are upgradeable for installation. より新しいバージョンがテストレポーにあるかもしれません。それを入手するには MX パッケージインストーラー (セクション 3.2) を使ってください。lib と dev パッケージを隠すボックスのチェックを外し、"mesa" を検索し、アップグレード可能なパッケージにチェックを入れ、インストールします。
- Hybrid graphics cards combine two graphic adapters on the same unit. A popular example is the [NVidia Optimus](#), which is supported on Linux with [Bumblebee/Primus](#). Newer graphics cards can also use the Primus functions built into the nvidia-driver without the Bumblebee system. To run an application under Primus functions use “nvidia-run-mx APP” to start an app with the graphics acceleration enabled. ハイブリッド・グラフィックス・カードは、2つのグラフィック・アダプタを同じユニットに組み合わせたものです。よく知られている例としては、N Vidia Optimus があり、Linux では Bumblebee でサポートされています。最近のグラフィックカードはバンブルシステムを使わずに nvidia-driver に内蔵されている primus 機能を使うこともできます。Primus機能でアプリケーションを実行するには、「nvidia-run-mx APP」を使用して、グラフィックスアクセラレーションを有効にした状態でアプリケーションを起動します。

3.3.3 フォント

Basic adjustment 基本的な調整

1. XFCE- Click **Start Menu > All Settings > Appearance, Fonts tab.** スタートメニュー > すべての設定 > 外観の「フォント」タブをクリックします。
2. KDE/Plasma - Click **Start Menu > System Settings > Appearance > Fonts.** スタートメニュー > システム設定 > フォントの順にクリックします。
3. Click on the pull-down menu to see the list of fonts and point sizes. プルダウンメニューをクリックすると、フォントとポイントサイズのリストが表示されます
4. Select the one you want, and click OK. 好みのフォントを選択し、OK をクリックします。

Advanced adjustments 高度な調整

1. Root 端末で次のコマンドを実行すると、いくつかのオプションが利用できます: **dpkg-reconfigure fontconfig-config**
2. Individual apps may have their own controls, often found in Edit (or Tools) > Preferences. 個々のアプリには独自のコントロールがあり、「編集」(または「ツール」) > 「環境設定」にあることが多い
3. さらなる調整については、[the MX/antiX Wiki](#) を参照してください。
4. 高解像度ディスプレイには特別なニーズがあります。[MX/antiX Wiki](#) を参照してください。

Adding fonts フォントの追加

1. There are a few font packages in MX Package Installer available with a single click. For more possibilities, click (Xfce) **Start Menu** > **System** > **Synaptic Package Manager**; KDE: use Discover instead of Synaptic. MX パッケージインストーラーには、ワンクリックで利用できるものがいくつかあります。より多くの可能性については、スタートメニュー > システム > Synaptic/Muon パッケージマネージャーをクリックしてください。
2. Use the search function for fonts. フォントの検索機能をご利用ください。
3. Select and download the ones you want. The Microsoft (Core) Fonts package **ttf-mscorefonts-installer** in MX Package Installer provides easy installation of the Microsoft True Type Core Fonts for use with websites and MS applications that run under Wine. 必要なものを選んでダウンロードしてください。Microsoft コアフォントパッケージ ttf-mscorefonts-installer(デフォルトでインストールされています)は、Wine上で動作するウェブサイトや MS アプリケーションで使用する Microsoft True Type コアフォントを簡単にインストールすることができます。
4. Extract if necessary, then copy as root (easiest in a root Thunar) the font folder to **/usr/share/fonts/**. 必要に応じて解凍し、ルート(Thunar のルートで最も簡単)でフォントフォルダを次の場所にコピーします: /usr/share/fonts/
5. Your new fonts should be available in (Xfce) the pull-down menu in All Settings > Appearance, Fonts tab or (KDE) Start Menu > SystemSettings > Appearance > Fonts 新しいフォントは、「すべての設定」→「外観」→「フォント」タブのプルダウンメニューで利用できるはずです。

3.3.4 デュアルモニタ

Multiple monitors are managed in MX Linux Xfce with Start menu > Settings > Display. You can use it to adjust resolution, select whether one clones the other, which ones will be turned on,

etc. It is often necessary to log out and back in to see the display you select. Users should also look at the Display tab of MX Tweak. Finer control of some features is sometimes available with **xrandr**. MX Linux Xfce では、スタートメニュー > 設定 > ディスプレイでマルチモニターを管理します。これを使用して、解像度の調整、一方が他方をクローンするかどうか、どのモニターをオンにするかなどを選択できます。選択したディスプレイを見るために、しばしばログアウトし、再びログインすることが必要です。ユーザーは MX Tweak の Display タブも見ておくといいでしょう。いくつかの機能のより細かい制御は、xrandr で利用できる場合があります。

Xfce 4.18 has improved handling multiple monitors greatly, with settings on the Advanced tab of Display that permit detailed settings for each monitor and the ability to save monitor profiles and have them automatically used when the same hardware is connected again. If problems persist, search [the Xfce Forum](#), the MX Linux Forum and [the MX/antiX WIki](#) if you are having unusual problems. Xfce 4.18 では、マルチモニタの扱いが大幅に改善され、ディスプレイの詳細タブで各モニタの詳細な設定が可能になり、モニタプロファイルを保存して同じハードウェアを再び接続したときに自動的に使用できるようになりました。問題が解決しない場合、Xfce フォーラム、MX Linux フォーラム、MX/antiX WIki を検索して、異常な問題がある場合は、MX/antiX WIki を検索してください。

in KDE/Plasma Dual Monitors are set up with the Display Configuration Tool. KDE/Plasma では、デュアルモニタは Display configuration tool で設定されます。

Links リンク

- [Xfce Docs: Display](#)

3.3.5 電源管理

Click the Power Manager plugins icon in the Panel. Here you can easily switch to Presentation mode (Xfce), or go to the Settings to set when a display shuts down, when the computer goes into suspension, the action initiated by closing the lid of a laptop, brightness, etc. On a laptop, battery status and information is displayed and a brightness slider is available. パネル内の「Power Manager」プラグインアイコンをクリックします。ここでは、プレゼンテーションモード(Xfce)に簡単に切り替えることができます。また、設定から、ディスプレイがシャットダウンするタイミング、コンピュータがsuspend状態になるタイミング、ノートパソコンの蓋を閉じたときに開始する動作、明るさなどを設定することができます。ノートパソコンでは、バッテリーの状態や情報が表示され、明るさのスライダーも利用可能です。

3.3.6 モニタ調整

There are several tools available for adjusting the display for particular monitors. 特定のモニターに合わせた表示を調整するためのツールがいくつか用意されています。

- Screen brightness can be set (Xfce only) with Start menu > Settings > Power Manager, Display tab; MX Tweak; or MX Brightness Systray that will place a handy Widget in the Systray. 画面の明るさは、スタートメニュー > 設定 > パワーマネージャ、ディスプレイタブ (Xfce のみ)、MX Tweak、またはシステムトレイに便利なウィジェットを配置する MX Brightness Systray で設定できます。
- For users with Nvidia, use **nvidia-settings** as root for fine-tuning the display. Nvidia を使用しているユーザーは、nvidia-settings を root として使用してディスプレイを微調整する。
- To change the gamma (contrast), open a terminal and enter: ガンマ(コントラスト)を変更するには、ターミナルを開いて入力する:

```
xgamma -gamma 1.0
```

1.0 is the normal level; change it up or down to decrease/increase contrast. 1.0 は通常のレベルであり、コントラストを減少/増加させるために上下に変更する。

- Color of the display's adaptation to the time of day can be controlled with fluxgui or Redshift. 時間帯に適応するディスプレイの色は、fluxgui または Redshift でコントロールできる。
- For more advanced adjustment and profile creation, install displaycal. より高度な調整とプロファイル作成には、displaycal をインストールしてください。
- Color profiles can be created (Xfce only): Start > Settings > Color Profiles. A color profile is a set of data that characterizes a color input or output device, and most are derived from ICC profiles. カラープロファイルを作成できます(Xfce のみ):スタート > 設定 > カラープロファイル。カラープロファイルは、カラー入力または出力デバイスを特徴付けるデータのセットで、ほとんどは ICC プロファイルから派生したものです。




Figure 3-32: Getting ready to add a color profile. 図 3-32 : カラープロファイルを追加する準備
ヘルプ: [こちら](#).

3.3.7 ティアリング (Screen tearing)

Screen tearing is a visual artifact in video display where a display device shows information from multiple frames in a single screen draw (Wikipedia). It tends to vary greatly depending on factors that include graphics hardware, particular application and user sensitivity. ティアリング (Screen Tearing)とは、ビデオディスプレイにおいて、ディスプレイデバイスが複数のフレームの情報を1つの画面描画に表示する視覚的な現象である(ウィキペディア)。グラフィックハードウェア、特定のアプリケーション、ユーザーの感度などの要因によって大きく異なる傾向がある。

In MX Linux, various solutions are available: MX Linux では、さまざまなソリューションが利用できる:

- Click the Compositor tab in MX Tweak, and use the pull-down menu to switch from the default [xfwm](#) to Compton, a free-standing [compositor](#). MX ツイーカのコンポジタタブをクリックし、プルダウンメニューを使用して、デフォルトの xfwm から独立型コンポジターの Compton に切り替えます。
- Use the pull-down menu to alter the vertical spacing (vblank). プルダウンメニューを使用して、垂直方向の間隔(vblank)を変更します。
- When an Intel graphics driver is detected, a check box becomes available in MX Tweak > Config Options tab that switches the system away from the default "modesetting," a switch that enables the Intel driver's TearFree option. Tearfree options also exist for nouveau, radeon, and amdgpu, and are displayed as appropriate. Intel グラフィックスドライバが検出されると、MX Tweak > Config Options タブでチェックボックスが利用可能になり、デフォルトの「modesetting」からシステムを切り替えます。このスイッチは、Intel ドライバの TearFree オプションを有効にします。Tearfree オプションは、nouveau、radeon、amdgpu にも存在し、必要に応じて表示されます。

リンク

- [MX/antiX Wiki](#)

3.4 ネットワーク

Internet connections are handled by Network Manager: インターネット接続は Network Manager によって処理される:

--Left-click the applet in the Systray Notification Area to see status, connect and explore options. Systray の通知領域でアプレットを左クリックすると、ステータス、接続、オプションの検索ができます。

--Right-click the applet > Edit Connections to open up a Settings box with five tabs. KDE: right-click will bring up Configure Network Connections. Click that to open the Settings box. アプレットを右クリック > 接続の編集 で 5 つのタブがある設定ボックスが開きます。

KDE: 右クリックすると Configure Network Connections が表示されます。これをクリックすると設定ボックスが開きます。

- Wired. In most situations this requires no attention; highlight and click the Edit button for special setups. ワイヤード。特殊な設定の場合は、ハイライトして Edit ボタンをクリックします。
- Wireless ワイヤレス
 - Network Manager will usually automatically detect your network card and use it to find available access points. Network Manager は通常、ネットワークカードを自動的に検出し、それを使って利用可能なアクセスポイントを探します。
 - For details, see Section 3.4.2 below. 詳細は 3.4.2 項を参照。
- Mobile Broadband (Xfce only). This tab allows you to use a 3G/4G mobile device for access to the web. Click the Add button to set up. モバイルブロードバンド(Xfce のみ)。このタブでは、3G/4G モバイルデバイスを使用してウェブにアクセスすることができます。追加ボタンをクリックして設定します。
- VPN. Click the Add button to set up. If you experience setup problems, consult [the MX/antiX Wiki](#). VPNAAdd ボタンをクリックしてセットアップします。セットアップに問題が発生した場合は、MX/antiX Wiki を参照してください。
- DSL (Xfce only). Click the Add button to set up. DSL (Xfce のみ)。追加ボタンをクリックして設定します。

もっと見る: [Ubuntu Wiki: Network Manager](#)

3.4.1 有線アクセス

MX Linux typically picks up wired internet access upon boot without much problem. If a Broadcom driver is required (rare), then use MX Network Assistant (Section 3.2). MX Linux は通常、起動時に有線インターネットアクセスを問題なく検出します。Broadcom ドライバが必要な場合は(まれですが)、MX Network Assistant を使用してください(セクション 3.2)。

Ethernet and cable イーサネットとケーブル

MX Linux comes preconfigured for a standard LAN (Local Area Network) that uses DHCP (Dynamic Host Configuration Protocol) to assign IP addresses and DNS (Domain Name System) resolution. This will work in most cases as-is. You can change the configuration with Network

Manager (KDE: Network Interfaces).MX Linux は、DHCP(ダイナミック・ホスト・コンフィギュレーション・プロトコル)を使用して IP アドレスと DNS(ドメイン・ネーム・システム)を割り当てる標準的な LAN(ローカル・エリア・ネットワーク)用にあらかじめ設定されています。ほとんどの場合、このままで動作します。Network Manager (KDE: Network Interfaces) で設定を変更できます。

When you boot MX Linux, your Network Adapters are assigned a short interface name by udev, the Kernel's Device Manager. For normal wired adapters this is usually eth0 (with subsequent adapters eth1, eth2, eth3, etc). USB adapters often come up on the eth0 interface in MX Linux, but the interface name can also depend on the adapter's chipset. For instance, Atheros cards often show up as ath0, while ralink usb adapters may be rausb0. For more a detailed list of all found network interfaces, open a terminal, become root, and enter: `ifp -a`. MX Linux を起動すると、カーネルのデバイス・マネージャーである udev によって、ネットワーク・アダプターに短いインターフェース名が割り当てられます。通常の有線アダプタの場合、これは通常 eth0(後続のアダプタは eth1、eth2、eth3 など)です。USB アダプタは MX Linux の eth0 インターフェイスに表示されることが多いですが、インターフェイス名はアダプタのチップセットにも依存します。例えば、Atheros カードはしばしば ath0 と表示され、ralink usb アダプタは rausb0 と表示されます。見つかったネットワークインターフェースの詳細リストについては、ターミナルを開いて root になり、`ifp -a` を 入力してください。

It is wise to connect to the Internet through a Router, as nearly all wired Routers contain optional Firewalls. In addition, routers use NAT (Network Address Translation) to translate from big Internet addresses to local IP addresses. This affords another layer of protection. Connect to the Router directly, or through a Hub or Switch, and your machine should Autoconfigure via DHCP. ほぼすべての有線ルーターにはオプションでファイアウォールが搭載されているため、ルーター経由でインターネットに接続するのが賢明です。さらに、ルーターは NAT(ネットワークアドレス変換)を使って、大きなインターネットアドレスからローカル IP アドレスに変換します。これにより、もう1つの保護層ができます。ルーターに直接、またはハブやスイッチを介して接続すると、マシンは DHCP 経由で自動設定されます。

ADSL または PPPoE (Xfce のみ)

If you use ADSL or PPPoE, connecting to the internet is easy in MX Linux. Right-click the Network Manager icon, then the DSL tab. Click the Add... button and fill in the required information, checking to connect automatically if you want. ADSL または PPPoE を使用している場合、MX Linux でインターネットに接続するのは簡単です。Network Manager アイコンを右クリックし、DSL タブをクリックします。Add...]ボタンをクリックし、必要な情報を入力します。

NOTE: if you encounter problems when using a USB device to connect, plug the unit into the computer, open a terminal and type: `dmesg | tail` 注:USB デバイスを使用して接続する際に問題が発生した場合は、本機をコンピューターに接続し、ターミナルを開いてタイプしてください:

```
dmesg | tail
```

Post the output on the MX Linux Forum with to get some help in finding the driver you need. 必要なドライバを見つける手助けを得るために、MX Linux フォーラムに出力を投稿してください。



Figure 3-34: Setting up DSL service. 図 3-34 : DSL サービスの設定

Dial-Up Internet ダイヤルアップインターネット

On the Device tab you will need to set up the serial information. Accepting the default /dev/modem may work, but you might need to try another interface. These are the Linux equivalents of the COM Ports under Windows: デバイスタブでシリアル情報を設定する必要があります。デフォルトの/dev/modem は動作するかもしれないが、他のインターフェースを試す必要があるかもしれない。これらは、Windows の COM ポートに相当するものです:

Table 3: Linux equivalents for COM Ports. 表 3 : COM ポートに相当する Linux。

ポート	等価
COM 1	/dev/ttys0
COM 2	/dev/ttys1
COM 3	/dev/ttys2
COM 4	/dev/ttys3

3.4.2 無線アクセス

MX Linux comes preconfigured to autodetect a WiFi card, and in most cases your card will be found and set up automatically. MX Linux は WiFi カードを自動検出するようにあらかじめ設定されており、ほとんどの場合、カードは自動的に検出され、セットアップされる。

A native driver usually comes as part of the Linux kernel (example: ipw3945 for Intel), but on some, especially newer machines it may be necessary to download a driver using the information

in Quick System Info > Network. ネイティブドライバは通常、Linux カーネルの一部として提供されています(例: Intel の ipw3945)が、一部のマシン(特に新しいマシン)では、Quick System Info > Network の情報を使ってドライバをダウンロードする必要があるかもしれません。

Sometimes there are multiple drivers available. You may want to compare them for speed and connectivity, and you may have to blacklist or remove the one you are not using to prevent a conflict. Wireless cards can be either internal or external. USB modems (wireless dongles) usually show up on the wlan interface, but if not then check others on the list.複数のドライバが利用可能な場合もあります。速度や接続性を比較し、競合を防ぐために使用していないものをブラックリストに入れたり削除したりする必要があるかもしれません。ワイヤレスカードには内蔵型と外付け型があります。USB モデム(ワイヤレスドングル)は通常 wlan インターフェースに表示されますが、表示されない場合はリストにある他のものをチェックしてください。

NOTE: The successful method varies for users because of the complicated interactions among the Linux kernel, wireless tools, and the local wireless card chipset and router. 注:Linux カーネル、ワイヤレスツール、ローカルワイヤレスカードチップセットとルーター間の複雑な相互作用のため、成功する方法はユーザーによって異なります。

Basic Wireless Steps ワイヤレスの基本ステップ

Click **Start menu** > **Settings** > **Network Connections** (KDE: Start Menu > Connections), or just click on the Network Manager icon in the Notification Area), and then the Wireless tab. One of 3 situations will arise. スタートメニュー>設定>ネットワーク接続(KDE:スタートメニュー>接続)、または通知領域のネットワークマネージャーアイコンをクリック)、そしてワイヤレスタブをクリックします。3つの状況のいずれかが発生します。

-**A wireless network has been found.** ワイヤレスネットワークが見つかりました。

- Click on the name of the network to use it. ネットワーク名をクリックすると利用できます。
 - Right-click the icon to access further options. アイコンを右クリックすると、その他のオプションにアクセスできます。
 - When done, click OK. 完了したら、OK をクリックする。

-**The found network does not function.** 見つかったネットワークは機能していない。

If wireless networks are seen but your computer cannot connect them, this means that either 1) the wireless card is managed correctly by the right driver but you have problems concerning the connection to your modem/router, the firewall, the provider, DNS, etc.; or 2) the wireless card is managed abnormally because the driver is not the most appropriate for that card or there are problems of conflict with another driver. In this case you should gather information on your wireless card to see if the card drivers may have problems and then try to test the network with a set of diagnostic tools. ワイヤレスネットワークは見えるが、コンピュータが接続できない場合、1)

ワイヤレスカードは正しいドライバで正しく管理されているが、モデム/ルーター、ファイアウォール、プロバイダー、DNS などへの接続に問題がある、2)ドライバがそのカードに最適でない、または他のドライバとの競合の問題があるため、ワイヤレスカードが異常に管理されている、のいずれかを意味します。この場合、ワイヤレスカードに関する情報を収集し、カードドライバに問題があるかどうかを確認し、診断ツールを使ってネットワークをテストしてみてください。

- Find out basic information by opening a terminal and entering one at a time: ターミナルを開き、1つずつ入力することで基本情報を調べる:

```
inxi -n
```

```
lsusb | grep -i net
```

```
lspci | grep -i net
```

And as root:

```
iwconfig
```

The output from these commands will give you the name, model and version (if any) of your wireless card (example below), as well as the associated driver and the mac address of the wireless card. The output of the fourth will give you the name of the Access Point (AP) you are linked to and other connection information. For example: これらのコマンドの出力は、ワイヤレスカードの名前、モデル、バージョン(もしあれば)(下の例)、関連するドライバ、ワイヤレスカードの mac アドレスを示します。4番目の出力は、リンクしているアクセスポイント(AP)の名前とその他の接続情報を表示します。例えば:

Network

```
Card-2:Qualcomm Atheros AR9462 Wireless Network Adapter driver: ath9k  
IF: wlan0 state: up mac: 00:21:6a:81:8c:5a
```

Sometimes you need the MAC number of the chipset in addition to that of your wireless card. The easiest way to do that is to click **Start menu > System > MX Network Assistant**, Introduction tab. For example: ワイヤレスカードの MAC 番号だけでなく、チップセットの MAC 番号も必要な場合があります。これを行う最も簡単な方法は、スタートメニュー > システム > MX ネットワークアシスタントの「はじめに」タブをクリックすることです。例えば:

```
Qualcomm Atheros AR9485 Wireless Network Adapter [168c:0032](rev 01)
```

The number in brackets identifies the type of chipset in your wireless card. The numbers before the colon identify the manufacturer, those after it the product. 括弧内の数字はワイヤレスカードのチップセットの種類を示します。コロンの前の数字は製造元、後の数字は製品を示します。

Use the information you have gathered in one of the following ways: 収集した情報は、以下のいずれかの方法で使用する:

- Do a web search using that information. Some examples using the above lspci output.
その情報を用いてウェブ検索してください。上記の lspci 出力を使ったいくつかの例。

```
linux Qualcomm Atheros AR9462
linux 168c:0032
debian stable 0x168c 0x0034
```

- Consult the Linux Wireless and the Linux Wireless LAN Support sites below to find out which driver your chipset needs, what conflicts might exist, and whether it needs firmware installed separately. Post your information on the MX Linux Forum and ask for help. 以下の Linux Wireless と Linux Wireless LAN Support のサイトで、お使いのチップセットに必要なドライバ、コンフリクトの有無、ファームウェアを別途インストールする必要があるかどうかを確認してください。MX Linux フォーラムに情報を投稿し、助けを求めてください。
- Turn off the Firewall, if any, until the linkage occurs between computer and Router. ファイアウォールがある場合は、コンピュータとルータの間でリンクが確立するまでファイアウォールをオフにします。
- Try restarting the Router. ルーターを再起動してみてください。
- Use the Diagnostic Section in MX Network Assistant to Ping your Router using the MAC address, Ping to any website such as Google or run [traceroute](#). If you can Ping a site using its IP (gotten from a web search) but you can not reach it with its domain name, then the problem may be in the configuration of the DNS. If you don't know to interpret the results of Ping and traceroute do a web search or post the results on the MX Linux Forum. MX ネットワークアシスタントの診断セクションを使用して、MAC アドレスを使用してルーターに Ping を送信するか、Google などのウェブサイトに Ping を送信するか、traceroute を実行します。Web 検索で取得した)IP を使用して Ping を送信することができても、ドメイン名を使用してサイトに到達できない場合は、DNS の設定に問題がある可能性があります。Ping と traceroute の結果の解釈がわからない場合は、ウェブ検索をするか、MX Linux フォーラムに結果を投稿してください。
- Sometimes using the terminal application **Ceni** (in the repos) can reveal hidden access points and other difficult factors. **NOTE:** using Ceni to configure your Network Interface in MX Linux will interfere and/or disable management of that interface by the default Network Manager. Ceni stores its configuration info in /etc/network/interfaces. Any interface defined in /etc/network/interfaces will be ignored by Network Manager, as Network Manager assumes that if a definition exists, you want some other application managing the device. ターミナルアプリケーションの Ceni(レポジトリにあります)を使うと、隠れたアクセスポイントや他の難しい要素がわかることがあります。注意: MX Linux でネットワークインターフェースを設定するために Ceni を使用すると、デフォルトのネットワークマネージャによるインターフェースの管理が妨害されたり、無効になったりします。Ceni は /etc/network/interfaces に設定情報を保存します。etc/network/interfaces で定義されたインターフェイスは、Network Manager によって無視されます。Network Manager は、定義が存在する場合、他のアプリケーションでデバイスを管理することを想定しているからです。

-No wireless interface is found. ワイヤレスインターフェースが見つかりません。

- Open a terminal and type the 4 commands listed at the beginning of the previous section. Identify the card, chipset and driver you need by doing a web search and consulting the sites reported, according to the procedure described above. ターミナルを開き、前節の冒頭に挙げた4つのコマンドを入力する。上記の手順に従って、ウェブ検索を行い、報告されているサイトを参照して、必要なカード、チップセット、ドライバーを特定する。
 - Look for the network entry, and note the detailed information on your specific hardware, and look for more information about that from the LinuxWireless site listed below, or ask on the Forum. ネットワークエントリを探し、あなたの特定のハードウェアの詳細情報をメモし、それに関する詳細情報を下記のLinuxWireless サイトから探すか、フォーラムで尋ねてください。
 - If you have an external wifi device and no information on a network card is found, unplug the device, wait a few seconds then plug it back in. Open a terminal and enter: 外付けの無線 LAN デバイスを使用していて、ネットワークカードの情報が見つからない場合は、デバイスのプラグを抜き、数秒待ってから再び差し込んでください。ターミナルを開いて入力します:

```
dmesg | tail
```

Examine the output for information about the device (such as the mac address) that you can use to pursue your issue on the web or the MX Linux Forum. デバイスに関する情報(mac アドレスなど)の出力を調べ、ウェブや MX Linux フォーラムで問題を解決するために使用します。

- A common example of this situation arising is with **Broadcom wireless chipsets**; see the [MX/antiX Wiki](#). このような状況が発生する一般的な例としては、Broadcom ワイヤレスチップセットがある。

Firmware ファームウェア

For some cards it is necessary to install firmware (for example, **firmware-ti-connectivity** for Texas Instruments WL1251). MX Linux comes with a good deal of firmware already available, either installed or in the repos, but you may have to track down your particular need or check the MX linux Support Forum. カードによっては、ファームウェアをインストールする必要があります(例えば、Texas Instruments WL1251 用の firmware-ti-connectivity)。MX Linux には、多くのファームウェアが用意されています。すでにインストールされているか、レポにあるかのどちらかですが、あなたの特定のニーズを探し出すか、MX linux サポートフォーラムをチェックする必要があるかもしれません。

Security セキュリティ

Wireless Security is handled by Network Manager. Here are the basic steps you need to follow (steps are similar in KDE with minor differences in terminology and location that are obvious):
ワイヤレスセキュリティは Network Manager によって処理されます。以下は基本的な手順です (KDE でも同じような手順がありますが、用語や場所が微妙に異なります):

- Right-click the Network Manager icon in the Notification Area > Edit connections (KDE: Configure Network Connections). 通知領域のネットワークマネージャーアイコンを右クリック > 接続を編集(KDE: Configure Network Connections)。
- Click on the Wireless tab, and highlight the name of the access point you want to connect to (for example, “linksys” or “starbucks 2345”). ワイヤレス]タブをクリックし、接続したいアクセスポイント名をハイライトします(例:"linksys "または "starbucks 2345")。
- Click the Edit button and then the Wireless Security tab. 編集ボタンをクリックし、ワイヤレスセキュリティタブをクリックします。
- Use the pull-down menu to select the security you want (for example: WPA and WPA2 Personal). プルダウンメニューを使用して、必要なセキュリティを選択します(例: WPA および WPA2 パーソナル)。
- Enter the password and click Save. パスワードを入力し、「保存」をクリックします。




Figure 3-35: Wireless security in Network Manager (Left: Xfce, Right: KDE/Plasma). 図 3-35 : Network Manager のワイヤレスセキュリティ(左: Xfce 、右: KDE/Plasma)。

It is equally possible to use **Ceni** to handle wireless security, as long as subsequently you will not be using Network Manager, with which it interferes. Ceni をワイヤレス・セキュリティの処理に使うことも、Network Manager と干渉しない限り、同様に可能だ。

Links リンク

- [Linux Wireless](#)
- [Linux Wireless LAN Support](#)
- [Debian Wiki: Wifi](#)
- [Arch Wiki: Wireless](#)

3.4.3 モバイルブロードバンド

For wireless internet access using a 3G/4G modem, please refer to the Debian Wiki's 3G pages linked below for compatibility information. Many 3G/4G modems will be recognized on MX Linux by Network Manager. 3G/4G モデムを使ったワイヤレスインターネットアクセスについては、以下にリンクされている Debian Wiki の 3G ページで互換性情報を参照してください。多くの 3G/4G モデムは MX Linux 上で Network Manager により認識されます。

3.4.4 テザリング

Tethering refers to the use of a device like a mobile phone or mobile WiFi HotSpot to provide mobile internet access to other devices, such as a laptop. A "HotSpot" needs to be created on the device with access for the other device to use. It is easy to set up an Android phone as a HotSpot : Settings > Connections > Mobile Hotspot and Tethering > Mobile Hotspot. To make the laptop the Hotspot, consult [this video](#). テザリングとは、携帯電話やモバイル WiFi HotSpot などのデバイスを使用して、ノートパソコンなどの他のデバイスにモバイルインターネットアクセスを提供することです。HotSpot "は、他のデバイスが使用できるように、アクセス可能なデバイス上に作成する必要があります。Android 携帯を HotSpot として設定するのは簡単です: 設定>接続>モバイルホットスポットとテザリング>モバイルホットスポット。ノートパソコンをホットスポットにするには、こちらのビデオを参照してください。

Troubleshooting トラブルシューティング

On some systems, modem connections fail due to an upgrade of the packages **udev** and **libudev1**. To solve this, open Synaptic, highlight the packages, and then click Package> Force version... Use the pull-down menu to drop to a lower version and click the Apply icon. システムによっては、udev と libudev1 パッケージのアップグレードが原因で、モデム接続に失敗することがあります。これを解決するには、Synaptic を開いてパッケージをハイライトし、Package> Force version...をクリックします。プルダウンメニューを使って低いバージョンに落とし、適用アイコンをクリックします。

In some cases this solution has not worked consistently for users, but they have found that the complete removal of **Network Manager** solved the problems. この解決策が一貫して機能しなかったユーザーもいますが、Network Manager を完全に削除することで問題が解決したケースもあります。

もっと見る: [Debian Wiki: 3G モデム](#)

3.4.5 コマンドラインユーティリティ

Command line utilities are useful for seeing detailed information, and are also commonly used in troubleshooting. Detailed documentation is available in the man pages. The most common ones below must be run as root. コマンドラインユーティリティは詳細な情報を見るのに便利で、トラブルシューティングにもよく使われる。詳細なドキュメントは man ページにあります。以下の最も一般的なものは、root で実行する必要があります。

Table 4: Wireless Utilities. 表 4:ワイヤレス・ユーティリティ。

コマンド	コメント
ip	ネットワーク・インターフェースの主な設定ユーティリティ。
ifup <インターフェース>	指定したインターフェイスを表示する。例えば： ifup eth0 はイーサネットポート eth0 を表示する。
ifdown <インターフェース>	ifup の逆
iwconfig	ワイヤレスネットワーク接続ユーティリティ。単体で使用し、ワイヤレスステータスを表示します。特定のアクセスポイントを選択するなど、特定のインターフェースに適用可能
rkill	ワイヤレスネットワーク・インターフェース(wlanなど)のソフトブロックを無効にする。
depmod -a	すべてのモジュールを調べて、変更されていれば、新しい設定を有効にする。

3.4.5 スタティック DNS

It is sometimes desirable to change your Internet setup from the default automatic **DNS** (Dynamic Name Service) configuration to a manual static one. Reasons for doing this may include greater stability, better speed, parental control, etc. You can make such a change either for the whole system or for individual devices. In either case, get the static DNS settings you are going to use from OpenDNS, Google Public DNS, etc., before you start. インターネットの設定を、デフォルトの自動 DNS(ダイナミック・ネーム・サービス)設定から、手動のスタティック(静的)設定に変更することが望ましい場合があります。その理由には、安定性の向上、スピードの向上、ペアレンタルコントロールなどがあります。このような変更は、システム全体または個々のデバイスに対して行うことができます。いずれの場合も、事前に OpenDNS や Google Public DNS などから、使用するスタティック DNS 設定を取得してください。

System wide DNS システム全体の DNS

You can make the change for everyone using your Router using a browser. You will need: ブラウザを使用して、ルーターを使用しているすべての人に変更を加えることができます。必要なものは以下の通りです:

- the Router's URL (list [here](#) if you have forgotten). ルーターの URL(忘れた場合はここにリストアップしてください)。
- its password, if you set one. パスワードを設定した場合は、そのパスワード。

Find and change your Router's Configuration Panel, following the directions for your particular router (list of guides [here](#)). ルーターの設定パネルを探し、各ルーターの指示に従って変更します(ガイドの一覧はこちら)。

個別の DNS

For single user change, you can use Network Manager. 単一ユーザーの変更には、Network Manager を使用できます。

- Right-click the connection icon in the Notification Area > Edit connections... 通知領域で接続アイコンを右クリック > 接続を編集...
- Highlight your connection and click the Edit button. 接続をハイライトし、編集ボタンをクリックします。
- On the IPv4 tab, use the pull-down menu to change the Method to “Automatic (DHCP) addresses only”. IPv4 タブで、プルダウンメニューを使用して「方法」を「自動(DHCP)アドレスのみ」に変更します。
- In the box for “DNS Servers” enter the static DNS settings you are going to use. DNS Servers "のボックスに、使用するスタティック DNS 設定を入力する。

- Click Save to exit. 「保存」をクリックして終了します。

3.5 ファイル管理

File management in MX Linux is carried out through Thunar on Xfce and Dolphin on KDE / Plasma. Much of their basic use is self-evident, but here are good things to know: MX Linux のファイル管理は、Xfce の Thunar と KDE / Plasma の Dolphin で行います。基本的な使い方は自明ですが、知っておくと良いことがあります:

- Hidden files are out of sight by default, but can be made visible via the menu (View > Show Hidden Files); or by pressing Ctrl-H. 隠しファイルはデフォルトでは表示されませんが、メニュー(表示 > 隠しファイルを表示)、または Ctrl-H キーを押すことで表示させることができます。
- The Side Pane can be hidden, and directory (folder) shortcuts can be placed there by right-clicking > Send To (KDE: Add to Places) or drag-and-drop. サイドペインは非表示にすることができ、ディレクトリ(フォルダ)のショートカットは、右クリック > Send To(KDE:場所に追加)またはドラッグ&ドロップでそこに配置することができます。
- The context menu has been populated with common procedures (“Custom Actions” on Xfce and “Actions” & “Root Actions” on KDE / Plasma) that vary by what is present or under focus. コンテキストメニューには、共通の手順(Xfce では "Custom Actions"、KDE / Plasma では "Actions" と "Root Actions")が追加されました。
- Root action is available via the context menu to open a terminal, edit as root, or open an instance of File Manager with root privileges. root アクションは、コンテキストメニューからターミナルを開いたり、root 権限で編集したり、root 権限でファイルマネージャーのインスタンスを開いたりすることができます。
- The File Managers easily handle FTP transfers, see below. ファイルマネージャーは FTP 転送を簡単に処理できます。
- Custom Actions greatly increase the power and utility of the File Managers. MX Linux comes with many pre-installed, but there are others available to copy and the individual can create them for individual needs. See Tips and Tricks (Section 3.5.1), below; and [the MX/antiX Wiki](#). カスタムアクションはファイルマネージャーのパワーとユーティリティを大幅に向上させます。MX Linux には多くのカスタムアクションがプリインストールされています。下記の Tips and Tricks(セクション 3.5.1)、および MX/antiX Wiki を参照してください。




Figure 3-36: Left: Custom actions set up in Thunar. Right: Custom Services in Dolphin. 図 3-36 :左: Thunar で設定したカスタムアクション。右: Dolphin のカスタムサービス

3.5.1 ヒントとコツ

- When working in a directory that requires superuser privileges, you can right-click > Open root Thunar here (or File > Open root Thunar here) or the similar “Root Action” in Dolphin. スーパーユーザー権限が必要なディレクトリで作業する場合は、右クリック> Open root Thunar here(または File>Open root Thunar here)、または Dolphin の同様の「Root Action」を使用します。
- Superuser privilege can be changed in MX Tweak > Other tab from using either the user’s password (default) or an administrative password, if one has been set up. スーパーユーザー権限は、MX Tweak > Other タブで、ユーザーのパスワード(デフォルト)または管理者パスワード(設定されている場合)のいずれかを使用して変更することができます。
- You can set up tabs with File > New Tab (or Ctrl-T), then move items from one location to another by dragging them to a tab and releasing it. ファイル>新規タブ(または Ctrl-T)でタブを設定し、アイテムをタブにドラッグして離すことで、ある場所から別の場所に移動できる。
- You can split the screen and navigate to another directory in one of the panels. Then move or copy files from one to the other. 画面を分割し、パネルの片方で別のディレクトリに移動することができます。その後、一方から他方へファイルを移動またはコピーします。

- In Xfce 4.18 and later, you can set up a multiple-tab view by default; it's easiest to use MX Tweak > Config Options tab for this purpose. Xfce 4.18 以降では、デフォルトで複数のタブ表示を設定できます。この目的のためには、MX Tweak > Config Options タブを使うのが最も簡単です。

You can assign a keyboard shortcut key to the Custom Action “Open terminal here.” カスタムアクションの “Open terminal here” にキーボードショートカットキーを割り当てることができます。

■ Thunar/Xfce

- Enable editable accelerators in All Settings > Appearance > Settings. すべての設定] > [外観] > [設定] で、編集可能なアクセラレータを有効にします。
- In Thunar, hover your mouse over the File > Open in Terminal menu item and press the keyboard combination that you would like to use for that action. Thunar のメニュー「ファイル」>「ターミナルで開く」にマウスカーソルを合わせ、その操作に使いたいキーボードの組み合わせを押します。
- Then when browsing in Thunar, use the keyboard combination to open a terminal window in your active directory. そして、Thunar でブラウズするときに、キーボードの組み合わせを使ってアクティブ・ディレクトリのターミナル・ウィンドウを開く。
- This applies equally to other items on Thunar’s File menu; for instance, you could assign Alt-S to create a symlink for a highlighted file, etc. これは Thunar の File メニューの他の項目にも同様に適用される。例えば、Alt-S を割り当てて、ハイライトされたファイルのシンボリックリンクを作成する、など。
- Actions listed in the context menu can be edited/deleted, and new ones added, by clicking Edit > Configure custom actions... コンテキストメニューに表示されているアクションは、[編集]> [カスタムアクションを設定...]をクリックして編集/削除したり、新しいアクションを追加したりできます。
- Dolphin / KDE Plasma: select Settings > Configure Keyboard Shortcuts and find Terminal entry. [設定] > [キーボードショートカットを設定] を選択し、端末エントリを見つけます。
- Various options and hidden commands are also visible, see Links below. さまざまなオプションや隠しコマンドも表示される。
- Both Java and Python are sometimes used to produce applications, carrying the ending *.jar and *.py, respectively. These files can be opened with a single click, like any other file; no more need to open a terminal, figure out what the command is, etc. **CAUTION:**

be careful of potential security issues. Java と Python の両方がアプリケーションの制作に使われることもある。それぞれ *.jar と *.py です。これらのファイルは、他のファイルと同じようにワンクリックで開くことができます。ターミナルを開いたり、コマンドの意味を調べたりする必要はありません。注意:潜在的なセキュリティ問題に注意してください。

- Compressed files (zip, tar, gz, xz, etc...) can be managed by a right-click on the file. 圧縮ファイル(zip, tar, gz, xz など)は、ファイルを右クリックして管理できます。

- To find files: ファイルを探す

--Thunar/Xfce: open Thunar and right-click any folder > Find files here. A dialog box will pop up to give you options. Running in the background is Catfish (Start menu > Accessories > Catfish). --Thunar/Xfce: Thunar を開き、任意のフォルダを右クリック > Find files here. ダイアログボックスがポップアップしてオプションが表示される。バックグラウンドで動作しているのは Catfish です(スタートメニュー > アクセサリ > Catfish)。

--Dolphin / KDE Plasma: Use Edit > Search in the Dolphin toolbar. --Dolphin / KDE Plasma:Dolphin ツールバーの Edit > Search を使用してください。

- Links/Symlinks リンク/シムリンク

--Thunar/Xfce: To set up a soft link (AKA symlink)--a file that points to another file or directory--right-click the target (file or folder you want the link to point to) > Create Symlink. Then drag (or right-click, cut and paste) the new Symlink to where you want it. --Thunar/Xfce: ソフトリンク(別名シンボリックリンク)--別のファイルやディレクトリを指すファイル--を設定するには、ターゲット(リンクを指すファイルやフォルダ)を右クリック > Symlink を作成します。次に、新しいシンボリックリンクを必要な場所にドラッグ(または右クリック、カット&ペースト)します。

--Dolphin / KDE Plasma: Right click on an empty spot in the Dolphin window and use Create New > Basic link to file or directory. --Dolphin / KDE Plasma:Dolphin ウィンドウの何もない場所で右クリックし、Create New > Basic link to file or directory を実行してください。

- Thunar custom actions. This is a powerful tool to expand the file manager's functions. To see the ones that are predefined during MX Linux development, click Edit > Configure Custom Actions. The dialogue box that pops up will show you what is predefined and give you an idea of what you can do yourself. To create a new Custom Action, click on the “+” button on the right. Details in [the MX/antiX wiki](#). Thunar カスタムアクション。これはファイルマネージャーの機能を拡張する強力なツールです。MX Linux 開発中に定義済みのものを見るには、[Edit] > [Configure Custom Actions]をクリックしてください。ダイアログボックスがポップアップ表示され、定義済みのアクションが表示されます。新しいカ

スタムアクションを作成するには、右側の "+"ボタンをクリックします。詳細は MX/antiX wiki をご覧ください。

- Folders can be displayed with images by placing an image that ends in *.jpg or *.png into the folder and renaming it “folder” フォルダは、*.jpg または*.png で終わる画像をフォルダに配置し、“フォルダ ”という名前に変更することで、画像と一緒に表示することができます。




Figure 3-37: using images to label folders. 図 3-37 : 画像を使ってフォルダにラベルを付ける。

3.5.2 FTP




Figure 3-38: Using Thunar to access an FTP site. 図 3-38 : Thunar を使って FTP サイトにアクセスする。

The File Sharing Protocol (FTP) is used to transfer files from one host to another host over a network. ファイル共有プロトコル(FTP)は、ネットワークを介してあるホストから別のホストにファイルを転送するために使用される。

Xfce FTP

- Open Thunar File Manager and click on Browse Network at the bottom of the left pane. Then click the Address bar at the top of the browser (or use Cntrl+L) and backspace to Thunar File Manager を開き、左ペインの下部にある Browse Network をクリックします。次に、ブラウザ上部のアドレスバーをクリックし(または Cntrl+L を使用)、バックスペースで
- Backspace in the address field to delete what is there (network://), then type the server name with the **ftp://** prefix. For example, to reach the MX documentation (if you have permission) you would enter this address: **ftp://mxlinux.org** アドレス・フィールドでバックスペースを押して、そこにあるもの(network://)を削除し、ftp:// プレフィックスを付けてサーバー名を入力します。例えば、MX ドキュメントにアクセスするには(権限があれば)、次のアドレスを入力 します: **ftp://mxlinux.org**
- Up pops an authorization dialog box. Fill in username and password, and let it save password if you are comfortable with that. 認証ダイアログボックスがポップアップします。ユーザー名とパスワードを入力し、パスワードの保存を許可してください。
- That's it. Once you have navigated to the folder you are always going to use, you can right-click the folder and in Thunar > Send to > Side Pane to create a very simple way to connect. これだけです。いつも使うフォルダに移動したら、そのフォルダを右クリックし、Thunar > Send to > Side Pane で、非常にシンプルな接続方法を作成できます。

KDE FTP

- Consult [the KDE userbase](#). KDE のユーザベースを参照してください。

Dedicated FTP applications such as Filezilla can be used as well. For a discussion of how FTP works, see [this page](#). Filezilla のような専用のFTP アプリケーションも使用できます。FTP の仕組みについては、こちらのページをご覧ください。

3.5.3 ファイル共有

There are various possibilities to share files between computers or between a computer and a device コンピュータ間、またはコンピュータとデバイス間でファイルを共有するには、さまざまな可能性があります。

- Samba. SAMBA is the most complete solution to share files with Windows machines on your network without making changes to the Windows machines. SAMBA can also be used by many network media players and Network-attached storage (NAS) devices. SAMBA offers some other services for interfacing with Windows networks, such as domain authentication, messaging services, and NETBIOS name resolution. For details, see below.
- NFS. This is the standard Unix protocol for sharing files. Many feel it is better than Samba for sharing files, and it can be used with Windows (2000 & XP) machines if you install “Services for Unix” or a third-party NFS client on them. Details: see [MX/antiX Wiki](#).
- Bluetooth: For file exchange, install **blueman** from the repos, reboot, pair with the device, then right-click the Bluetooth icon in the Notification Area > Send Files to Device.

3.5.4 Shares (Samba)




Figure 3-39: Browsing network shares Left: Thunar, Right: Dolphin.

File Managers can connect to shared folders (AKA Samba Shares) on Windows, Mac, Linux computers and NAS (Network Attached Storage) devices. For printing with Samba, see Section 3.1.2.

- Click on Browse Network in the left pane to show various networks.
- Click the Network you want to see available servers. Now drill down to find what you are looking for.
- Select a Server for available Samba Shares
- Select a Samba Share to see all the available folders

- A shortcut for the selected Share will be created in the Network sidebar section
- Browsing doesn't work, especially Windows. You can direct access a remote share by using the File Manager location bar (Ctrl+L) and using smb://servername/sharename. These places are bookmarkable in the side panes.

3.5.5 Creating Shares

On MX, Samba can also be used to create Shares for other computers (Windows, Mac, Linux) to access. Creating Public Shares with **MX Samba Config** is fairly straightforward, but keep in mind that creating Samba Shares is a complex area from a configuration perspective.

3.6 Sound



VIDEO: [How to enable HDMI audio with Linux](#)

MX Linux sound depends at the kernel level on Advanced Linux Sound Architecture (ALSA), and at the user level on [PulseAudio](#). In most cases sound will work out of the box, though it may need some minor adjustment. Click on the speaker icon to mute all audio, then again to restore--if that is how Preferences are set. Place cursor over speaker icon in the Notification Area and use scroll wheel to adjust volume. See also Sections 3.6.4, 3.6.5 and 3.8.9.

3.6.1 Sound Card Set-up

If you have more than one sound card, be sure to select the one you want to adjust using the tool MX Select Sound (Section 3.2). The sound card is configured and volume of selected tracks adjusted by right-clicking the speaker icon in the Notification Area > Open Mixer. If problems persist after logging out and back in, see Troubleshooting, below.

3.6.2 Simultaneous card use

There may be times when you would like to use more than one card simultaneously; for instance, you may want to hear music both through headphones and through speakers in another location. This is not easy to do in Linux, but check the PulseAudio [FAQ](#). Also, the solutions on [this MX/antiX Wiki page](#) may work, if you are careful to adjust the card references to your own situation.

Sometimes it is necessary to switch sound cards, for instance when one is HDMI and the other analog. This can be done with Pulse Audio Volume Control > Configuration tab; be sure to select the Profile option that works for your system. To make that switch automatic, see the script on [this GitHub site](#).

3.6.3 Troubleshooting

- [Sound not working](#)
- No sound, though speaker icon is in the Notification Area.
 - Try raising all controls to a higher level. For a System Sound such as a login, use the Playback tab in PulseAudio.
 - Edit the configuration file directly: see Section 7.4.
- No sound, and no speaker icon is in the Notification Area. It could be that the sound card is missing or unrecognized, but the most common problem is that of multiple sound cards, which we address here.
 - Solution 1: click **Start menu > Settings > MX Sound Card (KDE: System Settings > Hardware > Audio)**, and follow the screen to select and test the card you want to use.
 - Solution 2: use the volume control of PulseAudio (`pavucontrol`) to select the correct sound card
 - Solution 3: enter the BIOS and turn off HDMI.
 - Check the ALSA sound card matrix listed below.

3.6.4 Sound servers

Whereas the Sound Card is a hardware item accessible to the user, the Sound Server is software that works largely in the background. It permits general management of sound cards, and provides the ability carry out advanced operations on the sound. The most commonly used by individual users is PulseAudio. This advanced open-source sound server can work with several operating systems, and is installed by default. It has its own mixer that allows the user to control the volume and destination of the sound signal. For professional use, [Jack audio](#) is perhaps the best known.




Figure 3-40: Using PulseAudio Mixer. Left: Pavucontrol Right: KDE Audio Volume.

3.6.5 Links

- [MX/antiX Wiki: Sound not working](#)
- [ALSA: SoundCard Matrix](#)
- [ArchLinux Wiki: PulseAudio Information](#)
- [PulseAudio Documentation: Free desktop](#)

3.7 Localization

MX Linux is maintained by an international Dev Team that constantly works to improve and expand the options for localization. There are many languages into which our documents have not yet been translated, and if you can help with this effort please [register on Transifex](#) and/or post on the [Translation Forum](#).

3.7.1 Installation

The primary act of localization occurs during the use of the LiveMedium USB.

- When the boot screen first comes up, make sure to use the Function Keys to set your preferences.
 - F2. Select the language.
 - F3. Select the timezone you wish to use.

- If you have a complicated or alternative setup, you can use boot cheat codes. Here is an example to set a Tartar keyboard for Russian: `lang=ru kbvar=tt`. A full list of the boot parameters (=cheat codes) can be found in the [MX/antiX Wiki](#).
- If you set the locale values at the boot screen, then Screen 7 should show them during installation. If not, or if you want to change them, select the language and timezone you want.

Two other methods are available after the boot screen.

- The first screen on the installer allows the user to select a particular keyboard for use.
- The login screen has pull-down menus in the upper right corner where both keyboard and locale can be selected.

3.7.2 Post-installation

MX Tools includes two tools for changing keyboard and locale. See Sections 3.2.15 and 3.2.16 above.

Xfce4 and KDE/Plasma have their own methods as well:




Figure 3-41: Adding another keyboard layout Left: Xfce Right: KDE.

Here are the configuration steps you can take to localize your MX Linux after installation.

To change the keyboard:

Xfce

- Click **Start Menu > Settings > Keyboard**, Layout tab.
- Uncheck “Use system defaults” then click on the **+Add** button at the bottom and select the keyboard(s) you want available.

- Exit, then click Keyboard Switcher (flag) in the Notification Area to select active keyboard.

KDE/Plasma

- Click Start Menu > Settings > System Settings > Hardware > Keyboard> Layouts Tab
- Check “Configure Layouts” in the middle of the dialog, then click on the **+Add** button at the bottom and select the keyboard(s) you want available.
- Exit, then click Keyboard Switcher (flag) in the Notification Area to select active keyboard.
- Get language packs for major applications: click **Start menu > System > MX Package Installer**, provide the root password, then click Language to find and install language packs for the applications you use.
 - Setting up Chinese Simplified Pinyin is a bit more complicated, see [here](#).
- Change time settings: (Xfce) click **Start Menu > System > MX Date & Time**, (KDE: right click time in the panel > Adjust Date and Time) and select your preferences. If you are using the digital clock Date Time, right-click > Properties to choose 12h/24h and other local settings.
- Get spellchecker to use your language: install the **aspell** or **myspell** package for your language (e.g., **myspell-es**).
- Get local weather info.
 - **Xfce**: right-click the Panel > Panel > Add New Items > Weather Update. Right-click > Properties, and set the locale you want to see (it will guess by your IP address).
 - **KDE**: Right click on the desktop or panel depending on where the widget will appear and then Add Widget. Search for Weather and add the widget
- For **Firefox, Thunderbird or LibreOffice** localization, use **MX Package Installer > Language** to install the appropriate package for your language of interest.
- You may need or want to change the localization info (default language, etc.) available to the system. To do so, open a terminal, become root and enter: *dpkg-reconfigure locales*
 - You will see a list with all the locales that you can scroll through using the up and down arrow keys.

- Enable and disable what you want (or don't want), using the space bar to make the asterisk in front of the locale appear (or disappear).
- When done, click OK to advance to the next screen.
- Use arrows to select the default language you want to use. For US users, for instance, that would typically be **en_US.UTF-8**.
- Click OK to save and exit.

MORE: [Ubuntu documentation](#)




Figure 3-42: Re-setting the default language for the installed system.

3.7.3 Further notes

- You can temporarily change the language for a particular application by entering this code in a terminal (in this example, to change to Spanish):

```
LC_ALL=es_ES.UTF8 <command to launch>
```

This will work for most apps that are localized already.

- If you have selected the wrong language during installation you can change it once on the installed desktop, use MX Locales to correct it. You can also open a terminal and enter this command:

```
sudo update-locale LANG=en_GB.UTF8
```

Obviously you would need to change the language to the one that you want to use.

- It may happen that an individual application may not have a translation in your language; unless it is an MX application, we can do nothing about that, so you should send a message to the developer.

- Some desktop files that are used to create the Start menu may be missing a comment in your language, even though the application itself does have a translation in that language; please let us know with a post in the Translation Sub-Forum that supplies the correct translation.

3.8 Customization

Modern Linux Desktops like Xfce and KDE/Plasma make it very easy to change basic function and look of a user's configuration.

- Most importantly, remember: Right-click is your friend!
- Great control is available through the (Xfce) All Settings and (KDE/Plasma) Settings, System Settings (Panel icons).
- User changes are stored in config files in the directory: `~/.config/`. These can be queried in a terminal, see [the MX/antiX Wiki](#).
- Most system-wide config files are in `/etc/skel/` or `/etc/xdg/`

MORE: [Xfce Tips and tricks](#) (PDF)

3.8.1 Default Theming

Default theming is controlled by a number of customized elements.

Xfce

- Login screen can be modified with All Settings > LightDM GTK+ Greeter Settings.
- Desktop:
 - Wallpaper: All Settings > Desktop/ or right-click the desktop > Desktop Settings. When selecting from another location, keep in mind that after using the entry "Other" you need to navigate to the folder you want, then click "Open"; only then can you select a particular file in that location.
 - All Settings > Appearance. Sets GTK Themes and Icons. Bundled settings in MX Tweak – Themes.
 - All Settings > Window Manager. Sets window border themes.

KDE/Plasma

- Login screen (modify with System Settings > Startup and Shutdown then choose Login Screen, SDDM configuration)
 - Breeze
- Desktop:
 - Wallpaper: Right-click on desktop and select “Configure Desktop and Wallpaper”
 - Appearance: Click Main menu > Settings > System Settings > Appearance
 1. Global Themes – bundled theme set combinations
 2. Plasma Style – Set theme of plasma desktop objects
 1. Application Style – Configure application elements
 2. Window decorations – Minimize, maximize and close button styles
 3. Colors, Fonts, Icons and cursors can also be configured.
 - Application menu settings
 1. Right-click on menu icon to get configuration options. Default panel is in the standard application panel

3.8.3 Panels

3.8.3.1 Xfce Panel




Figure 3-43: Preferences screen for customization of panels.

MX Linux ships by default with [Docklike Taskbar](#) (xfce4-docklike-plugin) replacing the Xfce Window Buttons used in previous MX releases. This lightweight, modern, and minimalist taskbar for Xfce provides the same functionality as Xfce Window Buttons, while also providing more advanced “dock” features.

To view docklike taskbar Properties: Ctrl + Right click any icon. Or: MX Tweak > Panel tab, click “Options” button under Docklike.

Window Buttons can be restored by right-clicking an empty space > Panel > Add New Items.

Tricks for panel customization:

- To move the panel, unlock it by right-clicking a panel > Panel > Panel Preferences.
- Use MX Tweak to change the location of the panel: vertical or horizontal, top or bottom.
- To change display mode inside the Panel setting, select from the pull down menu: Horizontal, Vertical, or Deskbar.




Figure 3-44: The docklike taskbar with icons and context menu.

- To automatically hide the panel, choose from pull down menu: Never, Always, or Intelligently (hides the panel when a window overlaps with it).
- Install new panel items by right-clicking an empty space in the panel > Panel > Add New Items. You then have 3 choices:
 - Select one of the items on the main list that pops up
 - If what you want is not there, select Launcher. Once it is in place, right-click > Properties, click the plus sign and select an item off the list that pops up.
 - If you want to add an item not on either list, then select the empty item icon below the plus sign and fill in the dialog box that pops up.
- New icons show up at the bottom of the vertical Panel; to move them, right-click > Move
- Change the look, orientation, etc. by right-clicking the panel > Panel > Panel Preferences.
- Right-click the clock plugin “Date Time” to change the format of layout, date or time. For a custom time format you need to use “strftime codes” (consult [this page](#) or open a terminal and type *man strftime*).
- Create a double row of icons in the Notification Area by right-clicking it > Properties, and decreasing Maximum icon size until it changes.
- Add or delete a panel in Panel Preferences, clicking on the plus or minus button to the right of the top panel pull-down menu.
- One-click horizontal panel installation is available from MX Tweak (Section 3.2).

MORE: [Xfce4 docs: Panel](#).

3.8.3.2 KDE/Plasma Panel




Figure 3-45: Preferences screen for customization of panels.

Tricks for panel customization:

- To move the panel, Right click on panel then Edit panel. Hover over “Screen Edge” and move to location of your choice.
- Use MX Tweak to change the location of the panel: vertical (left), top or bottom. Or use the previous method to drag to any screen edge.
- To change display mode inside the Panel, once the Edit Panel dialog is open, Choose More Options Panel Alignment > left, center or right.
- To automatically hide the panel, once Edit Panel dialog is open, click “More Settings” and select “Auto Hide”
- Install new panel items by clicking on the panel >Add Widgets. You can select the desired widget to add from the dialog.
- Create a double row of icons in the Notification Area by using the Configure Panel dialog and selecting Height to change the height of the panel. Then using MX-Tweak > Plasma tab and setting the systray icon size larger or smaller as desired to create the double row effect. You can also have the System Tray icons scale automatically with the panel height by right clicking on the tray up arrow, Configure System tray and enabling scale with panel height.
- To show all open applications, click MX Tweak, Plasma tab, and enable “Show windows from all workspaces in panel.”
-

3.8.4 Desktop



VIDEO: [Customizing the desktop](#)



VIDEO: [Things to do after installing MX Linux](#)

The default desktop (AKA wallpaper, background) can be changed in various ways:

- Right-click any image > Set as wallpaper
- If you want the wallpapers available to all users, become root and put them in the /usr/share/backgrounds folder;

- If you want to restore the default wallpaper, it is in /usr/share/backgrounds/. There are also symlinks of the MX wallpaper sets in /usr/share/wallpapers for easy KDE usage.

Many other customization options are available.

- To change the theme:
 - Xfce - **Appearance**. The default theme is an MX mx-comfort (light and dark) that has larger borders and specifies the appearance of Whisker menu. Be sure to select an icon theme that will show well, especially on the dark version.
 - KDE/Plasma – **Global Theme**– MX theme is the default. You can also set individual theme elements in Plasma Style, Application Style, Colors, Fonts, Icons and cursors.
- When necessary to make thin borders easier to grab:
 - Xfce – Use one of the “thick border” **Window Manager** themes or consult [the MX/antiX Wiki](#).
 - KDE/Plasma – In **Application Style > Window Decorations**, set the desired “Border Size” from the drop down menu provided.
- Xfce - Add standard icons such as Trash or Home to the desktop in **Desktop, Icons** tab.
- Window behavior such as switching, tiling, and zooming can be customized
 - Xfce - **Window Manager Tweaks**.
 - Window switching via Alt+Tab can be customized to use a compact list instead of traditional icons
 - Window switching via Alt+Tab can also be set to show thumbnails instead of icons or a list, but it requires turning on [compositing](#) which some older computers may have difficulty supporting. To enable, first deselect Cycle on a list list on the “Cycling” tab, then click on the “Compositor” tab and check ’Show windows preview in place of icons’ when cycling.
 - Window tiling can be accomplished by dragging a window to a corner and releasing it there..
 - If compositing is turned on, Window zooming is available by using the Alt + Mouse Wheel combination.

- KDE/Plasma – **System Settings**
 - Window tiling can be accomplished by dragging a window to a corner and releasing it there.
 - Configuration of a variety of keystroke and mouse controls can be set as desired via the **Workspace > Window Behavior** dialog.
 - Alt-tab configuration, including theme, can be done in the **Task Switcher** dialog.
- Wallpaper
 - Xfce – Use the Desktop settings to choose wallpapers. To select a different wallpaper for each Workspace, go to **Background** and uncheck the option 'Apply to all workspaces.' Then select a wallpaper and repeat the process for each workspace by dragging the dialog box to the next workspace and selecting another wallpaper.
 - KDE/plasma – right click on the Desktop and select “Configure Desktop and Wallpaper”.




Figure 3-46: Unchecked box allows different backgrounds for each workspace Left: Xfce, Right: KDE.

Conky

You can display almost any kind of information on the desktop by using Conky:

- Both Conky Manager and MX Conky are installed by default.
- When you click on MX Conky, a dialog box will pop up if there are updates available.
- Click **Start menu > Accessories** to find Conky Manager. MX Conky is part of MX Tools.
- A set of Conkies that will work out of the box is included by default. You can import other sets using the gear icon at the right end of the menu bar in Conky Manager
- Highlight each conky and hit Preview if necessary to see what it looks like.
- Check the box to select any Conky you want to use. It will be auto-installed.
- The configuration files are stored in the folder `~/.conky/` in individual theme files; they can be edited by highlighting the Conky in the list and clicking on the edit icon (pencil).




Figure 3-47: Main screen of Conky Manager showing one of the conkies available.

HELP: [MX/antiX Technical Wiki](#)

MORE: [Conky home page](#)

Pull-down terminal



VIDEO: [Customizing the drop-down terminal](#)

MX Linux ships with a very handy drop-down terminal triggered with F4. If you wish to disable it:

Xfce - **Start menu > All Settings > Keyboard**, Applications Shortcuts tab.

KDE/plasma - System Settings > Startup and Shutdown > Startup and Shutdown delete Yakuake.

The drop down terminals are very configurable.

Xfce – right click on the terminal window and select Preferences

KDE/plasma – right click in the terminal window and choose Create new profile.

3.8.5 Touchpad

Xfce - General options for the touchpad on a laptop are found by clicking Settings > Mouse and Touchpad. Systems that are more sensitive to touchpad interference have a couple of options:

- Use MX-Tweak, Other tab to change the touchpad driver.
- Install **touchpad-indicator** to see fine control of behavior.. Right-click the icon in the Notification Area to set important options such as autostart.

KDE/Plasma – touchpad options are found in System Settings > Hardware > Input Devices. There is also a touchpad widget that can be added to the Panel (right click panel > add widgets)

Detailed changes can be made manually by editing the 20-synaptics.conf file under /etc/X11/xorg.conf.d (file is just "synaptics.conf on MX-19).

3.8.6 Start Menu Customization

3.8.6.1 Xfce (“Whisker”) menu



VIDEO: [Customizing Whisker menu](#)



VIDEO: [Fun with the Whisker menu](#)

MX Linux Xfce uses by default with the Whisker Menu, though a classic menu can be easily installed by right-clicking a panel > Panel > Add New Items > Applications Menu. Whisker Menu is highly flexible.

- Right-click the menu icon > Properties to set preferences, e.g.,
 - Move categories column to be next to the Panel.
 - Change location of Search box from top to bottom.
 - Decide which action buttons you want to show.
- Favorites are easy to add: right-click any menu item > Add to Favorites.
- Simply drag and drop Favorites to arrange them as wished. Right-click any entry to sort or remove.

Menu contents can be edited in Xfce by using **Menu > Accessories > Menu editor** (menulibre). In KDE a menu editor is accessed by right clicking the menu icon and choosing **Edit Applications**.

MORE: [Whisker menu features](#)

Editing Xfce menus

Individual menu entries can be edited in a number of ways (the menu entry “desktop” files are located in `/usr/share/applications/` and can also be edited as root directly).

- **MenuLibre**
- Right-click on an entry in Whisker Menu or Application Finder and you can edit it on a user-specific basis. The context menu contains Edit and Hide (the latter can be very useful). Selecting Edit brings up a screen where you can change name, comment, command and icon.




Figure 3-48: Menu entry edit screen.

3.8.6.2 KDE/Plasma (“kicker”)

MX Linux KDE/Plasma uses the Application Launcher menu by default, although alternates are easily installable via right-click on the menu icon and choosing “Show Alternatives alternates”. “Favorite” applications are shown as icons on the left of the menu.

- Right-click the menu icon > Configure Application Menu to set preferences, e.g.,
 - Show applications as name only or Name/Description combinations.
 - Change location of Search results.
 - Show recent or often-used items.
 - Flatten menu sub levels.
- Favorites are easy to add: right-click any menu item > Show in Favorites.
- Simply drag and drop Favorites to arrange them as wished. Right-click any entry to sort.-To remove from Favorites right click the icon then Show in Favorites and deselect the appropriate Desktop or Activity.

Editing KDE menus

Menu entries can be edited via Right-click on an entry in the menu and you can edit a launcher on a user-specific basis. The menu entry “desktop” files are located in `/usr/share/applications/` and can also be edited as root directly.




Figure 3-49: Menu entry edit screen

(Plasma).

3.8.7 Login Greeter

The user has a number of tools to customize the Login Greeter. Xfce ISOs use the Lightdm Greeter, while KDE/Plasma ISOs use SDDM.

Lightdm




Figure 3-50: the Lightdm configuration app.

- Click **Start menu > Settings > All Settings > LightDM GTK+ Greeter settings** to adjust position, background, font, etc.
- Autologin can be (in)activated from MX User Manager, Options tab.
- Some properties of the default login box are set in the code for the selected theme. Change theme for greater choice.
- You can have the login greeter show an image as follows:
 - **Start menu > Settings > About Me (Mugshot)**
 - Fill in details you want to add.
 - Click on the icon, navigate to the image you want to use.
 - Close
 - **Manual**
 - Create or select an image, and use **nomacs** or another photo editor to resize it to about 96x96 pixels
 - Save that image in your home folder as **.face** (make sure to include the dot and do not add any extension such as jpg or png).
 - Click All Settings > LightDM GTK+ Greeter Settings, Appearance tab: turn on the User image switch.
 - Whichever way you choose, log out, and you will see the image next to the login box; it will also show up in Whisker menu once you are logged back in.

SDDM




Figure 3-51: the SDDM configuration app.

- The SDDM settings are all in Plasma desktop's System Settings. A shortcut launcher for System Settings can be found on MX's default panel, or you can in any case search for it in the Applications Menu. In the Settings, go to Startup and Shutdown >> Login Screen (SDDM).
- The settings page for SDDM will allow you to:
 - select between different themes if you have more than one installed;
 - choose to customize a background for your selected theme;
 - remove (ie delete) an installed theme; and

- to get/install new themes either directly from KDE Store online or from a file on your storage drive/media (see below)
- root password required – since desktop manager is a system program, any changes to it or its configuration will affect files in the root partition, which is why you will be asked for your root password.
- background selection – you can change the background of your selected SDDM theme. Some themes come with their own preinstalled default background picture which will be displayed if you do not make any changes. This will also require root password.
- New SDDM themes can be found [in the KDE Store](#). You can also browse the themes directly from within the System Settings page for SDDM.
- In SystemSettings > Startup and Shutdown > Login Screen (SDDM), Get New Login Screens at the bottom of the window.
- To install a theme:
 - from a downloaded zip file, click on the “Install from File” button in the System Settings page for SDDM, then select the targeted zip file from file chooser that opens up.
 - While in the System Settings in-built SDDM theme browser, simply click on the “Install” button of the selected theme.

TAKE NOTE: Some themes in KDE Store may be incompatible. MX 23 uses Plasma version 5.27.5, which is the stable version available for Debian, Bookworm. You may therefore find that some of the latest SDDM themes built to utilize the latest features in Plasma may not work with Plasma 5.27's SSDM. Thankfully SSDM comes with a fallback login screen so that if a theme that you applied does not work, you can still log back into your desktop and from there change to another SDDM theme. Do some testing; some very new themes work while others don't.

3.8.8 Bootloader

The bootloader (GRUB) of an installed MX Linux can be modified with common options by clicking **Start menu > MX Tools > MX Boot Options** (see Section 3.2). For other functions, install **Grub Customizer**. [This tool should be used with caution](#), but it allows users to configure Grub settings such as the boot entry list configuration, names of partitions, color of menu entries, etc. Details [here](#).

3.8.9 System and Event sounds

Xfce

Computer beeps are silenced by default in the “blacklist” lines in the file `/etc/modprobe.d/pc-speaker.conf`. Comment out (# at the beginning) those lines as root if you wish to restore them.

Event sounds can be turned on system-wide by clicking **Start menu > Settings > Appearance**, **Other tab**: check Enable event sounds and, if you wish, Enable input feedback sounds. They can be managed with MX System Sounds (Section 3.2). If you do not start hearing small sounds when you close a window or logout, for instance, try these steps:

- Log out and back in.
- Click Start menu > Multimedia > PulseAudio Volume Control, Playback tab, and adjust the level as needed (start with 100%).
- Click the start menu, type "`!alsamixer`" (don't forget the exclamation point). A terminal window will appear with a single audio control (Pulseaudio Master).
 - Use F6 to select your audio card, and then adjust the channels that appear to higher volumes.
 - Look for channels like "Surround", "PCM" "Speakers", "Master_Surround", "Master_Mono" or "Master". The channels that are available depend on your particular hardware.

Three sound files are supplied by default: Borealis, Freedesktop and Fresh and Clean. All are located in `/usr/share/sounds`. Find others in the repos or with a web search.

KDE

To set system sounds click **System Settings > Notifications > Application Settings > Plasma Workspace > Configure Events**.

3.8.10 Default applications

General

The default applications to be used for general operations are set by clicking **Application menu > Settings > Default Applications (Xfce)** or **System Settings > Applications > Default Applications (KDE/Plasma)**. There you can set four preferences (Xfce: separate tabs for Internet and Utilities).

- Web browser
- Mail reader
- File manager
- Terminal emulator

- Map (KDE)
- Dialer (KDE)

Particular Applications

Many defaults for specific file types are set during an application's installation. But often multiple options exist for a given file type, and a user would like to determine which application would launch the file—such as the music player to open an *.mp3 file.

Xfce's Default Applications app has a third tab, "Others," where these MIME types can be set using a handy searchable table to find the type, then double-clicking the Default Application space to set the desired application.

General method

- Right-click any example of the file type you are interested in
- Make one of the following selections:
 - **Open with <listed application>**. This will open the file with the selected application for this particular instance, but will not affect the default application.
 - **Open with Other Application.** Scroll down the list to highlight the one you want (including "Use a custom command"), then check Open. The box at the bottom "Use as default for this kind of file" is unchecked by default, so check it if you want your selection to become the new default application that is launched when you click on any file of that particular type. Keep it unchecked for one-time usage.




Figure 3-52: Changing default application Left: Thunar Right: Dolphin.

3.8.11 Limited Accounts

For some purposes, it may be desirable to lock down an application or system in order to protect it from users. Examples include computers in a school or public location for general use, where the file system, desktop and internet access need to be closed. There are a number of options available.

- Some components of Xfce that support kiosk mode. Details in [the Xfce Wiki](#).
- KDE has an administrative mode, consult [the KDE Userbase](#).
- Check the browser you use to see if it has a kiosk mode.
- The dedicated kiosk distro [Porteus](#).

3.9 Accessibility

3.9.1 Screen magnifier

Magnus (Xfce) and **KMag** (KDE) are simple and handy tools to enlarge portions of the screen.

3.9.2 Screen reader

Orca screen reader At this time due to Debian's packaging, orca does not appear in the menus but can be launched manually. In particular orca is configurable in KDE's integrated accessibility settings and can be started with *Meta+Alt+S*. For use, see [this tutorial](#).

MORE:

[Xfce accessibility](#)

[KDE accessibility](#)

4 Basic use

4.1 Internet

4.1.1 Web browser

- MX Linux comes with the popular browser **Firefox** installed, which has a large set of add-ons to augment the user's experience.

[Firefox home page](#)

[Firefox add-ons](#)

- Upgrades of Firefox come through the MX Linux repos, and are usually available to users within 24 hours of release. For direct download, see Section 5.5.5.
- Localization files for Firefox can be installed easily with MX Package Installer.
- Firefox has a sync service that facilitates transferring bookmarks, cookies, etc. from an existing Firefox installation.
- Other browsers are available for easy download and installation via the MX Package Installer. Check the [MX/antiX Wiki](#) for configuration tips and tricks.

4.1.2 Email

- **Thunderbird** is installed by default in MX Linux. This popular email client integrates well with Google Calendar and Google Contacts. The most recent versions available can be found with the MX Package Installer > MX Test Repo.
- Localization files for Thunderbird can be installed easily with MX Package Installer.
- For help with links no longer opening a browser, consult [the MX/antiX Wiki](#).
- Other lightweight email clients are available from the MX Package Installer.

4.1.3 Chat

- **HexChat**. This IRC chat program is installed by default in MX Linux, and makes the exchange of text messages easy for the user.

[HexChat home page](#)

- **Pidgin.** This graphical, modular instant messaging client is capable of using multiple networks at once. MX Package Installer.

[Pidgin home page](#)

Video Chat

- **Zoom.** This very popular video chat program is cross-platform and can be installed on MX Linux without problem using the **MX Package Installer > Messaging**. It integrates automatically with PulseAudio, which is installed by default.
- **Gmail** has a talk function built in, now called [Google Meet](#). See Section 4.10.6
- **Skype.** A popular proprietary program for instant messaging as well as voice and video chat.

[Skype home page](#)

Troubleshooting

- If your voice is not being picked up even after you use the app's own tools, try this:
 - Sign into your video chat app, click on Options and go to the Sound Devices tab.
 - Click on the button to start a test call. While the call is going on, open PulseAudio Volume Control and go to the Recording tab.
 - Still while the test call is going on - change the Skype to the Webcam microphone.

4.2 Multimedia

Listed here are some of the many multimedia applications available in MX Linux. Advanced professional applications also exist, and can be found through targeted searches in Synaptic.

4.2.1 Music




Figure 4-1: Playing a CD track with Strawberry.

- Players
 - **Strawberry**. A modern music player and library organizer that can play every source from a CD to a Cloud Service. Installed by default.

[Strawberry home page](#)

- **Audacious**. A full-featured music player and manager. MX Package Installer.

[Audacious home page](#)

- **DeaDBeeF**. A lightweight player with a small memory footprint, robust set of basic features, and a focus on music playback. MX Package Installer.

[DeaDBeeF home page](#)

- Rippers and editors
 - **Asunder**. A graphical Audio CD ripper and encoder that can be used to save tracks from Audio CDs. Installed by default.

[Asunder home page](#)

- **EasyTAG**. A simple application for viewing and editing tags in audio files.

[EasyTAG home page](#)

4.2.2 Video



[VIDEO: UPDATE: Netflix on 32 bit Linux](#)

- Players
 - **VLC**. Plays a large range of video and audio formats, DVDs, VCDs, podcasts, and multimedia streams from various network sources. Installed by default.

[VLC home page](#)

- A YouTube Browser for **SM Player** (not installed by default).

[SMplayer home page](#)

- **Netflix**. Desktop capability of streaming Netflix is available for Firefox and Google Chrome.

[Netflix home page](#)



Figure 4-2: Running desktop Netflix in Firefox.

- Rippers and editors
 - **HandBrake**. A video ripper that is easy to use, fast and simple. Install with MX Package Installer.

[HandBrake home page](#)

- **DeVeDe.** This utility automatically converts material to formats compatible with audio CD and video DVD standards.

[DeVeDe home page](#)

- **DVDStyler.** Another good authoring utility. MX Package Installer.

[DVDStyler home page](#)

- **OpenShot.** A simple-to-use and feature-rich video editor. MX Package Installer.

[OpenShot home page](#)

4.2.3 Photos




Figure 4-3: Using the crop tool in Nomacs.

- **Nomacs.** A fast and powerful image viewer installed by default.

[Nomacs home page](#)

- **Mirage.** This speedy application is easy to use and allows you to view and edit digital photos. Install via MX Package Installer.

[Mirage project page](#)

- **Fotoxx.** This fast application allows easy photo editing and collection management while serving the needs of serious photographers. MX Package Installer > MX Test Repo.

[Fotoxx home page](#)

- **GIMP.** The premier image manipulation package for Linux. Help (**gimp-help**) must be installed separately, and is available in many languages. Basic package installed by default, full available from MX Package Installer.

[GIMP home page](#)

- **gThumb.** an image viewer and browser from the GNOME Developers that also includes an importer tool for transferring photos from cameras.

[gThumb Wiki](#)

- **LazPaint,** a cross-platform lightweight image editor with raster and vectorial layers. Default in MX-21.

[LazPaint documentation](#)

- **Gwenview,** the KDE project image viewer




Figure 4-4: Gwenview.

4.2.4 Screencasting




Figure 4-5: Main screen of SimpleScreenRecorder.

- **SimpleScreenRecorder.** A simple but powerful program to record programs and games. Install via MX Package Installer.

[SimpleScreenRecorder home page](#)

- **RecordMyDesktop.** Captures audio-video data of a Linux desktop session. Install via MX Package Installer.

[RecordMyDesktop home page](#).

4.2.5 Illustrations

- **mtPaint.** An easily learned application for creating pixel art and manipulating digital photos. Install via MX Package Installer.

[mtPaint home page](#)

- **LibreOffice Draw.** Diagrams, drawings and pictures can be created and modified with this application.

[LO Draw home page](#)

- **Inkscape.** This illustration editor has everything needed to create professional-quality computer art. MX Package Installer.

[Inkscape home page](#)

4.3 Office

4.3.1 Office suites

4.3.1.1 On the desktop

LibreOffice

MX Linux comes with a great free office suite called LibreOffice, which is the Linux equivalent and near drop-in replacement for Microsoft Office®. The suite is available under **Application Menu > Office > LibreOffice**. LibreOffice supports the .docx, .xlsx and .pptx file formats of Microsoft Office. The latest stable version available in the default repos is installed by default.




Figure 4-6: Main dashboard in LibreOffice 7.4.5.1.

- Word Processor: LibreOffice **Writer**. An advanced word processor compatible with .doc and .docx files.
- Spreadsheet: LibreOffice **Calc**. An advanced spreadsheet compatible with .xls and .xlsx files.

- Presentation: LibreOffice **Impress**. Presentations, compatible with .ppt and .pptx files.
- Draw: LibreOffice **Draw**. Used to create graphics and diagrams.
- Math: LibreOffice **Math**. Used for mathematical equations.
- Base: LibreOffice **Base**. Used to create and manipulate databases. If using this application to create or use databases in the native LibreOffice format, you must also install **libreoffice-sdbc-hsqldb** and **libreoffice-base-drivers** matched to version.
- Users can get more recent versions by a number of different methods:
 - Download directly from the LibreOffice. See [the MX/antiX Wiki](#) for details.
 - Download from MX Package Installer, Debian Backports tab.
 - Download the Flatpak (MX Package Installer) or the [Appimage](#).

LINKS

- [LibreOffice home page](#).
- [MX/antiX Wiki](#).

Other desktop suites are available as well.

- [Softmaker Free Office](#) -- MX Package Installer: Popular applications
- [Calligra Suite](#) (part of the KDE project) -- MX Package Installer: Test Repo

4.3.1.2 In the cloud

Google Docs and Office Suite

Google's [Docs](#) offers excellent online applications that include three standard office components: Docs, Sheets and Slides. It is easy to share files and the export options are very handy.

Microsoft 365

Microsoft products are not FOSS, yet many users need or want to have access to the, especially for business, institutional and other such contexts. Although Microsoft Office suite applications can't be natively installed under Linux, Microsoft's [Office365](#) (paid service) or

[On-line Office](#) (free) are just regular web pages that run fine inside any modern browser on MX Linux. Details in [the MX/antiX Wiki](#).

Other options

- [OnlyOffice](#) (paid service for enterprises)

4.3.2 Office finances

- GnuCash. Financial software for office use. It is easy to learn, and allows you to track bank accounts, stocks, income and expenses. Can import data in QIF, QFX and other formats, and supports double entry accounting. MX Package Installer. The Help package (**gnucash-docs**) needs to be installed separately.
- [GnuCash home page](#)




Figure 4-7: New account in GnuCash.

4.3.3 PDF

- **QPDFview**. A fast and lightweight viewer that includes a number of basic tools. Installed by default.

[QpdfView home page](#)

- **Okular**, the KDE project PDF and document reader

[Okular documentation](#)

- Document Scanner (formerly SimpleScan) is minimal scan software that works very well for everyday tasks. Installed by default on MX-23.

[Document Scanner home page](#)

- **PDFShuffler** makes simple the reordering, deleting and adding of PDF pages. Installed by default.

[PDFShuffler home page](#)

- **gscan2pdf** is a technical app for general scanning needs. MX Package Installer ([MX/antix Wiki](#)).

[gscan2pdf home page](#)

- For other functions (e.g., creating a PDF form), see [MX/antiX Wiki](#).

4.3.4 Desktop publication

- **Scribus**. Professional page layout that produces press-ready output. Available via MX Package Installer.

[Scribus home page](#)

4.3.5 Project time tracker

- **Kapow** punch clock. Simple but feature-rich app to record project time.

[Kapow home page](#)




Figure 4.8 Kapow set to track work on a project.

- [Other options](#)

4.3.6 Video meeting and remote desktop

- [AnyDesk](#). Allows easy remote access. MX Package Installer, along with other options.
- TeamViewer. Cross-platform application for Remote Support and Online Meetings. Free for private use. MX Package Installer.

[TeamViewer home page](#)

- [Zoom](#). A very popular video chat program that can be installed on MX Linux without problem using the **MX Package Installer > Messaging**.

4.4 Home

4.4.1 Finances

- **HomeBank**. Easy management of your personal accounting, budget and finance.

[HomeBank home page](#)

- **Grisbi** is very useful for the home. It can import QIF/QFX files, and has an intuitive interface. Well suited to banks outside the US.

[Grisbi home page](#)

4.4.2 Media Center

- **Plex Mediaserver**. Lets you bring together all your media and view it in one place. MX Package Installer.

[Plex home page](#)

- **Kodi Entertainment Center** (formerly XBMC) allows users to play and view videos, music, podcasts, and media files from local and network storage media. Install via MX Package Installer.

[Kodi home page](#)

4.4.3 Organization

- **Notes**. This handy Xfce plugin (**xfce4-notes-plugin**) allows you to create and organize sticky notes for your desktop.

Notes home page

- **KDE Pim Application**, a suite of applications to manage personal information.

https://community.kde.org/KDE_PIM

- **Osmo**. Nice compact Xfce application that includes calendar, tasks, contacts and notes.

Osmo home page



Figure 4-9: The personal information manager Osmo.

4.5 Security

4.5.1 Firewall

Gufw. A personal firewall configuration utility that makes it easier for the user to configure the firewall. Installed by default in Xfce and Fluxbox only. KDE users can search for gufw in MXPI.

In MX Linux 23, the Uncomplicated Firewall (aka UFW) is enabled by default and set to ignore all incoming connections. This may also block some popular networking services like Samba, SSH, VNC or KDE Connect from working out-of-the box.

Adding a Firewall exception Rule alleviates this in a secure manner. To configure a rule in the UFW run the “Firewall Configuration” (UFW app).

- The Firewall “Status:” Blue | indicates that the Firewall is on (enabled).
- Click the Rules button and then +.
- Click in the white Search box type “Samba” and click the “+ Add” button and then Close.




Figure 4-10: Adding an exception for Samba

NOTE: Samba version 4.7.x and up uses TCP on port 445. This all that is needed for Vista and newer versions of Windows.

WARNING: Older version of Samba devices and versions of Windows 2000 and older use UDP on ports 137 & 138 and TCP on ports 137, 139. Enabling these port ranges *MAY* result in data loss, Ransomware, Malware, or privacy issues.

Web Services Dynamic Discovery Service (WSDD)

If you are using WSDD Service (MX Test Repo) to allow Windows hosts to be able to browse to Linux shares (visible in Windows Explorer folder > Network):

- WSDD operates over port 5357 over TCP and port 3702 over UDP.
- At present there are no predefined UFW Firewall Rules for WSDD.

HELP:

[Homepage](#)

[Documentation](#)

4.5.2 Antivirus

- ClamAV. Useful to stop Linux users from unknowingly passing virus-infected emails and other documents to susceptible Windows users.

[ClamAV home page](#)

4.5.3 AntiRootkit

- chkrootkit. This application scans systems for known and unknown rootkits, backdoors, sniffers and exploits.

[chkrootkit home page](#)

4.5.4 Password protection

- Passwords and Keys. A password and key manager installed by default. Details on usage in [the MX/antiX Wiki](#).

[Passwords and Keys help](#)

- KeePassX. A password manager or safe that helps you to manage your passwords in a secure way. MX Package Installer.

[KeePassX home page](#)

4.5.5 Web access

Most modern browsers have add-ons that permit easy web filtering. **FoxFilter** is a well-established example that installs on Firefox, Chrome and Opera.




Figure 4-11: The preferences tab for FoxFilter.

4.6 Accessibility

Various open-source utilities exist for MX Linux users with disabilities.

- On-screen keyboard. **Onboard** is installed by default, and **Florence** is in the repos.
- Screen magnifier. **Magnus** (Xfce) and **KTTS** (KDE) installed by default.
- Text reader. **Orca** works well with KDE, less well with Xfce.
- Assistive applications
 - Xfce. Click Application Menu > Settings > Accessibility, and tick Enable Assistive Technologies. Change the available options to suit your liking.

[Xfce4 documentation: Accessibility](#)

- KDE maintains a large collection of accessibility aids.

[KDE Accessibility applications](#)

- Debian. Many other tools are available within Debian itself.

[Debian Wiki](#)

4.7 System

4.7.1 Root privileges

There are two common commands to obtain root (AKA administrator, superuser) privileges that you need to make system changes (e.g., installing software) using a terminal.

- **su**: requires the root password and grants privileges for entire terminal session
- **sudo**: requires your user password and grants privileges for a short time period

In other words, su lets you switch user so that you're actually logged in as root, while sudo lets you run commands in your own user account with root privileges. Also, su uses the environment (user-specific configuration) of the user root, while sudo allows root-level changes but keeps the environment of the user issuing the command. Starting with MX-21, MX Linux uses by default sudo.

The user can select whether to use “Root” or “User” on the “Other” tab of MX Tweak.

MORE: click Application Menu > enter “#su” or “#sudo” (without the quotes) in the search space and return to see the detailed man pages.

Running a root application

Some applications that can be found in the Application Menu require that the user have root privileges: gparted, lightdm gtk+ greeter, etc. Depending on how the launch command is written, the dialog box that pops up may show that root access will be stored (default setting) for as long as your session lasts (i.e., until you log out).



Figure 4-12: Dialog box when the command pkexec is used (no storage).

4.7.2 Get hardware specs

- Click **Application Menu > System > System Profiler and Benchmark** for a nice graphic display that includes the results of various tests.
- Click **Application Menu > MX Tools > Quick System Info**. The output is automatically copied to the clipboard, and can be pasted into a Forum post complete with code tags.

See Section 6.5 for the many other features of inxi.

4.7.3 Create symbolic links

A symbolic link (also soft link or symlink) is a special kind of file that points to another file or folder, much like a shortcut in Windows or an alias in Macintosh. A symbolic link does not contain any actual data (as a hard link does), it just points to another location somewhere in the system.

There are two ways to create a symlink: File Manager or the command line.

- **Thunar**

- Navigate to the file or folder (target of the link) that you want to point to from another location or under another name
- Right-click what you want to link > Create Symlink, and a symlink is created where you currently are
- Right-click the new symlink > Cut
- Navigate to where you want the link to be, right-click an open area > Paste. Change if desired the link name.
- **Dolphin/KDE-Plasma**

- Use Create New > Basic Link to File or Directory
- Command line: Open a terminal and type:

`ln -s TargetFileOrFolder LinkName`

- For example, to symlink a file named “foo” in your Downloads folder to your Documents folder, enter this:

`ln -s ~/Downloads/foo ~/Documents/foo`

4.7.4 Find files and folders

GUI

Xfce - Thunar




Figure 4-13: Search screen of Catfish looking for “MX-” in the Downloads folder.

Catfish is installed by default in MX Linux Xfce, and can be launched from the **Application Menu > Accessories**, or simply by starting to type “search” in the top search entry field. It is also integrated into Thunar so that the user can right-click a folder > Find files here.

[Catfish home page](#)

KDE/Plasma users can access the **Find** dialog built into the **Dolphin** File Manager toolbar.




Figure 4-14: Dolphin Find search results.

Other more advanced search software such as [recoll](#) is available in the repos.

CLI

There are some very handy commands for use in a terminal.

- *locate*. For each given pattern, locate searches one or more databases of file names and displays the ones that contain the pattern. For example, typing:

```
locate firefox
```

will return an extremely long list with every single file that has the word “firefox” in its name or its path. This command is similar to [find](#) and is best used when the exact file name is known.

[Locate examples](#)

- *whereis*. Another command-line tool, installed by default. For each given pattern, whereis searches one or more databases of file names and displays the file names that contain the pattern, but it ignores paths so the return list is much shorter. For example, typing:

```
whereis firefox
```

will return a much shorter list something like this:

```
firefox: /usr/bin/firefox /etc/firefox /usr/lib/firefox  
/usr/bin/X11/firefox /usr/share/firefox  
/usr/share/man/man1/firefox.1.gz
```

Whereis examples

- *which*: Arguably the most convenient tool of all, this command attempts to identify the executable. For example, typing:

```
which firefox
```

returns a single item:

```
/usr/bin/firefox
```

Which examples

4.7.5 Kill runaway programs

- Desktop
 1. Press **Ctrl-Alt-Esc** to change the cursor into an “x”. Click on any open screen to kill it, right-click to cancel. Be careful not to click on the desktop or your session will end abruptly.
 2. Xfce - Task Manager: **Application Menu > System > Task Manager**. Select the process you want and right-click to stop, terminate or kill.
 3. KDE/Plasma – **Application Menu > Favorites**, or click **Application Menu > System > System Monitor**
 4. A traditional tool is also available: click **Application Menu > System > Htop**, which brings up a terminal showing all running processes. Locate the program you want to stop, highlight it, press F9, then Return.
- Terminal: Press **Ctrl-C**, which will usually stop a program/command you started in a terminal session.
- If the above solutions don't work, try these more extreme methods (listed in increasing severity).
 1. Restart X. Press **Ctrl-Alt-Bksp** to kill all session processes, leaving you back at the login screen. Any unsaved work will be lost.
 2. Use magic SysRq key (REISUB). Hold down the **Alt** key (sometimes only the left Alt key will work) along with the **SysRq** (can be also labeled **Print Screen** or **PrtScrn**) key with another hand, then slowly, without releasing Alt-SysRq,

press the keys **R-E-I-S-U-B** one after the other. Hold down each key of the REISUB sequence for about 1 or 2 second before moving on to the next key; your system should shut down correctly and reboot. The purpose of this magic key is to go through several stages that nurse your system safely out of a failure of some sort, and often only the first 2 letters are sufficient. This is what happens when you go through the letters:

- **R - switch the keyboard mode.** This is said to "Switch the keyboard from raw mode, the mode used by programs such as X11 and svgalib, to XLATE mode" (from [Wikipedia](#)), but it is unsure if this would normally have any notable effect.
- **E - gracefully terminate all running programs.** This sends the SIGTERM signal to all processes except `init` and thereby asks them to gracefully terminate, giving them a chance to tidy up and free their resources, save data, etc...
- **I - forcibly kill all running programs.** This is similar to the E, but sends the SIGKILL signal to all processes except `init`, which kills them immediately and forcibly.
- **S - sync all disks and flush their caches.** All your disks normally have a write cache, a piece of RAM where the system caches data it wants to save on the device, to speed the access up. Syncing tells the system to flush these caches now and perform all remaining writes. That way you do not lose any data that has already been cached but not been written yet, and it protects from leaving the file system in an inconsistent state.
- **U - unmount all disks and remount them read-only.** This is again pretty unspectacular, it simply makes all mounted disks read-only to prevent any further (partial) writes.
- **B - reboot the system.** This reboots the system. However, it does not perform a clean shutdown, but instead a hard reset.

[Wikipedia: REISUB](#)

3. If nothing else works, hold down the power button of your computer for 10 seconds or so until it shuts down.




Figure 4-15: Task Manager, ready to kill a process. Right: KDE/Plasma Left: Xfce.

4.7.6 Track performance

General

- GUI
 - Click Application Menu > System > System Profiler and Benchmark, where you can not only see a great many specifications but also run performance tests.
 - Many conkies show some system performance; use Conky Manager to preview them for your needs and preferences. See Section 3.8.3.
 - Xfce plugins. A variety of plugins for monitoring the system can be placed in the Panel, including Battery Monitor, CPU Frequency Monitor, CPU Graph, Disk Performance Monitor, Free Space Checker, Network Monitor, Sensor plugin, System Load Monitor, and Wavelan. They can all be installed with the metapackage **xfce4-goodies**. KDE/plasma has a similar set of panel and desktop widgets.

[Xfce4 Goodies home page](#)

- CLI
 - lm-sensors. This hardware health monitoring package is installed by default in MX Linux. Open a terminal and enter with su or sudo:

sensors-detect

Click Return to answer yes to all questions. When it has finished, you will be able to get detailed information about the readings of the sensors that are available on your system by opening a terminal and entering: *sensors*.

[Lm-sensors home page](#)

Battery

Battery level is monitored by the Power Manager plugin (Xfce) on the Panel. A dedicated Panel plugin called *Battery Monitor* is also available by right-clicking the Panel > Panel > Add New Items ...

KDE has a Battery Monitor panel widget installed by default.

4.7.7 Schedule tasks

- GUI
 - MX Job Scheduler, see 3.2.11.
 - Scheduled tasks (**gnome-schedule**). A very handy way to schedule system tasks without having to directly edit system files. [Gnome-schedule home page](#).
 - KDE has a [Task Scheduler](#) with similar capabilities.




Figure 4-16: Main screen of KDE's Task Scheduler.

- CLI
 - You can edit **crontab**, a text file with a list of commands to be run at specified times.

[Crontab overview](#)

[Easy crontab generator](#)

4.7.8 Correct time

Correct time setting is normally taken care of at Live boot or during the installation. If your clock time is always wrong, there are 4 possible issues:

- wrong timezone
- wrong selection of UTC versus local time
- BIOS clock set wrong
- time drift

These issues are most easily addressed by using **MX Date & Time** > Application Menu > System (Section 3.4); for command line techniques, see [the MX/antiX Wiki](#).

4.7.9 Show Key Lock

On many laptops there is no indicator light for the activation of the CapsLock or NumLock keys, which can be very annoying. To solve this with an onscreen notifier, install **indicator-keylock** from the repos.

4.8 Good practices

4.8.1 Backup

The most important practice is to [back up your data and configuration files](#) regularly, a process that is easy in MX Linux. It is highly recommended that you back up to a different drive than the one your data is on! The average user will find one of the following graphical tools convenient.




Figure 4-17: Main screen of Lucky Backup.

- MX Snapshot, an MX Tool. See [Section 3.4](#).

[Overview](#)

- gRsync, a graphical frontend for [rsync](#).

[Overview of gRsync](#)

- **LuckyBackup.** An easy program to back up and sync your files. Installed by default.

[LuckyBackup manual](#)

- **Déjà Dup.** A simple but very effective backup tool.

[Déjà Dup home page](#)

- **BackInTime.** A well-tested app available from MX Package Installer > MX Test Repo (preinstalled on MX KDE)
- **Cloud service.** There are many cloud services that can be used for backing up or synching your data. DropBox and Google Drive are probably the best known, but many others exist.
- **Cloning.** Create a complete image of the hard drive.
 - **Clonezilla.** Download Clonezilla Live from the [Clonezilla home page](#), and then reboot into it.
 - **Timeshift.** Full system backup/restore; in the repos. [Timeshift home page](#) includes a detailed overview and how-to.
 - **Save the system to a live ISO (Section 6.6.3).**
 - **CLI tools.** See the discussion in the [Arch Wiki: Cloning](#)
- **CLI commands for doing backups (rsync, rdiff, cp, dd, tar, etc.).**

Data

Make sure you back up your data, including documents, graphics, music, and mail. By default, most of this is stored in your /home directory; we recommend that if possible you have a separate data partition, best in an external data location.

Configuration files

Here is a list of items to consider for backup.

- **/home.** Holds most of the personal configuration files.
- **/root.** Holds the changes you have made as root.
- **/etc/X11/xorg.conf.** X configuration file, if there is one.

- The GRUB2 files /etc/grub.d/ and /etc/default/grub.

List of installed program packages

It's also a good idea to save in your /home directory or in the cloud (Dropbox, Google Drive, etc.) a file that contains the list of programs that you have installed with Synaptic, apt or Deb Installer. If in the future you need to reinstall, you can recover the names of the files for reinstallation.

GUI

There is a dedicated tool for this purpose: **MX User Installed Packages**. See [Section 3.4](#).

There is also a tool [**aptik**](#) in the repos that can aid if used with caution. It can be helpful with settings files that tend to be overlooked.

CLI

You can create an inventory of all packages on your system installed since installation by copying this long command and running it in a terminal:

```
dpkg -l | awk '/^i|h|i/{ print $2 }' | grep -v -e ^lib[0-q\s-z] -e ^libr[0-d\f-z] -e ^libre[0-n\|p-z] -e -dev$ -e -dev: -e linux-image -e linux-headers | awk '{print $1" installed"}' | column -t > apps_installed.txt
```

That will create a text file in your home directory called “apps_installed.txt” that contains all the package names.

To reinstall ALL those packages at once: make sure that all needed repositories are enabled, then issue these commands one at a time:



```
sudo dpkg \SpecialChar nobreakdash\SpecialChar nobreakdashset-selections <
apps_installed.txt
apt-get update
apt-get dselect-upgrade
```

NOTE: this should not be attempted between MX releases based on different Debian versions (e.g., from MX-19.4 to MX-21)

4.8.2 Disk maintenance

As a system ages, it often accumulates data that is no longer being used and gradually fills up the disk. Such problems can be alleviated by periodic use of **MX Cleanup**.

Let us look at an example. When her machine was slowing down, one user checked free space on the disk using *inxi -D* and was startled to see that the disk was 96% full. **Disk Usage Analyzer**



provided a good graphical analysis. After it had been cleaned using MX User Manager, the percentage dropped to about 63% and the sluggishness was gone.

Figure 4-18. Left: Disk Usage Analyzer displaying a root directory almost full. Right: result of clearing out the cache as represented by Disk Usage Analyzer.

Defragging

Users coming from Windows may wonder about the need to defrag the drive periodically. Defrag is not likely to be needed on the MX default ext4 file system but if it's almost full and hasn't got a contiguous area big enough to allocate your file, you'll end up with fragmentation. You can check the status if necessary with this command:

```
sudo e4defrag -c /
```

You will see after a few seconds a score and a simple statement about whether it needs defragmentation or not.

4.8.3 Error checking

Many error messages are written to the appropriate file in `/var/log/` covering problems in applications, events, services and system. Some important ones include:

- `/var/log/boot`
- `/var/log/dmesg`
- `/var/log/kern.log`
- `/var/log/messages`
- `/var/log/Xorg.0.log`

You can view these logs conveniently using **Quick System Info**.

4.9 Games

Browsing the extensive list of games available through Synaptic (click Sections > Games at the bottom of the left panel) or following the links below will bring up many other titles for your enjoyment.

The following list contains some examples to whet your appetite.

4.9.1 Adventure and Shooter Games

- Chromium B.S.U.: A fast paced, arcade-style, top-scrolling space shooter.
[Chromium B.S.U. home page](#)
- Beneath A Steel Sky: A science-fiction thriller set in a bleak post-apocalyptic future.
[Beneath a Steel Sky home page](#)

- Kq: A console-style role playing game, similar to Final Fantasy.
[Kq home page](#)
- Mars. “A ridiculous shooter.” Protect planet from your jealous neighbors!
[Mars home page](#)




Figure 4-19: Enemy warships on the attack in Chromium B.S.U.

4.9.2 Arcade Games

- Defendguin: A clone of Defender, where your mission is to defend little penguins.
[Defendguin home page](#)
- Frozen Bubble: Colored bubbles are frozen at the top of the playing screen. As the Ice Press descends, you must pop out groups of frozen bubbles before the Press reaches your shooter.
[Frozen Bubble home page](#)
- Planet Penguin Racer: a fun racing game with your favorite penguin.
[Tuxracer home page](#)
- Ri-li: A toy train game.
[Ri-li home page](#)
- Supertux: A classic 2D jump’n’run side-scrolling game in a style similar to the original SuperMario games.
[Supertux home page](#)
- Supertuxkart: A much improved version of tuxkart.
[Supertuxcart home page](#)



Figure 4-20: Ri-li train needs to turn soon.

4.9.3 Board Games

- Gottcode games are clever and fun.

[Gottcode home page](#)

- Mines (gnomines): A minesweeper game for 1 player.

[Mines home page](#)

- Do'SSi Zo'la: The goal of the basic Isola game is to block the opponent by destroying the squares which surround him.

[Do'SSi Zo'la home page](#)

- Gnuchess: A chess game.

[Gnuchess home page](#)




Figure 4-21: High-tension moment in Mines.

4.9.4 Card Games

Here are some fun card games available from the repos.

- AisleRiot offers over 80 solitaire games.

[AisleRiot home page](#)

- Pysolfc: Over 1,000 solitaire games from a single application.

[Pysolfc home page](#)

4.9.5 Desktop Fun

- Xpenguins. Penguins walk around your screen. Can be customized with other characters like Lemmings and Pooh Bear (need to allow programs to run in root window).

[Xpenguins home page](#)

- Oneko. A cat (neko) follows your cursor (the mouse) around the screen. Can be customized with a dog or other animal.

[Wikipedia: Neko](#)

- Algodox. This free game presents a 2D physics sandbox where you can play with physics like never before. The playful synergy of science and art is novel, and makes it as educational as it is entertaining.

[Algodox home page](#)

- Xteddy. Puts a cute teddy on your desktop. Alternatively you can add your own image.

[Xteddy homepage](#)

- Tuxpaint. A drawing program for kids of all ages.

[Tuxpaint home page](#)



Figure 4-22: Budding genius at work in Tuxpaint.

4.9.6 Children

- Three packages of games and educational applications are available from MX Package Installer.
- In addition, Scratch is a free programming language and online community where you can create your own interactive stories, games, and animations. MX Package Installer.

[Scratch home page](#)




Figure 4-23: Coding screen for Dance Party using Scratch.

4.9.7 Tactics & Strategy Games

- Freeciv: A clone of Sid Meyer's Civilization© (version I), a turn-based multiplayer strategy game, in which each player becomes the leader of a stone age civilization, trying to gain ascendency as the ages progress.

[Freeciv home page](#)

- Lbreakout2: LBreakout2 is a breakout-style arcade game where you use your paddle to aim a ball at bricks until all bricks are destroyed. Many levels and surprises. Installed by default.

[Lgames home page](#)

- Lincity: A clone of the original Simcity. You must build and maintain a city and keep its people satisfied so that your population grows.

[Lincity home page](#)

- Battle for Wesnoth: A highly-rated turn-based strategy game with a fantasy theme. Build your army and fight to regain the throne.

[Battle for Wesnoth home page](#)



Figure 4-24: Trying to break through the first wall in Lbreakout.

4.9.8 Windows games

A number of Windows games can be played in MX Linux by using a Windows emulator such as Cedega or DOSBox, or some may even run under Wine: see Section 6.1.

4.9.9 Game Services



Figure 4-25: Sins of a Solar Empire: Rebellion running on Steam with Proton.

There exist various collections and services for the user wishing to play games on MX Linux. Two of the best known are easily installable with MX Package Installer.

- **PlayOnLinux.** A graphical frontend for Wine (Section 6.1) that allows Linux users to easily install and use numerous games and apps designed to run with Microsoft® Windows®.
[PlayOnLinux homepage](#).
- **Steam.** A proprietary digital distribution platform for purchasing and playing video games that provides installation and automatic updating of games. Includes Proton, a modified distribution of Wine.
[Steam homepage](#)

4.10 Google tools

4.10.1 Gmail

Gmail can be easily set up in Thunderbird following the prompts. It can also be easily accessed in any browser.

4.10.2 Google's Contacts

Google's Contacts can be linked into Thunderbird by using the add-on gContactSync.

[gContactSync home page](#)

4.10.3 Google cal

Gcal can be set up on a tab in Thunderbird with the add-ons Lightning and Google Calendar Tab.

[Lightning calendar home page](#)

4.10.4 Google tasks

Gtasks can be included in Thunderbird by ticking the Tasks entry of the calendar.

4.10.5 Google Earth

The easiest method of installing Google Earth is by using **MX Package Installer**, where it is in the “Misc” section.

There is also a manual method that may be useful in some installations.

- Install **googleearth.package** from the repos or directly from [the Google repo](#).
- Open a terminal and enter:

```
make-googleearth-package
```

- Once that is finished, become root and type:
`dpkg -i googleearth*.deb`
- An error message will appear on screen about dependency problems. Correct that by entering this last command (still as root):
`apt-get -f install`

Now finally Google Earth will appear in **Application Menu > Internet**.

4.10.6 Google Talk

[Google Duo](#) can be run directly from Gmail.

4.10.7 Google Drive

Convenient tools providing local access to your GDrive account exist.

- A free simple app called [Odrive](#) installs and works well.
- The proprietary cross-platform app [Insync](#) allows selective syncing and installation on multiple computers.

4.11 Bugs, issues and requests

Bugs are errors in a computer program or system that produce incorrect results or abnormal behavior. "Requests" or "enhancements" are additions requested by users, either as new applications or new features for existing applications. MX Linux deals with these in the following manner:

- Bugs are managed by means of [the MX and antiX Linux Bug Tracker](#).
- Requests can be made with a post in the [Bugs and Request Forum](#), being careful to provide information about hardware, system and other details
- Devs as well as Community members will respond to those posts with questions, suggestions, etc.



Figure 4-26: dashboard of the bug manager

5 Software Management

5.1 Introduction

5.1.1 Methods

MX Linux offers two complementary GUI methods of software management for CLI see 5.5.4):

- **MX Package Installer (MXPI)** for one-click installation / removal of popular applications. This includes applications in the Debian Stable, MX Test, Debian Backports, and the Flatpaks repositories (Section 3.2.11).
- **Synaptic Package Manager**, a full-featured graphical tool for a whole range of actions with Debian packages. (**Note:** Flatpaks are not available via Synaptic at this time)

MXPI is recommended and has the following advantages over Synaptic:

- It's a lot faster!
- The Popular Applications tab is restricted to the packages most often used, so everything is easy to find.
- It correctly installs some complicated packages that are difficult for new users (e.g. Wine).
- It is a single source including the repositories mentioned above and has newer packages than what Synaptic has by default.

Synaptic has its own advantages:

- It has a large number of advanced filters set up such as Sections (categories), Status, etc.
- It offers detailed information about particular packages.
- It makes it very easy to add new software repositories.

This Section 5 concentrates on Synaptic, which is the recommended method for beginners to manage software packages beyond the capabilities of MX Package Installer. It will also look at other methods that are available and may be required for certain situations.

5.1.2 Packages

Software operations in MX are accomplished behind the scenes through the [Advanced Package Tool \(APT\)](#) system. Software is provided in the form of a **package**: a discrete, non-executable bundle of data that includes instructions for your package manager about installation. Packages are stored on servers called repositories (repos), and can be browsed, downloaded, and installed through special client software called a package manager.

The majority of packages have one or more **dependencies**, meaning that they have one or more packages that must also be installed in order for them to work. The APT system is designed to automatically handle dependencies for you; in other words, when you try to install a package whose dependencies are not already installed, your APT package manager will automatically mark those dependencies for installation as well. It can happen that these dependencies can not be met, preventing the installation of a package. If help is needed with dependencies, please post a request for help in the MX Linux [Forum](#).

5.2 Repositories

APT repositories are much more than just web sites with downloadable software. The packages on repository sites are specially organized and indexed to be accessed through a package manager, rather than browsed directly.

WARNING: Be extremely cautious when adding other repositories to MX Linux! This is especially true for: Debian Sid or non official PPAs, it is very possible to break your installation beyond repair.

5.2.1 Standard repositories

MX Linux comes with a set of enabled repositories that offer you both security and choice. If you are new to MX Linux (and especially if you are new to Linux), it is recommended that in general you stick with the default repos at first. For security reasons, these repos are digitally signed, meaning that packages are authenticated with an encryption key to make sure they are authentic. If you install packages from non-Debian repos without the key, you will get a warning that they could not be authenticated. To get rid of this warning and make sure your installations are secure, you need to install missing keys using **MX Fix GPG keys**.

Repos are most easily added, enabled/disabled, removed, or edited through Synaptic, though they can also be altered by hand by editing the files in **/etc/apt** in a root terminal. In Synaptic, click **Settings > repos**, then click the button New and add the information. Repo information is often given as a single line, like this:

```
deb http://mxrepo.com/mx/testrepo/ bookworm test
```

Be careful to note the location of the spaces, which separate the information into four chunks that are then entered into separate lines in Synaptic.




Figure 5-1: Repos, with the MX test repo highlighted.

Some repos carry special labels:

- **contrib**, which depend on or are accessory to non-free packages.
- **non-free**, which do not meet the [Debian free software guidelines](#) (DFSG).
- **security**, which contain security-related updates only.
- **backports**, which contain packages from newer versions of Debian that have been made backwards compatible to keep your OS up-to-date.
- **MX**, which contain the special packages that make MX Linux what it is.

The current list of standard MX repos is kept in the [MX/antiX Wiki](#).

5.2.2 Community repos

MX Linux has its own Community Repos with packages that our Packagers build and maintain. These packages are distinct from official MX packages coming from Debian Stable, and contain packages from other sources:

- Debian Backports, from testing or even experimental.
- Our sister distro [antiX](#).
- Independent projects.
- Open-source hosts such as [GitHub](#).

The Community Repos are critical to MX Linux, since they permit an OS based on Debian Stable to stay abreast of important software developments, security patches and critical bug fixes.

In addition to the MX Main repo, the MX Test repo aims to get feedback from users before new packages are moved to Main. The easiest way to install from MX Test is with the [Package Installer](#) (Section 3.2), as it handles many steps automatically.

To find out more about what is available, who the packagers are, and even how to get involved, see [MX Community Packaging Project](#).

5.2.3 Dedicated repos

In addition to the general repos such as Debian, MX, and Community, there also exist a certain number of dedicated repos associated with a single application. When you add one of them, either directly or through Synaptic, then you will receive updates. Some are preloaded but not enabled, others you will add yourself.

Here is a common example (**Vivaldi** browser):

```
deb http://repo.vivaldi.com/stable/deb/ stable main
```

New users coming from Ubuntu or one of its derivatives often ask about **PPA repos**; Ubuntu deviates from standard Debian, so such repos need to be treated with caution. Consult the [MX/antiX Wiki](#).

5.2.4 Development repos

One final category of repository exists for acquiring the most recent (and thus least stable) build of an application. This is done through a version control system such as **Git** that can be consulted by the end user to stay current with development. A copy of the application source code can be downloaded into a directory on a local machine. The software repositories are a convenient method of managing projects using Git, and MX Linux keeps most of its code in [its own GitHub repo](#).

More: [Wikipedia: Software repository](#)

5.2.5 Mirrors

- MX Linux repos for both packages and ISOs (Image files) are “mirrored” on servers at different sites around the world; the same is true for Debian repos. These mirror sites provide multiple sources of the same information, and function to reduce download time, improve reliability, and provide a certain resiliency in case of server failure. During installation, the most likely mirror will be automatically selected for you based on location and language. But the user may have reasons to prefer another:
- The automatic assignment at installation may be wrong in some cases.
- The user may change residency.
- A new mirror may become available that is much closer, faster or more reliable.
- An existing mirror may change its URL.
- The mirror being used may become unreliable or go offline.

MX Repo Manager (Section 3.2) makes it easy to switch mirrors, enabling you to choose the one that works best for you. **Note:** Pay attention to the button that selects the fastest mirror for your location.

5.3 Synaptic Package Manager

The following section seeks to provide an up-to-date overview of Synaptic use. Note that your root password is required and, naturally, you will need to be connected to the Internet.

5.3.1 Installing and removing packages

Installing

- Here are the basic steps for installing software in Synaptic:
- Click **Start menu > System > Synaptic Package Manager**, supplying the root password if asked.
- Hit the **Reload** button. This button tells Synaptic to contact the online repository servers and download a new index file with information on:
 - What packages are available.
 - What versions they are.
 - What other packages are required for them to be installed.
- If you get a message that some of the repos failed to be contacted, wait a minute and then try again.
- If you already know the name of the package you are looking for, just click in the pane on the right and start typing; Synaptic will incrementally search as you type.
- If you don't know the package's name, use the Search box in the upper right corner to locate software based on name or keywords. This is one of Synaptic's greatest advantages over other methods.
- Alternatively, use one of the filter buttons in the bottom left corner:
 - **Sections** provides subareas such as Editors, Games and Amusement, Utilities, etc. You will see a description of each package in the bottom pane, and can use the tabs to discover more information about it.
 - **Status** groups packages by their installation situation.
 - **Origin** will show packages from a specific repository.
 - **Custom Filters** provides various filter options.
 - **Search Results** will show a list of previous searches for the Synaptic session you are in.
- Click the empty box at the left end of the package you want and select **Mark for Installation** on the pop-up screen. If the package has dependencies, you will be notified

and they will automatically be marked for installation as well. You can also just double-click the package if it is the only one you are installing.

- Some packages also have “**Recommended**” and “**Suggested**” packages that can be viewed via right-clicking the package name. These are additional packages that add functionality to the selected package, and it is a good idea to look them over.
- Click **Apply** to begin the installation. You can safely ignore any warning message: “You are about to install software that can’t be authenticated!”
- There may be additional steps: just follow the prompts as you receive them until the installation completes.




Figure 5-2: Checking recommended packages during package installation.

Removing software

Removing software from your system with Synaptic seems as straightforward as installing, but there is more to it than meets the eye:

- To remove a package, simply click the same box as for installation and select **Mark for Removal** or **Mark for Complete Removal**.
- Removal uninstalls the software, but leaves system configuration files in case you want to keep your settings.
- Complete Removal removes the software and the system configuration files as well (purging). Your personal configuration files related to the package will **not** be removed. Check also for other configuration file remnants in Synaptic’s category **Not installed (residual config)**.
- When you have other programs that depend on the package being removed, those packages will have to be removed as well. This usually happens when you remove

software libraries, services, or command-line applications that serve as back-ends to other applications. Make sure you read carefully the summary Synaptic gives you before clicking OK.

- Removing large applications that are composed of many packages can bring complications. Many times these packages are installed using a meta-package, which is an empty package that simply depends on all the packages you need for the application. The best way to remove a complicated package like this is to inspect the dependency list for the meta-package, and remove the packages listed there. Take care, however, that you don't uninstall a dependency of another application you want to keep!
- You may find that the status category Auto-removable begins to accumulate packages. These were installed by other packages and are no longer needed, so you can click on that status category, highlight all the packages in the right pane, and then right-click them to remove. Be sure to examine the list carefully when the verification box appears, because sometimes you may find that the dependencies listed for removal include packages you actually want to keep. Use *apt -s autoremove* to do a simulated (= the -s switch) dry run if you're unsure.




Figure 5-3: Getting ready to clear out the auto-removable packages.

5.3.2 Upgrading and downgrading software

Synaptic enables you to quickly and conveniently keep your system up-to-date.

Upgrading software

- Unless you are using a manual method in Synaptic or a terminal, upgrading is typically triggered by the a change in the **MX Updater** icon in the Notification Area (default: empty box turns green). There are two ways to proceed when this happens.

- Left-click the icon. This is the faster method because there is no wait for software to load, run, etc. A terminal window appears with the packages to upgrade; examine them carefully, then click OK to complete the process.
- Right-click the icon to use Synaptic instead.
- Click the Mark All Upgrades icon below the menu bar to select all available packages for upgrade, or click on the Installed (up-gradable) link in the left panel to review the packages or to select upgrades individually.
- Click Apply to begin the upgrade, ignoring the warning message. As the installation process begins, you have the option of watching the details in a terminal within Synaptic.
- With some package upgrades, you may be asked to confirm a dialog, enter configuration information, or decide whether or not to overwrite a configuration file you have altered. Pay attention here, and follow the prompts until the upgrade completes.

Downgrading software

Sometimes you may want to downgrade an application to an older version, for instance because of problems that arose with the new one. This is easy to do in Synaptic:

1. Open Synaptic, supply the root password, and click Reload.
2. Click on Installed in the panel on the left, then find and highlight the package you want to downgrade in the panel on the right.
3. On the menu bar, click Package > Force version...
4. Select from the available versions on the pull-down list. There may not be options available.
5. Click Force Version, then install in the usual manner.
6. To keep that lower version from immediately being upgraded again, you need to pin it.

Figure 5-4: Using Force version to downgrade a package.

Pinning a version

Sometimes you may want to pin an application to a specific version to keep it from being upgraded in order to avoid problems with more recent ones. This is easy to do:

1. Open Synaptic, supply the root password, and click Reload.
2. Click on Installed in the panel on the left, then find and highlight the package you want to pin in the panel on the right.
3. On the menu bar, click Package > Lock version...
4. Synaptic will highlight the package in red and add a lock icon to the first column.
5. To unlock, highlight the package again and click Package > Lock version (which will have a check mark).
6. Note that pinning via Synaptic does not prevent the package from being upgraded when using the command line.

5.4 Troubleshooting Synaptic issues

Synaptic is very reliable, but sometimes you may get an error message. A full discussion of such messages may be found in the [MX/antiX Wiki](#), so here we will only mention a couple of the most common.

- You get a message that some repos failed to download repository information. This is usually a transient event and you simply need to wait and reload; or you can use MX Repo Manger to switch repos.

- If the installation of a package shows that software you want to keep will be removed, click Cancel to back out of the operation.
- It may happen with a new repository that you see an error message after reloading that says something like: W: GPG error: [some repository URL] Release: The following signatures couldn't be verified . This message appears because apt includes package authentication in order to improve security, and the key is not present. To fix this, click **Start menu > System > MX Fix GPG keys** and follow the prompts. If no key is found, ask on the Forum.
- Occasionally, packages will not install because their install scripts fail one or more safety checks; for instance, a package might try to overwrite a file that is part of another package, or require downgrading another package due to dependencies. If you have an install or upgrade that is stuck on one of these errors, it is called a "broken" package. To fix this, click on the Broken packages entry in the left panel. Highlight the package and try first to fix the problem by clicking Edit > Fix Broken Packages. If that is not successful, then right-click the package to unmark or uninstall it.
- During installation or uninstallation, important messages sometimes appear about the process:
 - [Uninstall](#)? Occasionally, conflicts in package dependencies can cause the APT system to uninstall a large number of important packages in order to install some other package. This is rare with the default configuration, but becomes increasingly likely as you add unsupported repos. **BE VERY ATTENTIVE** whenever installing a package would require that others be removed! If a large number of packages are going to be removed, you may want to investigate another method of installing this application.
 - [Keep](#)? When upgrading, you may sometimes be informed that a new configuration file is available for a certain package, and be asked whether you want to install the new version or keep your current version.
 - **If the package in question is from an MX repository, it is recommended that you “install the maintainers version”.**
 - Otherwise, answer “keep the current version” (**N**), which is also the default choice.

5.5 Other methods

5.5.1 Aptitude

Aptitude is a package manager that can be used instead of apt or Synaptic. It is available from the repos, and is particularly helpful when dependency problems arise. Can be run as a straight CLI or as a primitive GUI.




Figure 5-5: Aptitude's home screen (GUI), showing dependency resolver.

For details on this option, see the [MX/antiX Wiki](#).

5.5.2 Deb packages

The software packages installed through Synaptic (and APT behind it) are in a format called Deb (short for Debian, the Linux distribution that devised APT). You can manually install downloaded deb packages using the graphical tool **Deb Installer** (section 3.2.28) or the command-line tool **dpkg**. These are simple tools to install local deb packages.

NOTE: if dependencies can not be satisfied, you will receive a notice and the program will stop.

Installing *.deb files with dpkg

1. Navigate to the folder containing the deb package you want to install.

2. Right-click an empty space to open a terminal and become root. Alternatively, click the arrow to move up one level and right-click the folder with the deb package > Open Root Thunar here.

3. Install the package with the command (substituting the real package name, of course):

```
dpkg -i packagename.deb
```

4. If you are installing multiple packages in the same directory at the same time (for instance if manually installing Libreoffice), you can do it all at once using:

```
dpkg -i *.deb
```

NOTE: In a shell command, the asterisk is a wild card in the argument. In this case it will cause the program to apply the command to any file whose name ends with .deb.

5. If required dependencies are not installed on your system already, you will get unmet dependencies errors as dpkg does not automatically take care of them. To correct these errors and finish the installation, run this code to force the installation:

```
apt -f install
```

6. apt will attempt to rectify the situation by either installing the needed dependencies (if they are available from the repos) or removing your .deb files (if the dependencies can not be installed).

NOTE: the command used in Step 5 above reflects the change from the legacy name **apt-get**.

5.5.3 Self-contained packages



[VIDEO: Launchers and Appimages](#)

Appimages, Flatpaks and Snaps are self-contained packages that do not need to be installed in the usual sense. **Be aware that these packages are not tested by Debian or MX Linux, so they may not function as expected.**

1. **Appimages:** simply download, move to /opt (recommended) and make executable by right-click > Permissions.
2. **Flatpaks:** use Package Installer to get apps from [Flathub](#).

3. **Snaps.** Unreliable on MX Linux unless the user has booted into systemd. Workaround and details in the Wiki reference below.

One of the big advantages of self-contained packages is that any extra software they need is included, and so won't impact adversely on software already installed. This also makes them much bigger than the traditional installed packages.

HELP: the [MX/antiX Wiki](#)

5.5.4 CLI methods

It is equally possible to use the command line to install, remove, update, switch repos and generally to manage packages. Instead of launching Synaptic to carry out common tasks.

Table 5: Common commands to manage packages.

Command	Action
apt install packagename	Install a certain package
apt remove packagename	Remove a certain package
apt purge packagename	Completely remove a package (but not configuration/data in /home)
apt autoremove	Clear out leftover packages after a removal
apt update	Refresh the package list from the repos
apt upgrade	Install all available upgrades
apt dist-upgrade	Intelligently handle changing dependencies with new versions of packages

Apt processes and results are displayed in a terminal using the default display that many users find unattractive and hard to read. There exists an alternate display format called **nala** that is installed by default, though it is not used by default due to rare bugs that have arisen during testing. But the colors and organization make for a very user-friendly alternative that many prefer. To enable it, open the file `~/.config/MX-Linux/apt-notifier.conf`, search for “nala” and remove the hash sign at the beginning of the line so that the result reads:

```
use_nala = true
```

5.5.5 More install methods

- Sooner or later some software that you want to install will not be available in the repos and you may need to use other installation methods. These methods include:

- **Blobs.** Sometimes what you want is not actually an installable package but a “blob” or pre-compiled collection of binary data stored as a single entity, especially closed-source. Such blobs are typically located in the directory /opt. Common examples include Firefox, Thunderbird and LibreOffice. **RPM packages:** Some distributions of Linux use the RPM packaging system. RPM packages are similar to deb packages in many ways, and there is a command-line program available from MX Linux to convert RPM packages to debs called **alien**. It does not come installed with MX Linux, but is available from the default repos. After you have installed it on your system, you can use it to install an rpm package with this command (as root): **alien -i packagename.rpm**. That will place a deb file with the same name in the location of the rpm file that you can then install as described above. For more detailed information on alien, see the internet version of its man page in the Links section at the bottom of this page.
- **Source code:** Any open-source program can be compiled from the programmer’s original source code if there is no other option. In ideal circumstances, this is actually a pretty simple operation, but sometimes you can run into errors that require more skill to sort through. Source is usually distributed as a tarball (tar.gz or tar.bz2 file). Your best option is usually to make a package request on the Forum, but see the Links for a tutorial on compiling programs.
- **Miscellaneous:** Many software developers package software in their own custom ways, usually distributed as tarballs or zip files. They may contain setup scripts, ready-to-run binaries, or binary installer programs similar to Windows setup.exe programs. In Linux, the installer often ends in **.bin**. Google Earth, for example, is often distributed this way. When in doubt, consult the installation instructions provided with the software.

5.5.6 Links

[MX/antiX Wiki: Synaptic errors](#)

[MX/antiX Wiki: Installing Software](#)

[MX/antiX Wiki: Compiling](#)

[Debian package management tools](#)

[Debian APT Guide](#)

[Wikipedia: Alien](#)

6 Advanced use

6.1 Windows programs under MX Linux

There are a certain number of applications, both open-source and commercial, that will allow Windows applications to run under MX Linux. They are referred to as *emulators*, meaning that they replicate the functions of Windows on a Linux platform. Many MS Office applications, games and other programs can be run using an emulator with varying degrees of success ranging from near-native speed and functionality to only basic performance.

6.1.1 Open-source

Wine is the primary open-source Windows emulator for MX Linux. It is a kind of compatibility layer for running Windows programs, but does not require Microsoft Windows to run the applications. [Best installed through MX Package Installer](#) (under Misc); if installing with Synaptic, select "winehq-staging" to get all [wine-staging](#) packages. Wine versions are rapidly packaged by the Community Repository members and made available to users, with the latest version coming from the MX Test Repo.

NOTE: In order to run Wine in a Live session, you need to use home persistence (Section 6.6.3).

- [Wine Home Page](#)
- [MX/antiX Wiki: Wine](#)

DOSBox creates a DOS-like environment intended for running MS-DOS-based programs, especially computer games.

- [DOSBox homepage](#)
- [DOSBox Wiki](#)

DOSEMU is software available from the repos that allows DOS to be booted in a virtual machine, making it possible to run Windows 3.1, Word Perfect for DOS, DOOM, etc.

- [DOSEMU Home Page](#)
- [MX/antiX Wiki: DOSEMU](#)




Figure 6-1: Photoshop 5.5 running under Wine.

6.1.2 Commercial

CrossOver Office allows you to install many popular Windows productivity applications, plugins and games in Linux, without needing a Microsoft Operating System license. Supports Microsoft Word, Excel and PowerPoint (up to 2003) particularly well.

- [CrossOver Linux Home Page](#)
- [Wikipedia: Crossover](#)
- [Application Compatibility](#)

Links

- [Wikipedia: Emulator](#)
- [DOS Emulators](#)

6.2 Virtual machines

Virtual machine applications are a class of programs that simulate a virtual computer in memory, allowing you to run any operating system on the machine. It is useful for testing, running non-native applications, and providing users the feeling of having a machine of their own. Many MX Linux users make use of virtual machine software to run Microsoft Windows “in a window” to seamlessly provide access to software written for Windows on their desktop. It is also used for testing to avoid installation.

6.2.1 VirtualBox Setup



VIDEO: [Virtual Box: set up a shared folder \(14.4\)](#)

A number of virtual machine software applications for Linux exist, both open-source and proprietary. MX makes it particularly easy to use **VirtualBox (VB)** so we will focus on that here. For details and the most recent developments, see the Links section below. Here is an overview of the basic steps to set up and run VirtualBox:

- **Installation.** This is best done via the MX Package Installer, where VB appears in the Misc section. This will enable the VB repository, download and install the latest version of VB. The repository will be left enabled, allowing automatic updates via MX Updater.
- **64bit.** VB requires Hardware Virtualization support to run a 64bit guest, the settings for which (if they exist) are located in the UEFI Firmware/BIOS. Details in [the VB Manual](#).
- **Reboot.** It is a good idea to let VB set itself up completely by rebooting after installation.
- **Post-installation.** Check that your user belongs to the vboxusers group. Open MX User Manager > Group Membership tab. Select your username and make sure that 'vboxusers' in the Groups list is ticked. Confirm and exit.
- **Extension Pack.** If you install VB from the MX Package Installer, the Extension Pack will be included automatically. Otherwise, you should download and install it from the Oracle web site (see Links). After the file is downloaded, navigate to it with Thunar and click on the file's icon. The Extension Pack will open VB and install automatically.
- **Location.** Virtual machine files are stored by default in your /home/VirtualBox VMs folder. They can be fairly large and if you have a separate data partition you may consider making the default folder there. Go to File > Preferences > General tab and edit the folder location.




Figure 6-2: Windows 2000 running in VirtualBox.

6.2.2 VirtualBox Use

- **Create a Virtual Machine.** To create a virtual machine start VB, click the New icon on the toolbar. You will need a Windows CD or a Linux ISO (32bit only). Follow the wizard, accepting all suggested settings unless you know better — you can always change them later. If your ISO has PAE, click on System > Options tab and enable it. You may need to increase the memory allocated to the Guest above the minimum default figure, still leaving sufficient memory for your Host OS. For Windows Guests, consider creating a larger virtual HD than the 10GB default – while it is possible to increase the size later, it is not a straightforward process. For Windows 10 or 11 60 Gb is required. Select a Host Drive or Virtual CD/DVD Disk File
- **Select a mount point.** Once the machine is set up, then you can select the mount point to be either the Host Drive or a Virtual CD/DVD Disk File (ISO). Click **Settings > Storage**, and a dialog box will pop up where you will see in the middle a Storage Tree with an IDE Controller and a SATA Controller below it. By clicking on the CD/DVD Drive icon in the Storage Tree, you will see the CD/DVD Drive icon appear in the Attributes section in the right side of the window. Click on the CD/DVD Drive icon in the Attributes section to open a drop-down menu where you can assign the Host Drive or a Virtual CD/DVD disc file (ISO) to be mounted on the CD/DVD Drive. (You can select a different ISO file by clicking on Choose a Virtual CD/DVD disk file and navigating to the file.) Run the machine. The device you selected (ISO or CD/DVD) will be mounted when you start the virtual machine and your OS can be installed.
- **GuestAdditions.** Once your Guest OS is installed, be sure to install VB GuestAdditions by booting into the Guest OS, then clicking Devices > Insert GuestAdditions and pointing toward the ISO that it will automatically locate. This will allow you to enable sharing files between Guest and Host and to adjust your display in various ways so that it suits

your environment and habits. If the app is unable to locate it, you may need to install the package **virtualbox-guest-additions** (done automatically if you used Package Installer).

- **Moving.** The safest way to move or change the settings of an existing Virtual Machine is to clone it: right-click the name of an existing machine > Clone, and fill in the information. To use the new clone, create a new Virtual Machine and in the wizard when you select the Hard Disk, choose "Use existing hard disk" and select the new clone's *.vdi file.
- **Documentation.** Detailed documentation for VB is available through Help on the menu bar or as a PDF from the website.




Figure 6-3: Settings screen in VirtualBox (MX-19.1).

Links

- [Wikipedia: Virtual Machine](#)
- [Wikipedia: Comparison of virtual machine software](#)
- [VirtualBox home page](#)
- [VirtualBox Extension Pack](#)

6.3 Alternate Window Managers




Figure 6-4: MATE running on top of MX-15 Linux, with YouTube Browser open.

A window manager (originally WIMP: Window, Icon, Menu, and Pointing device) in Linux is essentially the component which controls the appearance of [Graphical user interfaces](#) (GUI) and provides the means by which the user can interact with them.

The three MX Linux versions use Xfce, KDE or Fluxbox by definition. But other possibilities exist for users. MX Linux makes it easy to install many popular alternatives through the MX Package Installer, as described below.

- Budgie Desktop, a simple and elegant desktop using GTK+
 - [Budgie Desktop](#)
- Compiz, an OpenGL WM with compositing.
 - [Compix Window Manager](#)
- Gnome Base, a GTK+ based display manager and desktop that provides an ultra-light desktop environment.
 - [Gnome Ultra \(GOULD\), an ultra-light desktop environment](#)
- LXDE is a fast and light desktop environment whose components can be installed separately.
 - [LXDE home page](#)

- MATE is the continuation of GNOME 2 providing an intuitive and attractive desktop environment.
 - [MATE home page](#)
- IceWM is a very light-weight all-in-one desktop environment and stacking window manager.
 - [IceWM home page](#)

Once installed, you can choose the window manager you want from the Session Button in the center of the top bar on the default login screen; log in to as you normally would. If you replace the login manager with another from the repos, make sure you always have at least one available upon reboot.

MORE: [Wikipedia: X Window Managers](#)

6.4 Command Line

Although MX offers a complete set of graphical tools for installing, configuring, and using your system, the command line (also called the console, terminal, BASH, or shell) is still a useful and at times indispensable tool. Here are some common uses:

- Launch a GUI application to see its error output.
- Speed up system administration tasks.
- Configure or install advanced software applications.
- Execute multiple tasks quickly and easily.
- Troubleshoot hardware devices.

The default program to run a terminal in an MX desktop window is **Xfce Terminal**; KDE's default is **Konsole**. Some commands are only recognized for super user (root), while others may vary the output depending on user.

To obtain temporary root permissions, use one of the methods described in Section 4.7.1. You will recognize when Terminal is running with root privileges by looking at the prompt line right before the space where you type. Instead of a \$, you will see a #; in addition, the user name changes to **root** and may be written in red.

NOTE: If you try to run as a regular user a command that requires root privileges such as **iwconfig**, you may receive an error message that the command was not found, see a message box that the program must be run as root, or simply find yourself at the prompt again with no message at all.




Figure 6-5: User now has administrative (root) privileges.

6.4.1 First steps

- For more information on running a terminal for solving system problems, please refer to the topic **Troubleshooting** at the end of this section. Also, it is advisable to make backups of the files you are working on as a root user with the commands **cp** and **mv** (see below).
- Though terminal commands can be fairly complex, understanding the command line is just a matter of putting together simple things. To see how easy it can be, open a terminal and try a few basic commands. This will all make more sense if you do it as a tutorial exercise rather than just reading it. Let's start with a simple command: **ls**, which lists the contents of a directory. The basic command lists the contents of whatever directory you are currently in:

```
ls
```

- That's a useful command, but it's just a few short columns of names printed across the screen. Suppose we want more information on the files in this directory. We can add a **switch** to the command to make it print out more information. A **switch** is a modifier we append to a command to change its behavior. In this case, the switch we want is:

```
ls -l
```

- As you can see on your own screen if you are following along, this switch provides more detailed information (especially about permissions) on the files in any directory.
- Of course, we might want to see the contents of another directory (without going there first). To do this, we add an **argument** to the command, specifying which file we want to look at. An **argument** is a value or reference we add to a command to target its operation. By giving an argument of **/usr/bin/**, for instance, we can list the contents of that directory rather than the one where we currently are.

```
ls -l /usr/bin
```

- There are a lot of files in **/usr/bin/**! It would be nice if we could filter this output so that only entries that contained, say, the word “**fire**” would be listed. We can do this by **piping** the output of the **ls** command into another command, **grep**. The **pipe**, or **|** character, is used to send the output of one command to the input of another. The command **grep** searches for the pattern you give it and returns all matches, so piping the output of the previous command to it filters the output.

```
ls -l /usr/bin | grep fire
```

- Finally, suppose we want these results saved in a text file for use at a later time. When we issue commands, the output is usually directed to the console display; but we can redirect this output somewhere else, such as to a file, using the **>** (redirect) symbol to instruct your computer to make a detailed list of all the files that contain the word “**fire**” in a particular directory (by default your Home directory), and to create a text file containing that list, in this case named “**FilesOfFire**”

```
ls -l /usr/bin | grep fire > FilesOfFire.txt
```

- As you can see, the command line can be used to perform complex tasks very easily by combining simple commands in different ways.

6.4.2 Common commands

Filesystem navigation

Table 6: Filesystem navigation commands.

Command	Comment
cd /usr/share	Changes current directory to the given path: “/usr/share”. With no argument, cd takes you to your home directory.
pwd	Prints the current working directory path
ls	Lists the contents of the current directory. Use the -a switch to show hidden files as well, and the -l switch to show details on all files. Often combined with other terms. lsusb lists all the usb devices, lsmod all the modules, etc.

File management

Table 7: File management commands.

Command	Comment
cp <sourcefile> <destinationfile>	Copy a file to another filename or location. Use the -R switch (“ recursive ”) to copy entire directories.
mv <sourcefile> <destinationfile>	Move a file or directory from one location to another. Also used to rename files or directories and to make a backup: for example before changing a critical file such as xorg.conf you might use this command to move it to something like xorg.conf_bak .
rm <somefile>	Delete a file. Use the -R switch to delete a directory, and the -f switch (“ force ”) if you don’t want to be prompted to confirm each deletion.
cat somefile.txt	Prints the contents of a file on the screen. Only use on text files.
grep	Find a given string of characters in a given piece of text, and print the

	entire line it was on. Usually used with a pipe, e.g. cat somefile.txt grep /somestring/ will display the line from somefile.txt that contains somestring . To find a network usb card, for instance, you could type: lsusb grep -i Network . The grep command is case sensitive by default, so using the -i switch makes it case-insensitive.
dd	Copies anything bit by bit, so can be used for directories, partitions, and whole drives. Basic syntax is dd if=<somefile> of=<some other file>

Symbols

Table 8: Symbols.

Command	Comment
	The pipe symbol used to send the output of one command to the input of another. Some keyboards show two short vertical bars instead
>	The redirect symbol, used to send the output of a command into a file or device. Doubling the redirect symbol will cause the output of a command to be added to an existing file rather than replacing it.
&	Adding the ampersand to the end of a command (with a space before it) causes it to run in the background so that you don't have to wait for it to complete to issue the next command. Double ampersand indicates that the second command should only be run if the first has been successful.

Troubleshooting

For most new Linux users, the command line is mainly used as a troubleshooting tool. Terminal commands give quick, detailed information that can be easily pasted into a forum post, search box, or email when seeking help on the web. It is strongly recommended that you keep this information at hand when asking for help. Being able to refer to your specific hardware configuration will not only speed up your process of obtaining help, but also it will let others offer you more accurate solutions. Here are some common troubleshooting commands (see also Section 3.4.4). Some of them may not output information, or not as much information unless you are logged in as root.

Table 9: Troubleshooting commands.

Command	Comment
lspci	Shows a quick summary of detected internal hardware devices. If a device shows as /unknown/, you usually have a driver issue. The -v switch causes more detailed information to be displayed.
lsusb	Lists attached usb devices.
dmesg	Shows the system log for the current session (i.e. since you last booted). The output is quite long, and usually this is piped through grep , less (similar to most) or tail (to see what happened most recently). For example, to find potential errors related to your network hardware, try dmesg grep -i net .
top	Provides a real-time list of running processes and various statistics about them. Also available as Htop along with a nice graphical version Task Manager .

Accessing documentation for commands.

- Many commands will print out a simple “usage information” message when you use the `--help` or `-h` switch. This can be helpful for quickly recalling the syntax of a command.
For example: `cp --help`
- For more detailed information on how to use a command, consult the command’s man page. By default, man pages are displayed in the terminal’s **less** pager, meaning that only one screenful of the file is displayed at a time. Keep these tricks in mind to navigate the resulting screen:
 - The space bar (or PageDown key) advances the screen.
 - The letter **b** (or PageUp key) moves the screen backward.
 - The letter **q** exits the help document.

Alias

You can create an **alias** (personal command name) for any command, short or long, that you want; most easily done with the tool **MX Bash Config**. Details in the [MX/antiX Wiki](#).

6.4.3 Links

- [BASH Beginners Guide](#)
- [Command Line Basics](#)

6.5 Scripts

A script is a simple text file that can be written directly from a keyboard, and consists of a logically sequenced series of operating system commands. The commands are handled one at a time by a command interpreter which in turn requests services from the operating system. The default command interpreter in MX Linux is **Bash**. The commands must be understandable to Bash, and command lists have been established for programming use. A shell script is the Linux counterpart of batch programs in the Windows world.

Scripts are used throughout the Linux OS and applications that run on it as an economical method of executing multiple commands in an easily created and modified manner. During boot, for instance, many scripts are invoked to start up specific processes such as printing, networking, etc. Scripts are also used for automated processes, system administration, application extensions, user controls, etc. Finally, users of all kinds can employ scripts for their own purposes.

6.5.1 A simple script

Let's do a very simple (and famous) script to get the basic idea.

1. Open your text editor (**Start Menu > Accessories**), and type:

```
#!/bin/bash  
clear  
echo Good morning, world!
```

2. Save that file in your home directory with the name **SimpleScript.sh**
3. Right-click the file name, select Properties, and check “Allow this file to run as a program” on the Permissions tab.
4. Open a terminal and type:

```
sh /home/<username>/SimpleScript.sh
```
5. The line “Good morning, world!” will appear on your screen. This simple script doesn't do very much, but it does establish the principle that a simple text file can be used to send commands to control your system's behavior.

NOTE: All scripts open with a **shebang** as in the beginning of the first line: it is a combination of a hash sign (#), an exclamation point, and the path to the command interpreter. Here, Bash is the interpreter and it is found in the standard location for user applications.

6.5.2 A useful script

Let's look at a useful script for the ordinary user that reduces all the moves involved in backing up multiple sets of files into a single keystroke. The script below relies itself on a system script called **rdiff-backup** that would need to be installed from the repos for the script to work. It copies one directory to another, keeping a record of the differences in a special subdirectory so you can still recover files lost some time ago. (Incidentally, rdiff-backup relies in turn on a script called **diff**.)

In this example, a user named “newbie” wants to set up a script to back up documents, music, mail and pictures from the /home directory to an external drive.

```
1 #!/bin/bash  
2 #  
3 # This Rdiff-Backup script backs up to a second hard drive  
4 # It must be run as root in order to mount the second hard drive  
5  
6 # To restore files, issue the command: cp -a /mnt/sda1/username /home  
7 # To restore, but not overwrite:  
8 # cp -a -i \SpecialChar nobreakdash\SpecialChar nobreakdash"reply=no  
/mnt/sda1/username /home  
9  
10 # Mount the external devices  
11  
12 mount /dev/sdb1
```

```

13 mount /dev/sdb2
14 mount /dev/sdb3
15
16 # Execute the backup
17
18 rdiff-backup /home/newbie/Documents /mnt/sdb2/Documents
19 rdiff-backup /home/newbie/Music /mnt/sdb1/Music
20 rdiff-backup /home/newbie/Mail /mnt/sdb2/Mail
21 rdiff-backup /home/newbie/Pictures /mnt/sdb3/Pictures
22
23 # Unmount the external devices
24
25 umount /dev/sdb1
26 umount /dev/sdb2
27 umount /dev/sdb3

```

Now let's look at this script's components:

- Lines 2-8: a hash or number sign has been placed in front of these lines (called “commenting them out”) to indicate to Bash that they are not part of the sequence of commands to be executed. Their purpose here is to provide anyone who looks at this script with information about such things as the script’s origin, creator, purpose, and license (metadata).
- Line 10: good scripts separate the commands into clearly labeled procedural sections, also in lines 16 and 22.
- Lines 12-14: the three devices to be used for the backup have to first be mounted so they are available to the system.
- Lines 18-21: here bash is told to use the system script rdiff-backup to compare the original directories (sources) with the backup directories (targets), copy over the differences it finds, and keep a record of the changes.
- Lines 25-27: once the backup work is done, the external drives are unmounted from the system.

Anyone who wanted to use such a script would have to carry out a few execution steps:

1. Copy the whole script.
2. Right-click the desktop and select **Create New > Text file...**
3. Give the file a name that makes sense (no spaces, though), and add the “sh” extension so you will recognize it is a script. For this example, you might select **Backup_DocsMusicMailPictures.sh**
4. Open the new text file and paste in the script.

5. Change any names, locations, etc. to what they are on your particular system. In the example above, you may well have different names and/or locations for the directories to be backed up, and different devices where they are supposed to go.
6. Save that script in a place you can easily find it when you need it; let's say you make a new directory in your home called "**scripts**" for it.
7. Right-click the script, select Properties, click on the Permissions tab, and check the box **Is executable** or **Allow this file to run as a program** and click OK.
8. When you are ready to backup, open a terminal and type:

```
sh /home/scripts/Backup_DocsMusicMailPictures.sh
```

HINT: use the tab key to autocomplete the file name after you type the first few letters.

Links

- [Bash Beguinners Guide](#)
- [Linux Shell Scripting Tutorial](#)
- [Linux Commands](#)

6.5.3 Special script types

Some scripts require special software ([scripting language](#)) to run, rather than just launching them in Bash. The most common for regular users are Python scripts, which take the form *.py.

To run them, you need to call python to carry out the execution providing the correct path. If you downloaded "<somefile>.py" to your Desktop, for instance, you could do one of three things:

- Just click on it. MX Linux has a small program called Py-Loader that will launch it using python.
- Open a terminal and type:

```
python ~/Desktop/<somefile>.py
```

- Alternatively, you could open a terminal inside the folder itself, in which case you would type:

```
python ./<somefile>.py
```

Scripting languages are very advanced, and lie outside the scope of this Manual.

6.5.4 Pre-installed user scripts

inxı

, Inxi is a convenient command-line system information script written by a programmer known as “[h2](#)”. Enter `inxı -h` in a terminal to see all the options available, which include an entire range from sensor output to the weather. This is the command running behind **MX Quick System Info**.

MORE: [MX/antiX Wiki](#)

6.5.5 Tips and tricks

- Double-clicking a shell script opens it in the Featherpad editor by default instead of running the script. This is by design as a security measure to prevent accidentally running scripts when you didn't intend to. To change that behavior, click Settings > Mime Type Editor. Locate `x-application/x-shellscript` and change the default application to bash.
- A more advanced editor for programming scripts is [geany](#), installed by default. It is a flexible and powerful [IDE](#)/editor that is lightweight and cross-platform.

6.6 Advanced MX Tools

In addition to the configuration MX Apps discussed in Section 3.2, MX Linux includes utilities for the advanced user available from MX Tools.

6.6.1 Chroot rescue scan (CLI)

A set of commands that allow you to get into a system even if its initrd.img is broken. It also lets you get into multiple systems without rebooting. Details and images in the HELP file.

HELP: [here](#).

6.6.2 Live-usb kernel updater (CLI)



VIDEO: [Change your kernel on an antiX or MX live-USB](#)

WARNING: for use in a Live session only!

This command line application can update the kernel on an MX LiveUSB with any kernel that has been installed. This application will only show in MX Tools when running a Live session.

```

Will use running live system
Distro: MX-16-public-beta1_x64 Metamorphosis 31 October 2016
Found linuxfs file linuxfs in directory /antix
Found:
  1 total live kernel      (4.7.0-0.bpo.1-amd64)
  1 default live kernel    (4.7.0-0.bpo.1-amd64)
  0 old live kernels

  2 total installed kernels
  1 new installed kernel   (4.8.0-5.2-liquorix-amd64)

Only one new installed kernel was found:
Version           Date
4.8.0-5.2-liquorix-amd64 2016-10-30

Please select an action to perform
 1) Update vmlinuz from 4.7.0-0.bpo.1-amd64 (2016-10-31) (default)
 2) Update initrd using file /usr/lib/iso-template/template-initrd.gz
Press <Enter> for the default selection
Use 'q' to quit

```

Figure 6-6: The live-usb kernel updater tool ready to switch to a new kernel.

HELP: [here](#).

6.6.3 MX Live Usb maker

Use to create a Live-USB starting from an ISO file, a live -CD/DVD or an existing live-USB or even a running live system. Although UNetbootin is also available by default (see Section 2.2.3), Live-USB Maker has a number of advantages:

- It is faster.
- Saves state files across reboots.
- LiveUSB-Storage for saving files directly on the live-usb.
- Persistence.
- Remastering.
- Now offers [dd](#) option.
- Live kernel updating.

NOTE: the CLI form (**live-usb-maker**, run as root) offers many advanced options.




Figure 6-7: The live-usb maker tool ready to select the ISO to use.

HELP: [here](#).

6.6.4 Live remaster (MX Snapshot and RemasterCC)



VIDEO: [Make a snapshot of an installed system](#)



VIDEO: [MX-17: make a live-USB with persistence](#)



VIDEO: [MX-17: install apps on a live-USB with persistence](#)

NOTE: this application will only show in MX Tools and be executable when running a Live session.

The primary purpose of live remastering is to make it as safe, easy, and convenient as possible for users to make their own customized version of MX Linux that can be distributed to other computers. The idea is that you use a LiveUSB (or a LiveHD, a "frugal install;" see the [MX/antiX Wiki](#)) to a hard drive partition as the development and testing environment. Add or subtract packages and then when you are ready to remaster, use the GUI or script and reboot. If something goes horribly wrong, simply reboot again with the rollback option and you will boot into the previous environment.

Many users will already be familiar with the tool **MX Snapshot** for remastering(see also an older but still useful app [RemasterCC](#)) The remastered ISO (a “respin”) can be put on a LiveMedium in the usual manner (see Section 2.2) and then installed, if desired, by opening a root terminal and entering the command: *minstall-launcher*.




Figure 6-9: Opening screen of Snapshot.

MX Community members use Live remastering with Snapshot to produce unofficial spins of MX Linux that can be tracked [on the Forum](#).



The Live ISO may be run with what is called “persistence.” Persistence is a hybrid between a LiveMedium and a full install; it allows you to retain any files you install or add during a live session. Programs installed or removed from, and customizations to, the “demo” user files during live persistence will be carried over to the installed system.



6.7 SSH (Secure Shell)

SSH (Secure Shell) is a protocol used to securely log onto remote systems. It is the most common way to access remote Linux and Unix-like computers. MX Linux comes with the main packages necessary to run SSH in active mode, the main one being OpenSSH, a free implementation of the Secure Shell that consists of a whole suite of applications.

- Start or restart the ssh daemon as root with the command:

```
/etc/init.d/ssh start
```

- To start the ssh daemon automatically when the computer starts, click **All Settings > Session and Startup > Application Autostart**. Click the Add button, then in the dialog box insert a name such as StartSSH, a short description if you want, and the command

```
/etc/init.d/ssh start
```

Press OK and you are done. The next time you restart, the SSH daemon will be active.

- KDE users on MX Linux can do the same using **Preferences > Settings > Start & Stop > Automatic Start**.

6.7.1 SSH Troubleshooting

Occasionally, SSH does not work in passive mode, sending a message of denied connection. Then you can try the following:

- Edit as root the file '/etc/ssh/sshd-config'. About line 16 you will find the parameter 'UsePrivilegeSeparation yes'. Change that to

```
UsePrivilegeSeparation no
```
- Add yourself (or the intended users) to the group 'ssh' using MX User Manager or editing as root the file /etc/group.
- Sometimes the certificates can be missing or outdated; an easy way to rebuild them is to run (as root) the command

```
ssh-keygen -A
```

- Check if sshd is running by typing

```
/etc/init.d/ssh status
```

The system should answer '[ok] sshd is running.'

- If you are using a firewall, check that port 22 is not blocked. It must allow IN and OUT traffic.

MORE: [Openssh manual](#)

6.8 Synchronization

[File synchronization](#) (or syncing) allows files in different locations to remain identical. It takes one of two forms:

- one-way (“mirroring”), where one source computer is copied to others but not the reverse.
- two-way, where multiple computers are kept identical.

For instance, MX Linux users find it handy when managing multiple installations for themselves, family members or other groups, thus eliminating the need to update more than once. There is a large amount of [syncing software](#) available, but the following two have tested and proved useful to MX Linux users:

- [unison-gtk](#) (in the repos)
- [FreeFileSync](#)

7 Under the hood

7.1 Introduction

MX Linux ultimately inherits its fundamental design from [Unix](#), an operating system that has been around in various forms since 1970. From that Linux was developed, from which Debian produces its distribution. The base operating system is the topic of this section. Users coming from legacy systems such as MS Windows typically find a lot of unfamiliar concepts, and get frustrated trying to do things the way they are accustomed to doing them.

This section will give you an overview of some basic aspects of MX Linux OS, and how they differ from other systems to help ease your transition.

Links

- [Wikipedia: Unix](#)
- [Linux Home Page](#)
- [Wikipedia Debian](#)

7.2 The file system structure

There are two basic uses of the term “file system”.

- The first is the Operating System’s Filesystem. This refers to the files and their organization that the operating system uses to keep track of all the hardware and software resources it has at its disposal while running.
- The other use of the term file system refers to the Disk Filesystem, designed for the storage and retrieval of files on a data storage device, most commonly a disc drive. The Disk Filesystem is set when the disk partition is first formatted, prior to writing any data on the partition.

The Operating System’s Filesystem

If you open Thunar File Manager and click on File System in the left pane, you will notice a number of directories with names based on the [Unix Filesystem Hierarchy Standard](#).

Name	Size	Type	Date Modified
bin	4.1 kB folder		12/23/2014
boot	4.1 kB folder		01/27/2015
dev	3.3 kB folder		Today
etc	12.3 kB folder		Today
home	4.1 kB folder		01/05/2015
lib	4.1 kB folder		Yesterday
lost+found	16.4 kB folder		12/11/2014
media	4.1 kB folder		Today
mnt	4.1 kB folder		12/11/2014
opt	4.1 kB folder		Yesterday
proc	0 bytes folder		01/28/2015
root	4.1 kB folder		01/08/2015
run	880 bytes folder		Yesterday
sbin	12.3 kB folder		01/28/2015
sda2	4.1 kB folder		12/11/2014
selinux	4.1 kB folder		06/10/2012
sys	0 bytes folder		01/28/2015
tmp	4.1 kB link to var/tmp		Today
usr	4.1 kB folder		01/06/2014
var	4.1 kB folder		12/11/2014

Figure 7-1: The MX filesystem viewed in Thunar.

Here is a simple description of the major directories in MX Linux along with an example of when users commonly work with files in those directories:

- /bin
 - This directory contains binary program files which are used by the system during startup, but which also may be required by user actions once the system is fully up and running.
 - Example: Many basic command-line programs, such as the Bash shell, and utilities like /dd/, /grep/, /ls/, and /mount/ are located here, in addition to programs only used by the OS.
- /boot
 - As you might guess, files that Linux needs to boot are located here. The Linux kernel, the core of the Linux operating system, is kept here, as are bootloaders such as GRUB.
 - Example: no file here is commonly accessed by users.
- /dev
 - In this directory are special files that link to the various input/output devices on the system.
 - Example: no file here is commonly accessed directly by users, except in CLI mounting commands.
- /etc

- This directory contains configuration files for the system as well as application configuration files.
- Example: The file /etc/fstab specifies mount points for additional filesystems on devices, partitions, etc. that can be configured for your optimal use.
- Example: display problems sometimes involve editing the file /etc/X11/xorg.conf.
- /home
 - Here the user's personal directories (data and settings) reside. If there is more than one user, a separate subdirectory is set up for each. No user (except root) can read another user's home directory. The user's directory contains both hidden (where the filename is preceded by a dot) and visible files; hidden files can be revealed by clicking View > Show Hidden Files (or Ctrl-H) in Thunar File Manager.
 - Example: users typically organize their own files at first by using default directories such as Documents, Music, etc.
 - Example: a Firefox profile is located in the hidden directory .mozilla/firefox/
- /lib
 - This directory contains shared object libraries (analogous to Windows DLL's) that are required at boot time. In particular, kernel modules will be found here, under /lib/modules.
 - Example: no file here is commonly accessed by users.
- /media
 - Files for removable media such as CDroms, floppy drives, and USB Memory Sticks are installed here when the media are automounted.
 - Example: After dynamically mounting a peripheral device like a Flash Drive, you may access it here.
- /mnt
 - Physical storage devices must be mounted here before they can be accessed. After drives or partitions are defined in the file /etc/fstab, then their file system is mounted here.
 - Example: Users can access hard drives and their partitions that are mounted here.
- /opt
 - This is the intended location of major third-party application subsystems installed by the user. Some distros also place user-installed programs here.
 - Example: if you install Google Earth, this is where it will be installed. in the /opt subfolders: Also Firefox, Libre Office and Wine are located here,
- /proc

- The location for process and system information.
- Example: no file here is commonly accessed by users.
- /root
 - This is the home directory for the root user (administrator). Note that this is not the same as “/” the file system root.
 - Example: no file here is commonly accessed by users, but files saved while logged in as the root user may be saved here.
- /sbin
 - Programs are installed here if they are required by the system startup scripts but will not normally be run by users, other than root—in other words, system administration utilities.
 - Example: no file here is commonly accessed by users, but this is where files like *modprobe* and *ifconfig* are located.
- /tmp
 - This is the location of temporary files produced by programs—such as compilers—as they run. In general, these are short-term temporary files, of use to a program only while it is running.
 - Example: no file here is commonly accessed by users.
- /usr
 - This directory contains many files for user applications, and is analogous in some ways to the Windows directory “Program Files”.
 - Example: many executable programs (binaries) are located in /usr/bin
 - Example: documentation (/usr/docs) and configuration files, graphics and icons are in /usr/share.
- /var
 - This directory contains files that are constantly changing while Linux is running, e.g. logs, system mail and queued processes.
 - Example: you can look in /var/log/ using MX Quick System Info when trying to determine what happened during a process such as installing a package.

The Disk Filesystem

The disk file system is something about which the average user does not need to be much concerned. The default disk file system used by MX Linux is called ext4, a version of the ext2 file system that is journaled —i.e., it writes changes to a log before enacting them, rendering it more robust. The file system ext4 is set during installation when your Hard Drive is formatted.

By and large, ext4 has more years on its track record than any of its rivals, and combines stability and speed; for these reasons, we do not recommend installing MX Linux onto a different disk file system unless you are well-educated in the differences. However, MX Linux can read and write to many other formatted disk filesystems, and may even be installed on some of them, if for some reason one of them is preferred over ext4.

Links

- [Wikipedia Filesystem](#)
- [Wikipedia. Comparison of filesystems](#)
- [Wikipedia Ext4](#)

7.3 Permissions

MX Linux is an account-based operating system. This means that no program can run without a user account to run under, and any running program is thereby limited by the permissions granted to the user who started it.

NOTE: Much of the security and stability that Linux is known for hinges on the proper use of limited user accounts, and the protection provided by default file and directory permissions. For this reason, you should operate as root only for a procedure that requires it. Never log into MX Linux as root to run the computer for normal activities—running a web browser as root user, for instance, is one of the few ways you could get a virus on a Linux system!

Basic information

The default file permissions structure in Linux is fairly simple, but more than adequate for most situations. For each file or folder, there are three permissions that can be granted, and three entities (owner/creator, group, others/world) to which they are granted. The permissions are:

- Read permission means that data can be read from the file; it also means the file can be copied. If you don't have read permission for a directory you can't even see the names of files listed in it.
- Write permission means that the file or folder can be changed, appended, or deleted. For directories, it specifies whether a user can write to files in the directory.
- Execute permission means whether or not the user can run the file as a script or program. For directories, it determines whether or not the user can enter and make it the current working directory.


- Every file and folder acquires a single user designated as its owner when it is created on the system. (Note that if you move a file from another partition where it has a different owner, it will keep the original owner; but if you copy and paste it, it will be assigned to you.) It also has a single group designated as its group, by default the group to which the owner belongs. The permissions you grant to others affect everyone who isn't the owner or in the owning group.

NOTE: For advanced users, there are additional special attributes beyond read/write/execute that can be set: sticky bit, SUID, and SGID. For more information, see Links section below.

Viewing, setting and changing permissions

There are many tools available in MX Linux to view and manage permissions.

- GUI
 - **Thunar.** To view or change a file's permissions, right-click the file and select Properties. Click the Permissions tab. Here you can set the permissions granted to the owner, group, and others using the pull-down menus. For some files (like scripts , for instance), you need to check the box to make them executable, and for folders you can check a box to limit the deletion of files inside it to the owners.
- **NOTE:** you must be operating as root to change the permission of a file or directory whose owner is root. On bigger folders you MUST refresh your Thunar window or else the permissions will show incorrectly, even though the permissions have actually changed. Just hit F5 to refresh the window or else you will see the original permissions.
- **MX User Manager** is an easy way to change permissions by associating a user with specific groups.
- CLI
 - Internal partitions. By default, the root/superuser password is required to mount internal partitions. To change this behavior, click on **MX Tweak**, Other tab.
 - New external partitions. Formatting a new partition with ext4 requires root permissions, which can lead to unexpected or undesired result of the regular user not being able to write any files to the partition. To change this behavior, consult the [MX/antiX Wiki](#).
 - Manual operations. Although MX User Manager covers most daily situations, sometimes it can be preferable to deal with the command line. Basic permissions are represented by r (read), w (write) and x (execute); a dash indicates no permissions. To view permissions of a file on the command line, type this: `ls -l NameOfFile`. You may need to use the full location of the file (e.g., `/usr/bin/gimp`). The -l switch will cause the file to be listed in long format, displaying its permissions among other information.



A screenshot of a terminal window titled "Terminal". The command entered is "ls -l .asoundrc". The output shows a single file named ".asoundrc" with the following permissions: -rw-r--r--. The file was created by "newbie" on "users" on "Jan 7 14:42".

```
jb@UTRA:~$ ls -l .asoundrc
$ -rw-r--r--  newbie  users  277 Jan  7 14:42 .asoundrc
```

Figure 7-2: Viewing file permissions.

The characters right after the opening dash (indicating it is a regular file) contain the three permissions (read/write/execute) for owner, group and others: 9 characters total. Here it shows that the owner has read and write but not execute (rw-), but the group and others can only read. The owner in this case is specified to be “newbie” who belongs to the group “users”.

If for some reason it was necessary to change the ownership of this file to root using the command line, the user „newbie” would use the chown command like in this example:

```
chown root /home/newbie/.asoundrc
```

For details on using chown, as well as the more detailed chmod, see Links section.

Links

- [MX/antiX Wiki: Permissions](#)
- [File Permissions](#)

7.4 Configuration files

7.4.1 User config files

Files that hold individual user settings (such as high scores for your games, or the layout of your desktop) are stored within a Users home directory, typically as a hidden file or directory, and can only be edited by that user or by root. These personal configuration files are actually less often edited directly than system files because most of the user configuration is done graphically through the applications themselves. When you open an application and click Edit > Preferences, for example, your selections are written to a (usually hidden) configuration file in your user directory. Likewise in Firefox, when you type *about:config* in the address bar, you are editing the hidden configuration files. The Xfce configuration files are stored in `~/.config/`.

7.4.2 System config files

Files that hold system-wide configurations or defaults (such as the file that determines which services automatically launch during boot up) are largely stored in the `/etc/` directory and are only

editable by root. Most of these files are never touched directly by regular users, such as these for instance:

- */etc/rc.d/rc5.d* — Contains files to control runlevel 5 into which MX Linux boots after login.
- */etc/sysconfig/keyboard* — Used to configure the keyboard.
- */etc/network/interfaces* — Defines internet interfaces on the system.

Some configuration files can contain just a few lines, or even be empty, while others may be quite long. The important point is that if you are looking for a configuration file for an application or process, head for the /etc directory and look around. Caution: because these files affect the whole system, 1) back up any file you intend to edit (easiest in Thunar: copy and paste back in, optionally adding BAK at the end of the file name), and 2) be very careful!

7.4.3 Example

Sound problems can be solved with a number of graphical and command-line tools, but once in a while a user needs to edit directly the system-wide configuration file. For many systems, this will be */etc/modprobe.d/snd-hda-intel.conf*. It is a simple file whose top paragraph looks like this:

```
# some chips require that the model be set manually
# for example asus g71 series may need model=g71v
options snd-hda-intel model=auto
```

To try to get sound, you might decide to substitute the exact information about the sound model in place of the word “auto”. To find out your sound model, you could open a terminal and type:

```
lspci | grep Audio
```

The output will depend on the system, but it will take the following form:

```
00:05.0 Audio device: nVidia Corporation MCP61 High Definition Audio (rev a2)
```

Now you can plug that information back into the configuration file:

```
# some chips require that the model be set manually
# for example asus g71 series may need model=g71v
options snd-hda-intel model=nvidia
```

You would save the file, reboot the machine, and hopefully your sound should be working. You could also try more precision by using *model=nvidia mcp61* instead, if the first did not work.

Links

- [Understanding Linux Configuration Files](#)
- [File Permissions](#)

7.5 Runlevels

MX Linux boots up by default using a type of initialization process ([init](#)) called **sysVinit**. After completing the boot process, init executes all startup scripts in a directory specified by the default runlevel (this runlevel is given by the entry for ID in /etc/inittab). MX Linux has 7 runlevels (other processes such as systemd do not use runlevels in the same manner):

Table 10: Runlevels in MX Linux.

Runlevel	Comment
0	Halt the system
1	Single-user mode: provides a root console without logon. Useful if you lose your root password
2	Multiuser with no network
3	Console logon, no X (i.e. no GUI)
4	Not used/custom
5	Default GUI logon
6	Reboot the system

MX Linux defaults to runlevel 5, therefore any init scripts set up in the level 5 config file will run at boot.

Use

Understanding runlevels can be handy. When users have a problem with X Window Manager, for instance, they can not correct it on the default runlevel 5, because X is running on that level. But they can get to runlevel 3 to work on the problem in one of two ways.

- From the Desktop: press Ctrl-Alt-F1 to get out of X. To actually drop to runlevel 3, become root and type *telinit 3*; this will stop all the other services still operating on runlevel 5.
- From the GRUB menu: press **e** (for edit) when you see the GRUB screen. On the subsequent screen, add a space and the number 3 at the end of the line (by default where the word „quiet” is) that starts with “linux” located one above the lowest line (the actual boot command). Press F-10 to boot.

Once the cursor is at a prompt, login with your normal username and password. If necessary, you can also login as “root” and provide the administrative password. Useful commands when you are looking at the prompt on runlevel 3 include:

Table 11: Common runlevel 3 commands.

Command	Comment
runlevel	Returns the number of the runlevel you are on.
halt	Run as root. Shuts the machine down. If that does not work on your system, try poweroff.
reboot	Run as root. Reboots the machine.
<application>	Runs the application, as long as it is not graphical. For instance, you can use the command nano to edit text files, but not leafpad.
Ctrl-Alt-F7	If you used Ctrl-Alt-F1 to drop out from a running desktop but did not continue down to runlevel 3, this command brings you back to your desktop.
telinit 5	Run as root. If you are on runlevel 3, enter this command to get to the login manager lightdm.

Links

- [Wikipedia: Runlevel](#)
- [The Linux Information Project: Runlevel Definition](#)

7.6 The kernel

7.6.1 Introduction

This Section covers common user-centered interactions with the kernel. Consult the Links for other, more technical aspects

7.6.2 Upgrading/Downgrading

Basic steps

Unlike other software on your system, the kernel is not upgraded automatically except below the minor revision level (indicated by the third number in the kernel name). Before you change your current kernel, you would do well to ask yourself some questions:

- Why do I want to upgrade the kernel? Is there a driver I need for new hardware, for instance?
- Should I downgrade the kernel? For example, Core2 Duo processors tend to have odd issues with the default MX-Linux kernel that are solved by switching to the default Debian 4.9 kernel (using MX Package Installer).
- Am I aware that unnecessary changes might bring problems of one kind or another?

MX Linux provides an easy method of upgrading/downgrading the default kernel: open MX Package Installer and click on the “Kernel” category. There you will see a number of kernels that are available to the user. Select the one you want to use (ask on the Forum if unsure) and install it.

Once you check and install the new kernel, reboot and make sure the new kernel is highlighted; if not, click on the options line and select what you want.




Figure 7-3: Kernel options in MX Package Installer for 64bit architecture.

Advanced

Many users will normally turn to **MX Package Installer** for upgrading their kernel, but it can also be done manually. Here is a basic approach for manually upgrading the Linux kernel on your system.

- First, find out what you currently have installed. Open a terminal and enter `inxi S`. For instance, a user of MX-19 64 bit version might see something like this:
`Kernel: 5.8.0-2-amd64 x86_64 bits`
Be sure to write down the name of the kernel from the output of that command.
- Second, select and install a new kernel. Open Synaptic, search on `linux-image` and look for a higher kernel number that matches the architecture (e.g., 686) and processor (e.g., PAE) that you already have, unless you have a good reason to change. Install the one you want or need in the usual manner.
- Third, install the `linux-headers` package that match the new kernel you selected. There are two methods of doing this.
 - Look carefully at the Synaptic entries beginning `linux-headers` and match the kernel.
 - Alternatively, you can install the headers more easily after rebooting into the new kernel by typing the following code in a root terminal:
`apt-get install linux-headers-$(uname -r)`
Headers will also be installed if you use a command such as `m-a prepare`.
- When you reboot, you should automatically boot into the highest available kernel. If it doesn't work, you have the option to return to what you were using: reboot, and when you see the GRUB screen highlight Advanced Options for whatever partition you want to boot into, then select the kernel and press Enter.

7.6.3 Kernel upgrade and drivers

[Dynamic Kernel Module Support \(DKMS\)](#) automatically recompiles all DKMS driver modules when a new kernel version is installed. This allows drivers and devices outside of the mainline kernel to continue working after a Linux kernel upgrade. The exception concerns proprietary graphics drivers (Section 3.3.2).

- NVidia drivers
 - If installed with sgfxi, they must be rebuilt with sgfxi, see Section 6.5.3
 - If installed with the MX Nvidia driver installer or via synaptic/apt-get, the kernel modules may need to be rebuilt. Re-running MX Nvidia driver installer from the menu should offer to reinstall and rebuild the modules. If your reboot gets stuck at a console prompt, become root and enter "`ddm-mx -i nvidia`" to reinstall and rebuild the driver modules.
- Intel drivers
 - You may need to upgrade the driver, depending on the kernel you select for upgrade target.

7.6.4 More options

Other considerations and choices exist with respect to kernels:

- Other pre-rolled kernels exist such as the Liquorix kernel, which is a version of the Zen kernel and is intended to provide a better desktop use experience in terms of responsiveness, even under heavy loads such as during gaming, plus low latency (important for audio work). MX Linux updates the Liquorix kernels frequently, so it is most easily installed through the **MX Package Installer** > MX Test Repo.
- Distros (e.g., MX's sister distro antiX) often roll their own.
- Knowledgeable individuals may compile a specific kernel for particular hardware.

7.6.5 Links

- [Wikipedia: Linux kernel](#)
- [Anatomy of the Linux kernel](#)
- [Linux kernel archives](#)
- [Interactive map of Linux kernel](#)

7.6.6 Kernel panic and recovery

A kernel panic is a relatively rare action taken by the MX Linux system when it detects an internal fatal error from which it can not safely recover. It can be caused by a number of different factors that range from hardware problems to a bug in the system itself. When you get a kernel panic, try rebooting with the MX Linux LiveMedium, which will overcome temporarily any software problems and hopefully allow you to see and offload your data. If that doesn't work, then unplug all unnecessary hardware and try again.

Your first concern is to access and secure your data. Hopefully, you have it backed up somewhere. If not, you can use one of the data recovery programs such **ddrescue** that is supplied with MX Linux. Your last resort is to take your hard drive to a professional recovery business.

There are a number of steps you might have to take to recover a functional MX Linux system once you have your data safe, although ultimately you may have to reinstall using the LiveMedium. Depending on the type of failure, the following steps may be undertaken:

1. Remove packages that broke the system.
2. Reinstall the graphic driver.
3. Reinstall GRUB using **MX Boot Repair**.
4. Reset the root password.
5. Reinstall MX Linux, selecting the check box to keep /home (see Section 2.5) so that your personal configurations will not be lost.

Be sure to ask on the Forum if you have any questions about these procedures.

Links

- [GNU C Library Home Page](#)
- [Ddrescue](#)

7.7 Our positions

7.7.1 Systemd

MX Linux ships with two init systems: SysVinit (default) and [systemd](#). Because the use of the "systemd" as a system and service manager has been controversial, we want to be clear about its function in MX Linux: **systemd is included but not enabled**. You can scan your MX system and discover files bearing *systemd** names, but those simply provide a compatibility hook/entrypoint when needed. MX Linux uses *systemd-shim*, which emulates the *systemd*

functions that are required to run the helpers without actually using the service. This means that SysVinit remains the default init yet MX Linux can use Debian packages that have systemd dependencies such as CUPS and Network Manager. This approach also allows the user to retain the ability to choose his/her preferred init at boot by selecting the systemd entry.

7.7.2 Non-free software

MX Linux is fundamentally user-oriented, so includes a certain amount of [non-free software](#) to assure that the system works out of the box as much as possible. The user can see a list by opening a [console or terminal](#) and typing:

vrms

Examples:

- The “wl” driver (broadcom-sta) and non-free firmware with proprietary components.
- A dedicated tool for installing Nvidia graphic drivers.
-

Our rationale: it is much easier for advanced users to remove these drivers than it is for regular users to install them. And it's particularly difficult to install a driver for a network card without Internet access!

Default list for MX-23:

Non-free packages installed on mx

amd64-microcode	Processor microcode firmware for AMD CPUs
atmel-firmware	Firmware for Atmel at76c50x wireless
networking chips.	
bluez-firmware	Firmware for Bluetooth devices
broadcom-sta-dkms	dkms source for the Broadcom STA Wireless
driver	
firmware-amd-graphics	Binary firmware for AMD/ATI graphics chips
firmware-atheros	Binary firmware for Qualcomm Atheros
wireless cards	
firmware-bnx2	Binary firmware for Broadcom NetXtremeII
firmware-bnx2x	Binary firmware for Broadcom NetXtreme II
10Gb	
firmware-brcm80211	Binary firmware for Broadcom/Cypress
802.11 wireless c	
firmware-intel-sound	Binary firmware for Intel sound DSPs
firmware-ipw2x00	Binary firmware for Intel Pro Wireless
2100, 2200 and	
firmware-iwlwifi	Binary firmware for Intel Wireless cards
firmware-libertas	Binary firmware for Marvell wireless cards
firmware-linux	Binary firmware for various drivers in the
Linux kerne	
firmware-linux-nonfree	Binary firmware for various drivers in the
Linux kerne	
firmware-misc-nonfree	Binary firmware for various drivers in the
Linux kerne	
firmware-myricom	Binary firmware for Myri-10G Ethernet
adapters	
firmware-netxen	Binary firmware for QLogic Intelligent
Ethernet (3000	
firmware-qlogic	Binary firmware for QLogic HBAs
firmware-realtek	Binary firmware for Realtek wired/wifi/BT
adapters	
firmware-sof-signed	Intel SOF firmware - signed
firmware-zd1211	binary firmware for the zd1211rw wireless
driver	
intel-microcode	Processor microcode firmware for Intel
CPUs	
nvidia-detect	NVIDIA GPU detection utility
unrar	Unarchiver for .rar files (non-free
version)	

Reason: Modifications problematic

Contrib packages installed on mx

b43-fwcutter	utility for extracting Broadcom 43xx
firmware	
firmware-b43-installer	firmware installer for the b43 driver
firmware-b43legacy-installer	firmware installer for the b43legacy
driver	
mx-debian-firmware	metapackage that depends on Debian
firmware shipped wi	
virtualbox-guest-utils	x86 virtualization solution - non-X11
guest utilities	
virtualbox-guest-x11	x86 virtualization solution - X11 guest
utilities	

25 non-free packages, 1.4% of 1802 installed packages.

6 contrib packages, 0.3% of 1802 installed packages.

8 Glossary

Linux terms can be confusing and offputting at first, so this Glossary provides a list of the ones used in this Manual to get you started.

- **applet:** A program designed to be executed from within another application. Unlike an application, applets can not be executed directly from the operating system.
- **backend:** Also /back-end./ The backend includes the various components of a program that process the user input entered through the frontend. See also frontend.
- **backport:** Backports are new packages that have been recompiled to run on a released distribution in order to keep it up-to-date.
- **BASH:** The default shell (command-line interpreter) on most Linux systems as well as on Mac OS X, BASH is an acronym for Bourne-again shell.
- **BitTorrent:** Also/bit torrent/ or /torrent./ A method invented by Bram Cohen to distribute large files without the need for a single individual to provide the hardware, hosting and bandwidth resources required.
- **boot block:** An area of a disk outside the MBR having information for loading the operating system that is needed to start a computer.
- **bootloader:** Program that initially chooses an operating system to load after the BIOS has finished initializing the hardware. Extremely small in size. the bootloader's only job is to hand control of the computer over to the Operating System's kernel. Advanced bootloaders offer a menu to choose between several installed operating systems.
- **chainloading:** Also /chain loading./ Instead of directly loading an operating system, a boot manager like GRUB can use chain loading to pass control from itself to a boot sector on a hard disk partition. The target boot sector is loaded in from disk (replacing the boot sector from which the boot manager itself was loaded) and the new boot program is executed. In addition to when it is necessary, as in booting Windows from GRUB, the advantage to chainloading is that each operating system on the hard disk drive —and there could be dozens— can be responsible for having the correct data in its own boot sector. So GRUB residing in the MBR need not be rewritten every time there are any changes. GRUB can simply chainload the relevant information from the boot sector of a given partition whether it has changed or remained the same since the last boot time.
- **cheat code:** Codes can be entered when booting a LiveMedium to change the booting behavior. They are used to pass options to the MX Linux operating system to set parameters for particular environments.
- **command line interface (CLI):** Also known as console, terminal, command prompt, shell, or bash. This is a UNIX-style text interface, which MS-DOS was also designed to resemble. A root console is one where administrative privileges have been acquired after entering the root password.
- **desktop environment:** The software which provides a graphical desktop (windows, icons, desktop, task bar, etc) for an operating system user.
- **disk image:** A file containing the complete contents and structure of a data storage medium or device such as a hard drive or DVD. See also ISO.

- **Distribution:** A Linux Distribution, or **distro**, is a particular packaging of the Linux kernel with various GNU software packages, and different desktops or window managers. Since—unlike the proprietary code used in the Microsoft and Apple OS's—GNU/Linux is Free, Open-Source Software, literally anyone in the world who has the ability can freely build on what has been done and innovate a new vision of a GNU/Linux operating system. MX Linux is a distro based on the Debian Linux family.
- **file system:** Also file system. This refers to the way that files and folders are logically arranged on a computer's storage devices so they may be found by the operating system. It can also refer to the type of formatting on a storage device, such as the common Windows formats NTFS and FAT32, or the Linux formats ext3, ext4 or ReiserFS, and in this sense refers to the method actually used to encode binary data on the Hard Disk Drive, floppy, flash drive, etc.
- **firmware.** The small programs and data structures that internally control the electronic components
- **free-as-in-speech:** The English word “free” has two possible meanings: 1) without cost, and 2) without restrictions. In part of the open-source software community, an analogy used to explain the difference is 1) “free” as in beer vs. 2) “free” as in speech. The word /freeware/ is used universally to refer to software that is simply without cost, whereas the phrase /free software/ loosely refers to software that is more properly called open-source software, licensed under some type of open source license.
- **frontend:** Also front-end. The frontend is the part of a software system that interacts directly with the user. See also backend.
- **GPL:** The GNU General Public License. This is a license under which many open-source applications are released. It specifies that you may view, modify, and redistribute the source code of applications released under it, within certain limits; but that you may not distribute the executable code unless you also distribute the source code to anyone who asks for it.
- **GPT:** A partitioning scheme used by native UEFI
- **Graphical User Interface (GUI):** This refers to a program or operating system interface that uses pictures (icons, windows, etc), as opposed to text (command-line) interfaces.
- **home directory:** One of the 17 top-level directories branching from the root directory in MX Linux, /home contains a subdirectory for every registered user of the system. Within each Users home directory s/he has full read-write privileges. Further, most of the user-specific configuration files for various installed programs are stored in hidden subdirectories within the /home/username/ directory—as is downloaded email. Other downloaded files usually go by default into the home/username/Documents or /home/username/Desktop subdirectories.
- **IMAP:** The Internet Message Access Protocol is a protocol that allows an e-mail client to access a remote mail server. It supports both on-line and off-line modes of operation.
- **interface:** A point of interaction between computer components, often referring to the link between a computer and a network. Examples of interface names in MX Linux include **WLAN** (wireless) and **eth0** (basic wired).
- **IRC:** Internet Relay Chat, an older protocol to render the exchange of text messages easier.

- **ISO:** A disc image following an international standard that contains data files and file system metadata, including boot code, structures, and attributes. This is the normal method for delivering Linux versions such as MX Linux over the Internet. See also **disk image**.
- **kernel:** The layer of software in an operating system that interacts directly with the hardware.
- **LiveCD/DVD:** A bootable compact disc from which one can run an operating system, usually with a complete desktop environment, applications, and essential hardware functionality.
- **LiveMedium:** a general term that includes both LiveCD/DVD and LiveUSB.
- **LiveUSB:** A USB flash drive on which an operating system has been loaded in such a way that it can be booted and run. See LiveDVD.
- **mac address:** a hardware address that uniquely identifies each node (connection point) of a network. It is formed of a string of usually six sets of two-digits or characters, separated by colons.
- **man page:** Short for **manual**, man pages typically contain detailed information about switches, arguments, and sometimes the inner workings of a command. Even GUI programs often have man pages, detailing available command line options. Available in Start menu by typing a # before the name of the man page you want into the Search box, for example: *#pulseaudio*.
- **MBR:** Master Boot Record: the first 512-byte sector of a bootable hard disk drive. Special data written to the MBR enables the computer's BIOS to pass the boot process off to a partition with an installed operating system.
- **md5sum:** A program that calculates and verifies a file's data integrity. The MD5 hash (or checksum) functions as a compact digital fingerprint of a file. It is extremely unlikely that any two non-identical files will have the same MD5 hash. Because almost any change to a file will cause its MD5 hash to also change, the MD5 hash is commonly used to verify the integrity of files.
- **mirror:** Also mirror site. An exact copy of another Internet site, commonly used to provide multiple sources of the same information to supply reliable access to large downloads.
- **module:** Modules are pieces of code that can be loaded and unloaded into the kernel upon demand. They extend the functionality of the kernel without the need to reboot the system.
- **mountpoint:** The place on the root file system where a fixed or removable device is attached (mounted) and accessible as a subdirectory. All computer hardware needs to have a mountpoint in the file system to be usable. Most standard devices such as keyboard, monitor and your primary hard disk drive are mounted automatically at boot.
- **mtp:** MTP stands for Media Transfer Protocol and operates at the file level so that your device doesn't expose its entire storage device. Older Android devices used USB mass storage for transferring files back and forth with a computer.
- **NTFS®:** Microsoft's New Technology File System debuted in 1993 on the Windows NT Operating System, geared to business networks, and with revisions entered the mainstream Windows user's desktop computers in later versions of Windows 2000. It has

been the standard file system since Windows XP was introduced in late 2001.

Unix/Linux-oriented folk say it stands for “Nice Try File System”!

- **open-source:** Software whose source code has been made available to the public under a license that allows individuals to modify and redistribute the source code. In some cases, open-source licenses restrict the distribution of binary executable code.
- **package:** A package is a discrete, non-executable bundle of data that includes instructions for your package manager about installation. A package doesn't always contain a single application; it might contain only part of a large application, several small utilities, font data, graphics, or help files.
- **package manager:** A package manager such as (Synaptic or Gdebi) is a collection of tools to automate the process of installing, upgrading, configuring, and removing software packages.
- **Panel:** The highly configurable panel in Xfce4 appears by default at the left side of the screen and contains navigation icons, open programs and system notifications.
- **Partition Table:** A partition table is a hard disk architecture that expands on the older Master Boot Record (MBR) partitioning scheme using globally unique identifiers (GUID) to enable the existence of more than the original four partitions.
- **persistence:** the ability when running a LiveUSB to retain changes made during a live session.
- **port:** A virtual data connection that can be used by programs to exchange data directly, instead of going through a file or other temporary storage location. Ports have numbers assigned for specific protocols and applications, such as 80 for HTTP, 5190 for AIM, etc.
- **purge:** A command that removes not only the package named, but also any configuration and data files associated with it (though not those in a user's home directory).
- **repo:** A shortened form of repository.
- **repository:** A software repository is an internet storage location from which software packages may be retrieved and installed via a package manager.
- **root:** Root has two common meanings in a UNIX/Linux OS; they are intimately connected, but the distinction is important to understand.
 - The **root file system** is the basic logical structure of all the files the operating system can access, whether programs, processes, pipes or data. It should follow the Unix Filesystem Hierarchy Standard, which specifies where in the hierarchy to locate all types of files.
 - The **root user** who owns the root file system —and so has all permissions necessary to do anything to any file. While it is sometimes necessary to temporarily assume the powers of the /**root user**/ to install or configure programs, it is dangerous and violates the basic security structure of Unix/Linux to log in and operate as /root/ unless absolutely necessary. In a command line interface, a regular user can temporarily become root by issuing the command **su** then entering the root password.
- **runlevel:** A runlevel is a preset operating state on a Unix-like operating system. A system can be booted into any of several runlevels, each of which is represented by a single digit integer. Each runlevel designates a different system configuration and allows access to a

different combination of processes (i.e., instances of executing programs). See Section 7.5.

- **script:** An executable text file, containing commands in an interpreted language. Usually refers to BASH scripts which are used extensively “under the hood” of the Linux operating system, but other languages may be used as well.
- **session:** A login session is the period of activity between a user logging in and logging out of a system. In MX Linux, this typically indicates the lifetime of a particular user “process” (the program code and its current activity) that Xfce invokes.
- **SSD:** A solid-state drive (SSD) is a nonvolatile storage device that stores persistent data on solid-state flash memory.
- **source code:** The human-readable code in which software is written prior to being assembled or compiled into machine-language code.
- **switch:** A switch (also /flag/, /option/ or /parameter/) is a modifier appended to a command to change its behavior. A common example is **-R** (recursive), which tells the computer to carry out the command through all subdirectories.
- **symlink:** Also symbolic link and soft link. A special type of file that points to another file or directory and not to data. It allows the same file to have different names and/or locations.
- **tarball:** An archiving format, like zip, popular on the Linux platform. Unlike zip files, though, tarballs may use one of a number of different compression formats, such as gzip or bzip2. They usually end in file extensions like .tgz, .tar.gz, or .tar.bz2.
Many archive formats are supported in MX with a graphical application called Archive Manager. Usually an archive can be extracted simply by right-clicking on it in Thunar.
- **(U)EFI:** Unified Extensible Firmware Interface is a kind of system firmware used on recent machines. It defines a software interface between an operating system and platform firmware, and represents the successor of old BIOS.
- **Unix:** Also UNIX. The operating system which Linux is modeled after, developed in the late 1960’s at Bell Labs and used primarily for servers and mainframes. Like Linux, Unix has many variations.
- **UUID (Universally Unique IDentifier).** A universally unique identifier (UUID) is a 128-bit number that identifies unique Internet objects or data.
- **window manager:** A component of a desktop environment that provides the basic maximize/minimize/close/move functions for windows in the GUI environment.
Sometimes it can be used as an alternative to a full desktop environment. In MX Linux, the default window manager is Xfce4.
- **X:** Also X11, xorg. The X Window System is a networking and display protocol which provides windowing on bitmap displays. It provides the standard toolkit and protocol to build graphical user interfaces (GUIs) on Unix-like operating systems and OpenVMS, and is supported by almost all other modern operating systems.